

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center /

Multi-input transactions

Updated 4 months ago

Overview

UTXO blockchains support using multiple source addresses in a single transaction. When sending transactions from your Fireblocks workspace, multi-input transactions must originate from a single vault account.

By default, when creating transactions in the Fireblocks Console or API, inputs in a vault account are combined from the smallest to the largest until the requested amount and all fees are accommodated. Create transactions using the Fireblocks Console to automatically combine address inputs that transfer the total amount requested. Create transactions using the Fireblocks API to select address inputs for new transactions either automatically or manually.

When you create transactions using the Fireblocks Console, you can select '**max**' to transfer the total amount of the selected asset using the available inputs.

Input management

UTXO transactions created in Fireblocks are limited to 250 inputs for Bitcoin, Bitcoin Cash, Bitcoin SV, Dash, and Litecoin, 110 inputs for Cardano, and 50 inputs for ZCash. Each blockchain's respective testnet has the same input limitations. However, in testnet workspaces that use the Fireblocks Communal API Co-Signer, all UTXO transactions are limited to 50 inputs. [Learn more about the Fireblocks Communal API Co-Signer.](#)

If you expect a high volume of incoming transactions to separate deposit addresses, you can use the Fireblocks API to manage outgoing UTXO transaction inputs manually. Each method below can be used independently of the others.

Transactions that require more inputs than the allowed amount will fail with the substatus `TOO_MANY_INPUTS`.

Don't see what you're looking for? [Log in](#) for the full Help Center experience

 Fireblocks Help C

/

inputs that can be used for each UTXO transaction. Pass the specific inputs in the [create a new transaction request](#) by specifying the `inputsSelection` parameter within the `extraParameters` object. Use the `ToSpend` object to only use the selected inputs. The transaction will fail if the specified inputs don't cover the requested amount.

Configure input selection

Instead of the default automatic input selection, you can switch your workspace to inverse input selection. With inverse input selection, inputs are automatically selected from largest to smallest amounts up to the maximum allowed inputs for new transactions created in the Fireblocks Console. Contact [Fireblocks Support](#) to change the input selection for your workspace.

Use the default selection method to avoid leaving small amounts of assets spread across multiple deposit addresses.

Use the inverse selection method if you frequently send large UTXO transactions and encounter transactions failing with the `TOO_MANY_INPUTS` substatus.

Periodically consolidate UTXO asset wallets

Use the [maximum spendable amount](#) API endpoint to find the maximum amount available for a single transaction from a vault account. You can then merge a UTXO asset wallet to combine the maximum available inputs into a single address output or send larger transfers as multiple transactions.

To merge multiple UTXO inputs into a single output, create a transaction using the maximum spendable amount and transfer it to an asset wallet in a different vault account in your workspace. This is an on-chain transaction that requires network fees. This allows future transactions to require significantly fewer inputs.

Consolidate UTXO inputs in the Fireblocks Console

For example, if a vault account has 600 Bitcoin deposit addresses, each with \$2, then the largest transaction available is \$500 even though the total amount held in the vault account is \$1200. Using the Fireblocks Console, you can create a \$500 transaction from this vault account to another vault account that will automatically select the first 250 inputs. The

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

whitelist a vault deposit address or use the one-time address feature. The deposit address can be in the same vault account as the source or a specific deposit address in a different vault account.

Consolidate UTXO inputs in the Fireblocks API

Find the [maximum spendable amount](#) in a single transaction. Then create a transaction using the [create a new transaction](#) endpoint and include the `extraParameters` field to identify the addresses in [InputsSelection](#). Send the transaction to a single deposit address in your Vault.

Was this article helpful?

Yes

No

ON THIS PAGE

Overview

Input management

Manually select inputs for each transaction

Configure input selection

Periodically consolidate UTXO asset wallets

Related Articles

-  [Dismiss a transaction card](#)
-  [Reviewing transaction details \(Recent Activity and Transaction History\)](#)
-  [Boost or drop a stuck EVM-based transaction](#)
-  [Retry a transaction](#)
-  [Boost a stuck UTXO transaction](#)
-  [Multi-destination UTXO transactions](#)

Don't see what you're looking for? Log in for the full Help Center experience



Fireblocks Help Center



fireblocks.com

fireblocks.com

Status

API Docs

Console

info@fireblocks.com



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)