

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center /

Fireblocks Help Center

Backup & Recovery

Native workspace key backup solution

Withdrawing your assets

Warning

Whenever a new version of the [Recovery Utility](#) is available, we recommend checking this guide to ensure you follow the correct withdrawal procedure.

Overview

After you reconstruct your private key material, you can use the Recovery Utility to withdraw your assets from your vault accounts.

Before you begin

Make sure you have the following set up:

- An offline machine with a camera (to reconstruct the private key material and initiate transactions)
- An online machine with a camera (to gather information for transaction creation and to broadcast the transaction)

Additionally, both offline and online machines should have the recovery binary executed.

Creating a withdrawal

To create a withdrawal transaction, there are three options:

Option 1: Fireblocks native Recovery Utility

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center


/

4. Select **Create Transaction**. A QR code appears, but don't do anything with this yet.

Note

If you are withdrawing BTC, BTC_TEST, DOGE, LTC, ZEC, or DASH, you must first configure a Blockchair API key. See the [Blockchair API Key Configuration](#) section below.

5. On the *online* machine, open the **Recovery Relay** and select **Scan QR Code**. Now scan the QR code from Step 4 with the *online* machine's camera.



6. A Withdraw asset dialog opens. Complete the following fields:
 - a. **From Address:** Select the address from which you want to withdraw funds.
 - b. **Memo or Tag field (when applicable):** This field only appears when the associated blockchain requires a memo or tag for transactions. Enter the memo or tag for the address you selected.
 - c. **Additional fields:** Depending on the blockchain, additional fields may appear on the dialog. These can include requests for a node address, an API key, and more. Enter this information when these fields appear.
7. After you finish Step 6, select **Prepare Transaction** on the *online* machine. A QR code appears. Use the *offline* machine's camera to scan the QR code.
8. On the *offline* machine, review the transaction's details. If everything appears correct, select **Approve & Sign Transaction**. A QR code appears. Use the *online* machine to scan the QR code.

Don't see what you're looking for? Log in for the full Help Center experience

Fireblocks Fireblocks Help Center

/

Note:

Native withdrawal relies on third-party RPC providers configured in the Recovery Utility. If an RPC provider is unavailable or experiencing issues, the native withdrawal may not work. In such cases, you can use Option 2 or Option 3 as alternatives.

Option 2: Fireblocks native Recovery Utility - Raw Signing

You can withdraw your assets using the raw signing method through the Recovery Utility. This method requires you to serialize a transaction before submitting it for signing. After the tool produces the signature, you will need to embed the signature into the transaction in order to broadcast it to the network.

For detailed instructions on using raw signing, see the [Using the Recovery Tool for raw signing](#) article.

Option 3: Exporting keys to an external wallet

This option can be used if the Recovery Utility does not support a desired asset or functionality. However, it is generally not recommended due to the security risks of transferring a private key to an online device, which could expose your key. Only ECDSA assets such as BTC and ETH work with this option, whereas EdDSA assets such as SOL and TON won't work.

1. On the *offline* machine, [recover your private key material](#).
2. After you finish the recovery procedure, [reconstruct your workspace](#).
3. In the Recovery Utility, navigate to your desired vault account and asset from which you want to export your private key.
4. Select **Show keys**.



5. Copy and paste the Wallet Import Format (WIF) private key onto a USB drive or other storage device.

Don't see what you're looking for? Log in for the full Help Center experience



6. Move the WIF private key to an online device and load it to a third-party wallet.
7. Using the third-party wallet, import your private keys by following [this article](#) (note that steps 1 to 3 are only used for the old recovery tool).

Important

We recommend moving any funds associated with this address to a new address where the private keys have not been exposed. Any exposed private keys uploaded to a third-party wallet are at a higher risk of attacks.

Blockchair API Key Configuration

Starting with Recovery Utility version 1.8.2, an API key is required for Blockchair API access. If you are withdrawing any of the following assets, you must acquire and configure a Blockchair API key before proceeding with the withdrawal:

- BTC
- BTC_TEST
- DOGE
- LTC
- ZEC
- DASH


Don't see what you're looking for? Log in for the full Help Center experience

Fireblocks Fireblocks Help Center

/

3. Select **Settings**.


4. In the list of assets, locate the asset you're withdrawing.



5. Click the key icon next to the URL.


6. Enter your Blockchair API key.

Don't see what you're looking for? Log in for the full Help Center experience



Once configured, you can proceed with the standard withdrawal process.

Note: If you don't add a valid API key, you will see an error that says "Could not get balance" as follows:



Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

Was this article helpful?

Yes

No

ON THIS PAGE

Overview

Before you begin

Creating a withdrawal

Blockchair API Key Configuration

Related Articles

-  MPC-CMP rollout for Fireblocks mobile application
-  Reset an Admin or Signer's Recovery Passphrase
-  Settings & Configuration
-  Verifying a recovery package
-  Recovering private key material
-  Recovery Passphrase
-  Travel Rule compliance for exchange transactions
-  Reconstructing your workspace
-  Mobile Key Share Backup and Recovery
-  Generating a Workspace Key Backup Package - Fireblocks Recovery Utility
-  How to perform Key Backup and Recovery
-  Disaster Recovery Service: CoinCover
-  Third-Party Disaster Recovery Services
-  Native Workspace Key Backup and Recovery with Python Script
-  About Backup and Recovery
-  Mobile Key Share Backup and Recovery with a Third-Party DRS

Don't see what you're looking for? Log in for the full Help Center experience



Fireblocks Help Center



[fireblocks.com](#)

[Status](#)

[API Docs](#)

[Console](#)

[info@fireblocks.com](#)



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)