

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center 

Fireblocks Help Center

Tokenization

Token utility contract templates

Operating the Allowlist contract

Overview

The Allowlist token utility contract can be used to control who explicitly can interact with your Fireblocks token contracts. This contract works seamlessly with Fireblocks ERC-20F, ERC-721F, and ERC-1155F token contracts and uses a registry of authorized addresses to enforce access control.

- The Allowlist must be used with a deployed Fireblocks token contract, not third-party contracts like those created by BitBond, OpenZeppelin, etc.
- Multiple Fireblocks token contracts can work with the same Allowlist.
- A token contract can only be connected to a single Allowlist or Denylist at a given time. You can change which Allowlist or Denylist is connected as required.

The Allowlist is upgradeable using the UUPS proxy pattern. This consists of a Fireblocks-deployed *Logic* contract and a customer-deployed *Proxy* contract that points to the *Logic* contract. [Learn more](#).

Deploying

When deploying an Allowlist contract, make sure to enter the addresses, such as a Fireblocks vault account, you want for the Default Admin, Pauser, and Upgrader roles.

[Learn more about smart contract roles](#).

Roles for managing the Allowlist

The following smart contract roles can be assigned to help manage the Allowlist.

Don't see what you're looking for? Log in for the full Help Center experience

Fireblocks Fireblocks Help Center

/

...can add, remove, or change permissions by adding and removing addresses in the Allowlist

Updating the Allowlist

After deploying the Allowlist, you can add and remove addresses to and from the Allowlist as needed.

First, you need to grant someone the Access List Admin role.

1. On the Tokenization page, select **More Actions (...)** > **Manage contract** corresponding to the relevant smart contract.
2. Copy the Access List Admin role hash from the Read functions.
3. Select **Write** and use the grantRole function.
4. Enter the hash for the Access List Admin role you copied in step 2, and then enter the address that should be granted the role.
5. Select **Submit**.

At this point, the user granted the Access List Admin role can add and remove addresses to and from the Allowlist.

Adding addresses

1. On the Tokenization page, select **Manage contract**  for the Allowlist contract.
2. Then select **Write** and use the accessListAdd function.
3. Enter the addresses to add to the Allowlist. You must select the Enter key after each address you add.
4. Select **Submit**.

Removing addresses

1. On the Tokenization page, select **Manage contract**  for the Allowlist contract.
2. Then select **Write** and use the accessListRemove function.
3. Enter the address you want to remove from the Allowlist.
4. Select **Submit**.

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

You can connect the Allowlist to one or more of your deployed Fireblocks token contracts, such as ERC-20F, ERC-721F, and ERC-1155F.

First, you need to grant the Contract Admin role for your Fireblocks token contract to a user's address.

1. In the Fireblocks Console, go to the Tokenization page and select **More Actions (...)** > **Manage contract** for the token contract you want the Allowlist connected to.
2. Copy the Contract Admin role hash from the Read functions.
3. Then select **Write** and use the grantRole function.
4. Enter the hash for the Contract Admin role you copied in step 2, and then enter the address that should be granted the role.
5. Select **Submit**.

At this point, the user granted the Contract Admin role can access the token contract and connect the Allowlist.

1. On the Tokenization page, copy the address to the Allowlist.
2. Select **More Actions (...)** > **Manage contract** corresponding to the relevant token contract.
3. Then select **Write** and use the accessRegistryUpdate() function.
4. Enter the Allowlist's address in the **Access registry** field.
5. Select **Submit**.

Was this article helpful?

Yes

No

ON THIS PAGE

Overview

Deploying

Roles for managing the Allowlist

Updating the Allowlist

Connecting the Allowlist to your Fireblocks token contracts

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center





[fireblocks.com](#)

[Status](#)

[API Docs](#)

[Console](#)

[info@fireblocks.com](#)



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)