Project One --- JIFFIES

This assignment will involve designing two kernel modules:

- Design a kernel module that creates a /proc file named /proc/jiffies that reports the current value of jiffies when the /proc/jiffies file is read, such as with the command cat /proc/jiffies
 - Be sure to remove /proc/jiffies when the module is removed.
- 2. Design a kernel module that creates a proc file named /proc/seconds that reports the number of elapsed seconds since the kernel module was loaded. This will involve using the value of jiffies as well as the HZ rate. When a user enters the command

```
cat /proc/seconds
```

your kernel module will report the number of seconds that have elapsed since the kernel module was first loaded. Be sure to remove /proc/seconds when the module is removed.

See detailed instructions below...

I. Kernel Modules Overview

The first part of this project involves following a series of steps for creating and inserting a module into the Linux kernel.

You can list all kernel modules that are currently loaded by entering the command

lsmod

This command will list the current kernel modules in three columns; name, size, and where the module is being used.

```
#include <linux/init.h>
#include <linux/kernel.h>
#include <linux/module.h>
/* This function is called when the module is loaded. */
int simple init(void) {
    printk(KERN INFO "Loading Kernel Module\n");
    return 0;
}
/* This function is called when the module is removed. */
void simple exit(void) {
    printk(KERN INFO "Removing Kernel Module\n");
}
/* Macros for registering module entry and exit points. */
module init(simple init);
module exit(simple exit);
MODULE LICENSE("GPL");
MODULE DESCRIPTION("Simple Module");
MODULE AUTHOR ("SGG");
```

Figure 2.21 Kernel module simple.c.

The program in Figure 2.21 (named simple.c and available with the source code for this text) illustrates a very basic kernel module that prints appropriate messages when it is loaded and unloaded.

The function simple init() is the **module entry point**, which represents the function that is invoked when the module is

loaded into the kernel. Similarly, the simple exit() function is the **module exit point** — the function that is called when the module is removed from the kernel.

The module entry point function must return an integer value, with 0 representing success and any other value representing failure. The module exit_point function returns void. Neither the module entry point nor the module exit_point is passed any parameters. The two following macros are used for registering the module entry and exit points with the kernel:

```
module init(simple init)
module exit(simple exit)
```

Notice in the figure how the module entry and exit point functions make calls to the printk() function.printk() is the kernel equivalent of printf(), but its output is sent to a kernel log buffer whose contents can be read by the dmesg command. One difference between printf() and printk() is that printk() allows us to specify a priority flag, whose values are given in the inux/printk.h> include file. In this instance, the priority is KERN_INFO, which is defined as an *informational* message.

The final lines—MODULE LICENSE(), MODULE DESCRIPTION(), and MODULE AUTHOR()—represent details regarding the software license, description of the module, and author. For our purposes, we do not require this information, but we include it because it is standard practice in developing kernel modules.

This kernel module simple.c is compiled using the Makefile accompanying the source code with this project. To compile the module, enter the following on the command line:

make

The compilation produces several files. The file simple.ko represents the compiled kernel module. The following step illustrates inserting this module into the Linux kernel.

II. Loading and Removing Kernel Modules

Kernel modules are loaded using the insmod command, which is run as follows:

```
sudo insmod simple.ko
```

To check whether the module has loaded, enter the 1smod command and search for the module simple. Recall that the module entry point is invoked when the module is inserted into the kernel. To check the contents of this message in the kernel log buffer, enter the command

dmesg

You should see the message "Loading Module." Removing the kernel module involves invoking the rmmod command (notice that the .ko suffix is unnecessary):

```
sudo rmmod simple
```

Be sure to check with the dmesg command to ensure the module has been removed.

Because the kernel log buffer can fill up quickly, it often makes sense to clear the buffer periodically. This can be accomplished as follows:

```
sudo dmesg -c
```

Proceed through the steps described above to create the kernel module and to load and unload the module. Be sure to check the contents of the kernel log buffer using dmesg to ensure that you have followed the steps properly.

As kernel modules are running within the kernel, it is possible to obtain values and call functions that are available only in the kernel and not to regular user applications. For example, the Linux include file linux/hash.h> defines several hashing functions for use within the kernel. This file also defines the constant value GOLDEN_RATIO_PRIME (which is defined as an unsigned long). This value can be printed out as follows:

```
printk(KERN_INFO "%lu\n", GOLDEN_RATIO_PRIME);
```

As another example, the include file inux/gcd.h> defines the following function

```
unsigned long gcd(unsigned long a, unsigned b);
```

which returns the greatest common divisor of the parameters a and b.

Once you are able to correctly load and unload your module, complete the following additional steps:

- 1. Print out the value of GOLDEN RATIO PRIME in the simple init() function.
- 2. Print out the greatest common divisor of 3,300 and 24 in the simple exit() function.

As compiler errors are not often helpful when performing kernel development, it is important to compile your program often by running make regularly. Be sure to load and remove the kernel module and check the kernel log buffer using dmesg to ensure that your changes to simple.c are working properly.

In Section 1.4.3, we described the role of the timer as well as the timer interrupt handler. In Linux, the rate at which the timer ticks (the **tick rate**) is the value HZ defined in <asm/param.h>. The value of HZ determines the frequency of the timer interrupt, and its value varies by machine type and architecture. For example, if the value of HZ is 100, a timer interrupt occurs 100 times per second, or every 10 milliseconds. Additionally, the kernel keeps track of the global variable jiffies, which maintains the number of timer interrupts that have occurred since the system was booted. The jiffies variable is declared in the file linux/jiffies.h>.

- 1. Print out the values of jiffies and HZ in the simple init() function.
- 2. Print out the value of jiffies in the simple exit() function.

Before proceeding to the next set of exercises, consider how you can use the different values of jiffies in simple_init() and simple_exit() to determine the number of seconds that have elapsed since the time the kernel module was loaded and then removed.

III. The /proc File System

The /proc file system is a "pseudo" file system that exists only in kernel memory and is used primarily for querying various kernel and per-process statistics.

```
#include <linux/init.h>
#include <linux/kernel.h>
#include <linux/module.h>
#include <linux/proc_fs.h>
#include <asm/uaccess.h>
#define BUFFER SIZE 128
#define PROC NAME "hello"
```

```
ssize t proc read(struct file *file, char __user *usr_buf,
                  size_t count, loff_t *pos);
static struct file operations proc ops = {
    .owner = THIS MODULE,
    .read = pro c read,
};
/* This function is called when the module is loaded. */
int proc init(void) {
    /* creates the /proc/hello entry */
   proc create(PROC NAME, 0666, NULL, &proc_ops);
   return 0;
}
/* This function is called when the module is removed. */
void proc exit(void) {
    /* removes the /proc/hello entry */
   remove proc entry(PROC NAME, NULL);
}
```

Figure 2.22 The /proc file-system kernel module, Part 1

This exercise involves designing kernel modules that create additional entries in the /proc file system involving both kernel statistics and information related to specific processes. The entire program is included in Figure 2.22 and Figure 2.23. We begin by describing how to create a new entry in the /proc file system. The following program example (named hello.c and available with the source code for this text) creates a /proc entry named /proc/hello. If a user enters the command

```
cat /proc/hello
the infamous Hello World message is returned.
/* This function is called each time /proc/hello is read */
ssize t proc read(struct file *file, char user *usr buf, size t count, loff t *pos) {
    int rv = 0;
    char buffer[BUFFER SIZE];
    static int completed = 0;
    if (completed) {
        completed = 0;
        return 0;
    completed = 1;
    rv = sprintf(buffer, "Hello World\n");
    /* copies kernel space buffer to user space usr buf */
    copy to user(usr_buf, buffer, rv);
    return rv;
}
module init(proc init);
module exit(proc exit);
MODULE LICENSE("GPL");
MODULE DESCRIPTION("Hello Module");
MODULE AUTHOR("SGG");
```

Figure 2.23 The /proc file system kernel module, Part 2

In the module entry point proc_init(), we create the new /proc/hello entry using the proc_create() function. This function is passed proc_ops, which contains a reference to a struct file operations. This struct initializes the .owner and .read members. The value of .read is the name of the function proc_read() that is to be called whenever /proc/hello is read.

Examining this proc_read() function, we see that the string "Hello World\n" is written to the variable buffer where buffer exists in kernel memory. Since /proc/hello can be accessed from user space, we must copy the contents of buffer to user space using the kernel function copy_to_user(). This function copies the contents of kernel memory buffer to the variable usr buf, which exists in user space.

Each time the /proc/hello file is read, the proc_read() function is called repeatedly until it returns 0, so there must be logic to ensure that this function returns 0 once it has collected the data (in this case, the string "Hello World\n") that is to go into the corresponding /proc/hello file.

Finally, notice that the /proc/hello file is removed in the module exit point proc_exit() using the function remove_proc_entry().

cpsc 351-Project One Jiffies Project due 24 Mar 2021 at 2359			
Your name: Evan Delasota			
Repository: https://github.com/Evan-delasota/jiffies-project			
erify each of the following items and check the correct column. Incorrectly marked items will incur a 5% penalty.			

Completed	Not Completed	Jiffies Project
		Modify the hello.c project, and confirm that it correctly makes (using make), and displays the GOLDEN_PRIME_RATIO on module load, and the gcd of 3300 and 24 on module removal.
		Create a kernel module that creates a <i>proc file named proc</i> /jiffies, and that reports the current value of jiffies when the <i>proc</i> /jiffies file is read, such as with the command: cat proc / jiffies
		Be sure /proc/jiffies is removed when the module is removed
		Save the output of /proc/jiffies, and submit it with your project
		Create a kernel module that creates a proc fie named /proc/seconds, that reports the number of elapsed seconds since the kernel module was loaded, such as with the command cat proc/seconds
		Your calculation involves jiffies and HZ, and includes the header files needed to compile and run your code
		Be sure /proc/seconds is removed when the module is removed
		Save the output of reading from /proc/seconds, and submit it with your project
Comments		