OWNER MODULE – MOBILE APPLICATION

Precondition: The owner account has been created during system setup.

Postcondition: The owner is signed in and the Owner Dashboard is displayed with owner-level access.

No.	Epic	Persona (User)	I want to (action)	So that (benefit)
OM-LOG-01	Owner Login (Mobile)	As the owner	I want to log in to the mobile app with my owner credentials	I can monitor sales and inventory of all three branches from my phone

Precondition: The owner is logged in.

Postcondition: The selected owner screen is open.

No.	Epic	Persona (User)	I want to (action)	So that (benefit)
OM-NAV-01	Owner Navigation (Bottom Bar and More Menu)	As the owner	I want a bottom navigation bar and a More menu that give access to every owner function	I can reach any report or list within one or two taps

OWNER MODULE – MOBILE APPLICATION

Precondition: The owner is logged in. Sales and inventory records exist.

Postcondition: The dashboard shows the latest saved information of all branches.

No.	Epic	Persona (User)	I want to (action)	So that (benefit)
OM-DASH-01	Owner Dashboard (Mobile)	As the owner	I want a dashboard showing sales and inventory conditions across all three branches	I can monitor the business even when I am away from the stores

Precondition: The owner is logged in. Completed sales have been recorded by the branches.

Postcondition: The sales summary for the selected period and branch is displayed read-only.

No.	Epic	Persona (User)	I want to (action)	So that (benefit)

OWNER MODULE – MOBILE APPLICATION

OM-SLS-01	Sales Summaries	As the owner	I want to review daily, weekly, and monthly recorded sales by branch	I can see how each branch and product is performing

Precondition: The owner taps a transaction in Sales Summaries or Recent Activities.

Postcondition: The transaction details are displayed read-only.

No.	Epic	Persona (User)	I want to (action)	So that (benefit)
OM-SLS-02	Sales Transaction Details	As the owner	I want to open a sale to see its items and payment information	I can verify individual transactions

OWNER MODULE – MOBILE APPLICATION

Precondition: The owner is logged in. Inventory records exist for the three branches.

Postcondition: The selected branch's expected inventory is displayed read-only.

No.	Epic	Persona (User)	I want to (action)	So that (benefit)
OM-INV-01	Multi-Branch Inventory Monitoring (Mobile)	As the owner	I want to view the expected inventory of each branch	I can quickly check the stock situation of an individual branch

Precondition: The owner opened Branch Comparison from the Inventory tab.

Postcondition: The quantities of the selected ingredient in all three branches are displayed.

No.	Epic	Persona (User)	I want to (action)	So that (benefit)
OM-INV-02	Branch Inventory Comparison (Mobile)	As the owner	I want to compare one ingredient across the three branches	I can see which branch has too little or too much and decide where to restock

OWNER MODULE – MOBILE APPLICATION

Precondition: The owner is logged in. Minimum stock levels and expiration alert periods are configured.

Postcondition: The current alerts of all branches are displayed.

No.	Epic	Persona (User)	I want to (action)	So that (benefit)
OM-ALR-01	Low-Stock and Expiration Alerts (Mobile)	As the owner	I want to see low-stock and expiration alerts from all three branches	I can decide on replenishment and prevent spoilage

Precondition: The owner is logged in. Branch staff have submitted discrepancies.

Postcondition: The discrepancy list is displayed.

No.	Epic	Persona (User)	I want to (action)	So that (benefit)

OWNER MODULE – MOBILE APPLICATION

OM-DSC-01	Inventory Discrepancy Review List (Mobile)	As the owner	I want to see the discrepancies submitted by branch staff	I know which count differences need my review

Precondition: The owner opened a discrepancy that is “Pending Review”.

Postcondition: The authorized adjustment is saved and the discrepancy status is “Adjusted”.

No.	Epic	Persona (User)	I want to (action)	So that (benefit)
OM-DSC-02	Discrepancy Details and Authorized Adjustment (Mobile)	As the owner	I want to review a discrepancy and authorize an adjustment when necessary	the expected inventory is corrected only with my approval and with a full record

OWNER MODULE – MOBILE APPLICATION

Precondition: The owner is logged in. Records exist for the branches.

Postcondition: The selected record type is displayed read-only.

No.	Epic	Persona (User)	I want to (action)	So that (benefit)
OM-REC-01	Sales and Inventory Records (Mobile)	As the owner	I want to browse historical sales and inventory records of all branches, separated by type	I can keep track of business and inventory activity even when I am away

Precondition: The owner is logged in.

Postcondition: The permitted account information is displayed.

No.	Epic	Persona (User)	I want to (action)	So that (benefit)
OM-PRF-01	Owner Profile (Mobile)	As the owner	I want to view my permitted account information	I can confirm I am signed in with the owner account

OWNER MODULE – MOBILE APPLICATION

Precondition: The owner is logged in.

Postcondition: The session ends and the Login screen is displayed.

No.	Epic	Persona (User)	I want to (action)	So that (benefit)
OM-LGO-01	Owner Logout (Mobile)	As the owner	I want to log out of the mobile app	my business data stays protected if my phone is used by someone else

OWNER MOD

Precondition: T

Postcondition:

No.	Acceptance Criteria (System Requirements)
OM-LOG-01	1. The Login screen shows the TakoSync logo, an “ID / Email” field, a “Password” field with a Show/Hide (eye) icon, and a full-width “Log In” button. 2. The Password field masks characters by default; tapping the eye icon shows or masks the password (e.g., “Owner#2026”). 3. The owner enters the ID or email (e.g., OWNER-GELO or owner@gelos.test) and password and taps “Log In”; the button shows a loading indicator and is disabled until the response arrives. 4. If the ID/Email or Password is blank, login is blocked, the empty field is outlined in red, and “Please enter your ID or email.” or “Please enter your password.” is shown. 5. If the credentials are invalid, the system shows the generic message “Invalid ID/email or password. Please try again.” without revealing which entry was wrong. 6. If a branch staff account (e.g., BR1-STAFF) is entered, the system does not grant owner-level access and shows “This account does not have owner access.” 7. If the credentials are valid, the system opens an authenticated session, verifies the owner role, and grants access to all three branches. 8. After successful login, the system opens the Owner Dashboard with the bottom navigation visible. 9. Credentials are sent over a secure connection (HTTPS/TLS) and passwords are never stored or displayed as plain text except while the Show/Hide icon is on.
	Passed
	Failed
	Total
	Rate (%)

Precondition: T

Postcondition:

No.	Acceptance Criteria (System Requirements)
OM-NAV-01	1. A bottom navigation bar with five tabs — Dashboard, Sales, Inventory, Alerts, More — is shown on all main owner screens; each tab has an icon and label. 2. The active tab is highlighted; tapping a tab opens its screen and keeps the previously chosen filters of that tab. 3. The Alerts tab shows a numeric badge with the number of active low-stock and expiration alerts of all branches; the badge is hidden at 0. 4. Tapping “More” opens a list with three entries: Discrepancies (with a badge for items “Pending Review”), Records, and Profile and Logout. 5. Detail screens (Transaction Details, Branch Comparison, Discrepancy Details, Record Details) hide the bottom bar, show a back arrow, and return to the screen the owner came from. 6. The device Back button on a main tab other than Dashboard returns to the Dashboard; on the Dashboard it shows the message “Press

OWNER MOD

	Passed
	Failed
	Total
	Rate (%)

Precondition: T

Postcondition:

No.	Acceptance Criteria (System Requirements)
OM-DASH-01	1. After login, the Owner Dashboard opens by default with a top bar showing the business name and a refresh icon. 2. A “Total Recorded Sales” card shows the combined sales of all branches (e.g., ₱12,450) with a period selector (Today, This Week, This Month) that updates the amount when changed. 3. Below it, three branch sales cards (Branch 1 ₱4,820 · Branch 2 ₱3,990 · Branch 3 ₱3,640) are shown side by side or in a horizontal scroll; tapping a card opens Sales Summaries filtered to that branch. 4. An “Inventory Status” summary shows the number of items that are Normal, Low Stock, and Out of Stock across all branches (e.g., Normal 38 · Low Stock 3 · Out of Stock 1). 5. A “Low-Stock Items” list shows up to 5 items with item name, branch, expected quantity, and minimum level (e.g., “Takoyaki sauce · Branch 1 · 360 ml / min 400 ml”); “See all” opens Alerts. 6. A “Nearing Expiration” list shows up to 5 items with name, branch, and expiration date (e.g., “Eggs · Branch 1 · exp. 2026-12-05”); “See all” opens the Expiration tab of Alerts. 7. A “Recent Activities” list shows the latest sales and inventory records with type, reference or item, amount or quantity, and branch (e.g., “TXN-B1-20261125-0001 · ₱187”, “Stock-In · Takoyaki sauce · +720 ml”); tapping a row opens its details. 8. Pull-to-refresh or the refresh icon reloads the data; returning from another screen shows the latest saved information. 9. Skeleton placeholders are shown while loading, and the dashboard loads within 3 seconds under standard mobile network conditions.
	Passed
	Failed
	Total
	Rate (%)

Precondition: T

Postcondition:

No.	Acceptance Criteria (System Requirements)

OWNER MOD

OM-SLS-01	1. The “Sales” tab shows three period tabs — Daily, Weekly, Monthly — a date selector, and a branch filter (All branches, Branch 1, Branch 2, Branch 3). 2. The date selector opens a date picker for the chosen period (a day, a week, or a month) and defaults to today, the current week, or the current month. 3. A total sales card shows the amount for the selection (e.g., Daily 2026-11-25 ₱2,310; Weekly 2026-11-19 to 11-25 ₱12,450; Monthly November 2026 ₱31,890). 4. A “Sales by Branch” section lists each branch with its amount (e.g., Branch 1 ₱4,820 · Branch 2 ₱3,990 · Branch 3 ₱3,640) and respects the branch filter. 5. A “Products Sold” list shows each product with the quantity sold (e.g., “Octobits Takoyaki 4 pcs: 46 sold”), sorted from highest to lowest. 6. A “Transactions” list shows reference, time, branch, and total for each completed sale (e.g., TXN-B1-20261125-0001 · 19:32 · Branch 1 · ₱187), newest first. 7. Tapping a transaction opens Transaction Details (OM-SLS-02). 8. Only completed and recorded sales are included; cancelled or uncompleted orders never appear. 9. If there are no sales for the selection, “No sales recorded for this period.” is shown. 10. The screen is read-only and loads within 3 seconds under standard mobile network conditions.
	Passed
	Failed
	Total
	Rate (%)

Precondition: T

Postcondition:

No.	**Acceptance Criteria (System Requirements)**
OM-SLS-02	1. The Transaction Details screen opens with a back arrow and the transaction reference as the title (e.g., TXN-B1-20261125-0001). 2. A header section shows date and time, branch, and the branch account that recorded the sale (e.g., BR1-STAFF). 3. An items table lists each line with product and size, quantity, unit price, and subtotal, followed by the total (e.g., Octobits 4 pcs x2 ₱98 + Cheese 8 pcs x1 ₱89 = ₱187). 4. A payment section shows the payment method and amounts (e.g., Cash, received ₱200, change ₱13). 5. The screen is read-only; the owner cannot edit or delete a recorded sale. 6. The back arrow returns to the previous screen with its filters and scroll position kept.
	Passed
	Failed
	Total

OWNER MOD

	Rate (%)

Precondition: T

Postcondition:

No.	Acceptance Criteria (System Requirements)
OM-INV-01	1. The “Inventory” tab shows a branch selector at the top (Branch 1, Branch 2, Branch 3), with Branch 1 selected by default. 2. Selecting another branch reloads the list for that branch without logging out. 3. Each row shows ingredient name, expected quantity with unit (e.g., “All-purpose flour · 9,375 g”), and a stock status tag (Normal, Low Stock, Out of Stock). 4. Low Stock means the expected quantity is at or below the minimum level and above 0; Out of Stock means 0. 5. Prepared batter appears as its own row in bottles with the batch reference (e.g., “Branch 1: 5 bottles · Batch #001”). 6. Items with expiration tracking show the earliest recorded expiration date (e.g., “Eggs · exp. 2026-12-05”). 7. A “Compare Branches” button opens Branch Comparison (OM-INV-02). 8. The owner can view but cannot edit quantities here; configuration is done on the web portal. 9. If a branch has no records, “No inventory records for this branch.” is shown; if loading fails, “Unable to load inventory. Pull down to retry.” is shown.
	Passed
	Failed
	Total
	Rate (%)

Precondition: T

Postcondition:

No.	Acceptance Criteria (System Requirements)
OM-INV-02	1. Branch Comparison opens with a back arrow, the title “Compare Branches”, and an ingredient selector (searchable list) showing the current ingredient. 2. Three cards are shown side by side or stacked, one per branch, each with the expected quantity and unit and a stock status tag (e.g., Eggs: Branch 1 25 pcs · Branch 2 18 pcs · Branch 3 30 pcs). 3. Changing the ingredient in the selector updates all three cards immediately. 4. Prepared batter can be selected and compared in bottles. 5. If a branch has no record for the ingredient, its card shows “Not tracked”. 6. The screen is read-only; the back arrow returns to the Inventory tab with the same branch selected.
	Passed

OWNER MOD

	Failed
	Total
	Rate (%)

Precondition: T

Postcondition:

No.	Acceptance Criteria (System Requirements)
OM-ALR-01	1. The “Alerts” tab shows two tabs — Low Stock and Expiration — each with a count, and branch filter chips (All, Branch 1, Branch 2, Branch 3) below them. 2. The Low Stock tab lists items at or below their minimum level, including items at 0 with an “Out of Stock” tag. 3. A low-stock card shows ingredient, branch, expected quantity, and minimum stock level (e.g., “Takoyaki sauce · Branch 1 · 360 ml · Min 400 ml”). 4. The Expiration tab lists batches inside the alert period with a “Near Expiration” tag and batches past their date with an “Expired” tag. 5. An expiration card shows ingredient, branch, batch information (e.g., Batch DR-1023), quantity, and recorded expiration date (e.g., 2027-05-30), with the earliest date first. 6. Selecting a branch chip filters both tabs to that branch. 7. Alerts update after a stock-in, stock-out, waste, sale consumption, or authorized adjustment is saved in any branch. 8. A note on the screen states “Alerts support your decisions. The system does not create purchase orders.” 9. If there are no alerts, “No alerts at the moment.” is shown.
	Passed
	Failed
	Total
	Rate (%)

Precondition: T

Postcondition:

No.	Acceptance Criteria (System Requirements)

OWNER MOD

OM-DSC-01	1. “Discrepancies” opens from the More menu with a back arrow, branch filter chips (All, Branch 1, Branch 2, Branch 3), and status chips (All, Pending Review, Adjusted). 2. Each card shows item, branch, difference (e.g., “Eggs · Branch 1 · −1”), date and time (e.g., 2026-11-25 20:45), and a status tag (“Pending Review” amber, “Adjusted” green). 3. The list is sorted with Pending Review first, then newest first. 4. Tapping a card opens Discrepancy Details (OM-DSC-02). 5. The More menu badge shows the number of discrepancies that are “Pending Review”. 6. If nothing matches the filters, “No discrepancies found.” is shown.
	Passed
	Failed
	Total
	Rate (%)

Precondition: T

Postcondition:

No.	Acceptance Criteria (System Requirements)
OM-DSC-02	1. Discrepancy Details shows a back arrow and read-only fields: item, expected quantity, actual quantity, difference, branch, date and time, submitting branch account (e.g., BR1-STAFF), and the staff remarks (e.g., “1 egg cracked, not recorded earlier”). 2. A “Pending Review” discrepancy shows a primary “Authorize Adjustment” button; an “Adjusted” discrepancy shows the adjustment record instead and no button. 3. Tapping “Authorize Adjustment” opens an adjustment form with the previous expected quantity (25) and actual quantity (24) read-only, an “Adjusted quantity” field prefilled with the actual quantity, and a required “Reason” field. 4. If the Reason is blank or the adjusted quantity is not a number zero or greater, “Confirm” is blocked and the field is highlighted with a message. 5. Tapping “Confirm” opens the dialog “Adjust Eggs in Branch 1 from 25 to 24?” with “Cancel” and “Confirm”; nothing is applied until the owner confirms. 6. On confirmation, the system updates the branch’s expected quantity (e.g., Eggs 25 → 24) and sets the discrepancy to “Adjusted”. 7. The system saves an Authorized Adjustment record with the previous expected quantity, actual quantity, adjusted quantity, reason, approving owner, date/time, and the related discrepancy record. 8. A success message “Adjustment saved.” appears and the owner returns to the discrepancy list. 9. The adjustment shows in Records under “Authorized Adjustments” and in the branch’s Transaction History. 10. Inventory is never adjusted automatically solely because a discrepancy exists.
	Passed
	Failed

OWNER MOD

	Total
	Rate (%)

Precondition: T

Postcondition:

No.	Acceptance Criteria (System Requirements)
OM-REC-01	1. “Records” opens from the More menu with a back arrow and a horizontally scrollable tab row: Sales, Sales Consumption, Stock-In, Stock-Out, Waste, Spillage, Physical Inventory Counts, Authorized Adjustments. 2. Each tab lists only records of that type; types are never merged (e.g., Sales Consumption is never shown under Stock-Out). 3. A branch filter (All, Branch 1, Branch 2, Branch 3) and a date range filter (e.g., 2026-11-01 to 2026-11-25) apply to the selected tab. 4. Each row shows the reference, branch, item or product, quantity or amount, and date and time (e.g., “Sales Consumption · Cheese cubes · −8 pcs · TXN-B1-20261125-0001 · Branch 1 · 19:32”). 5. The list is sorted newest first and loads more rows when scrolled to the end. 6. Tapping a row opens Record Details with reference, type, branch, item, quantity, date and time, and the branch account that recorded it (not an individual staff member). 7. Physical Inventory Counts rows show expected vs. actual quantity and the difference; Authorized Adjustments rows show previous, adjusted quantity, reason, and approving owner. 8. If no record matches the filters, “No records found.” is shown. 9. The owner can view but cannot edit or delete records. 10. The list loads within 3 seconds under standard mobile network conditions.
	Passed
	Failed
	Total
	Rate (%)

Precondition: T

Postcondition:

No.	Acceptance Criteria (System Requirements)
OM-PRF-01	1. “Profile and Logout” opens from the More menu with a back arrow and an account card. 2. The card shows the account ID (OWNER-GELO), email (owner@gelos.test), and role “Owner”. 3. Only permitted information is shown; passwords are never displayed. 4. A “Log Out” button sits at the bottom of the screen and starts the logout confirmation (OM-LGO-01).
	Passed

OWNER MOD

	Failed
	Total
	Rate (%)

Precondition: T

Postcondition:

No.	Acceptance Criteria (System Requirements)
OM-LGO-01	1. Tapping “Log Out” opens a dialog “Are you sure you want to log out?” with “Cancel” and “Log Out”. 2. “Cancel” closes the dialog and keeps the owner on the same screen, still signed in. 3. “Log Out” ends the session immediately and opens the Login screen with empty fields. 4. After logout, pressing the device Back button does not reopen protected screens or show business data. 5. To regain access, the owner must log in again with valid owner credentials.
	Passed
	Failed
	Total
	Rate (%)

OWNER MOD

Precondition: T

Postcondition:

No.	Remarks	Status
OM-LOG-01		

	0
	0
	9
	0

Precondition: T

Postcondition:

No.	Remarks	Status
OM-NAV-01		

OWNER MOD

0	
0	
6	
0	

Precondition: T

Postcondition:

No.	Remarks	Status
OM-DASH-01		

0	
0	
9	
0	

Precondition: T

Postcondition:

No.	Remarks	Status

OWNER MOD

OM-SLS-01		

0
0
10
0

Precondition: T

Postcondition:

No.	Remarks	Status
OM-SLS-02		

0
0
6

OWNER MOD

0

Precondition: T

Postcondition:

No.	Remarks	Status
OM-INV-01		

0
0
9
0

Precondition: T

Postcondition:

No.	Remarks	Status
OM-INV-02		

0

OWNER MOD

0
6
0

Precondition: T

Postcondition:

No.	Remarks	Status
OM-ALR-01		

0
0
9
0

Precondition: T

Postcondition:

No.	Remarks	Status

OWNER MOD

OM-DSC-01		

0
0
6
0

Precondition: T

Postcondition:

No.	Remarks	Status
OM-DSC-02		

0
0

OWNER MOD

10
0

Precondition: T

Postcondition:

No.	Remarks	Status
OM-REC-01		

0
0
10
0

Precondition: T

Postcondition:

No.	Remarks	Status
OM-PRF-01		

0

OWNER MOD

0
4
0

Precondition: T

Postcondition:

No.	Remarks	Status
OM-LGO-01		

0
0
5
0