

f00tils

Freestanding assembly GNU userland * <https://f00.sh>

Reply to Attn of: REL/F00

TO: Maintainers and Users

FROM: Project Engineering

SUBJECT: Release memo - f00tils 0.16.8

REF: README drop-in, site #drop-in, F00_CORE wiring, v0.16.7

Bottom line: 0.16.8 clarifies drop-in policy and finishes F00_CORE. Scripts and non-TTY do not auto-enable --core; only chrome is TTY-gated. Documented on README and <https://f00.sh/#drop-in>. F00_CORE=1 / core=true now seeds GNU-clone mode for find, grep, and diffutils as well as ls.

1. Purpose

Record the drop-in clarification and F00_CORE fix under house prime directive.

2. Behavior truth

- is_tty (TCGETS): color/chrome only
- Modern semantics remain on pipes unless core is set (find skips .git, grep smart-case, ...)
- GNU clone: --core, F00_CORE=1, or config core=true
- Installer replace does not set F00_CORE

3. Code

- find/grep/diff/cmp/sdiff/diff3 seed local core flags from g_json_core at entry
- Docs: README, site callout, MODERN-FEATURES, install seed comments

4. Verification

- 4.1 cd asm && make && make check
- 4.2 F00_CORE=1 f00-find ... includes .git; without it modern skips .git
- 4.3 F00_CORE=1 f00-grep hello is case-sensitive (no smart-case)
- 4.4 Release assets: SOP + memo-release-0.16.8.pdf + file_id.diz

5. Install

curl -fsSL <https://f00.sh/install.sh> | bash * pin F00_VERSION=v0.16.8 * drop-in: F00_CORE=1

Project Engineering
f00tils release

Date: 2026-07-27

cc: ['https://f00.sh', 'github.com/theesfeld/f00']