Management of a limited resource:

(Memory hunger of applications increases with capacity!)

⇒ Sophisticated algorithms needed, together with support from HW and from compiler and loader.

Start by looking at mapping from logical addresses to physical addresses:

- at compile time: absolute references are generated (eg MS-DOS .com-files)
- at load time: can be done by special program
- at execution time: needs HW support

Address mapping can be taken one step further:

dynamic linking: use only one copy of system library

 \Rightarrow OS has to help: same code accessible to more than one process

Nick Blundell, Eike Ritter Operating Systems with C/C++ 2010/11



Linux Device Drivers

Fragmentation

Swapping raises two problems:

- over time, many small holes appear in memory (external fragmentation)
- programs only a little smaller than hole ⇒ leftover too small to qualify as hole (internal fragmentation)

Strategies for choosing holes:

- First-fit: Start from beginning and use first available hole
- Rotating first fit: start after last assigned part of memory
- Best fit: find smallest usable space
- Buddy system: Free holes are administered according to tree structure; smallest possible chunk used

If memory demand is too high, memory of some processes is transferred to disk

Usually combined with scheduling: low priority processes are swapped out

Problems:

- Big transfer time
- What to do with pending I/O?

First point reason why swapping is not principal memory management technique

exception: MS-Windows 3.1: based on MS-DOS for 8086, which is not sophisticated enough (no MMU).

⇒ user decides which process is swapped out possible only at few pre-defined moments

⇒ multi-processing severely limited

DOS-mode in Windows 9.x has same limitations!

Nick Blundell, Eike Ritter Operating Systems with C/C++ 2010/11 2 2



Linux Device Drivers

Paging

Alternative approach: Assign memory of a fixed size (page)

⇒ avoids external fragmentation

Translation of logical address to physical address done via page table

Hardware support mandatory for paging:

If page table small, use fast registers

Store large page tables in main memory, but cache most recently used entries

Instance of a general principle:

Whenever large lookup tables are required, use cache (small but fast storage) to store most recently used entries

Memory protection easily added to paging: protection information stored in page table Page Table

Memory address

Control bits

Logical Address

Pagenumber

Nick Blundell, Eike Ritter Operating Systems with C/C++ 2010/11 5

f d

Main Memory

Segmentation

Idea: Divide memory according to its usage by programs:

- Data: mutable, different for each instance
- Program Code: immutable, same for each instance
- Symbol Table: immutable, same for each instance, only necessary for debugging

Requires again HW support

can use same principle as for paging, but have to do overflow check


Paging motivated by ease of allocation, segmentation by use of

⇒ combination of both works well (eg 80386)


Nick Blundell, Eike Ritter Operating Systems with C/C++ 2010/11 6



Linux Device Drivers



Linux Device Drivers



Virtual memory

Idea: complete separation of logical and physical memory

⇒ Program can have extremely large amount of virtual memory

Generalisation of paging and segmentation works because most programs use only small fraction of memory intensively.

Efficient implementation tricky

Reason: Enormous difference between

- memory access speed (ca. 60ns)
- disk access speed (ca. 6ms)

Factor 100,000 !!

Nick Blundell, Eike Ritter Operating Systems with C/C++ 2010/11 2 9



Page replacement algorithms

1.) FIFO:

easy to implement, but does not take locality into account Further problem: Increase in number of frames can cause increase in number of page faults (Belady's anomaly)

2.) Optimal algorithm:

select page which will be re-used at the latest time (or not at all) ⇒ not implementable, but good for comparisons

Demand Paging

Virtual memory implemented as demand paging:

memory divided into units of same length (pages), together with valid/invalid bit

Two strategic decisions to be made:

- Which process to "swap out" (move whole memory to disk and block process): done by swapper
- which pages to move to disk when additional page is required: done by pager

Minimisation of rate of page faults (page has to be fetched from memory) crucial

If we want 10% slowdown due to page fault, require fault rate $p < 10^{-6}!!$

Nick Blundell, Eike Ritter Operating Systems with C/C++ 2010/11 10



Linux Device Drivers

3.) Least-recently used:

use past as guide for future and replace page which has been unused for the longest time

Problem: Requires a lot of HW support

Possibilities:

- -Stack in microcode
- -Approximation using reference bit: HW sets bit to 1 when page is

Now use FIFO algorithm, but skip pages with reference bit 1, resetting it to 0

⇒ Second-chance algorithm

Thrashing

If process lacks frames it uses constantly, page-fault rate very high.

- ⇒ CPU-throughput decreases dramatically.
- ⇒ Disastrous effect on performance.

Two solutions:

1.) Working-set model (based on locality):

Define working set as set of pages used in the most recent Δ page references

keep only working set in main memory

⇒ Achieves high CPU-utilisation and prevents thrashing

Difficulty: Determine the working set!

Approximation: use reference bits; copy them each 10,000 references and define working set as pages with reference bit set.

Nick Blundell, Eike Ritter Operating Systems with C/C++ 2010/11 13



Memory Management in the Linux Kernel

Have only four segments in total:

- Kernel Code
- Kernel Data
- User Code
- User Data

Paging used as described earlier

Have elaborate permission system for pages

2.) Page-Fault Frequency:

takes direct approach:

- give process additional frames if page frequency rate high
- remove frame from process if page fault rate low

Nick Blundell, Eike Ritter Operating Systems with C/C++ 2010/11 14



Kernel memory and user memory

Memory usage in linux influenced by HW limitations of earlier architecture

Result: When using 32 bit architecture, division of logical address space in

- 3GB for user processes (so-called high memory)
- 1GB for kernel (so-called low memory)

If kernel requires more memory, pages in high memory may be temporarily mapped into low memory

Division not present in 64 bit architecture

Page caches

Experience shows: have repeated cycles of allocation and freeing same kind of objects (eg inodes, dentries) can have pool of pages used as cache for these objects (so-called slab cache) cache maintained by application (eg file system) kmalloc uses slab caches for commonly used sizes

Nick Blundell, Eike Ritter Operating Systems with C/C++ 2010/11 17



