一、从TT文档下载文件

1、打开TT官方文档

http://labs.tradingtechnologies.com/apis/tt-fix/System Overview.html

2. Managing FIX Sessions



3、找到 stunnel 的下载链接

Connecting to TT FIX

FIX clients can connect to TT FIX over a Secure TCP (SSL) connection using the following information. FIX clients can connect to the TT UAT environment via the Internet or stunnel; for the TT Production environment, clients can use stunnel.

	UAT	Production
FIX Back Office	fixdropcopy-ext-uat-cert.trade.tt: 11501/11701	fixdropcopy-ext-prod-live.trade.tt: 11701
FIX Order Routing	fixorderrouting-ext-uat-cert.trade.tt: 11502/11702	fixorderrouting-ext-prod-live.trade.tt: 11702
Security Definition	fixsecurityinfo-ext-uat-cert.trade.tt: 11503/11703	fixsecurityinfo-ext-prod-live.trade.tt: 11703

To configure connections for stunnel:

1. Install the <u>stunnel</u> software, if necessary.


Note: The first time you install stunnel, you might receive a prompt similar to the following. If so, simply enter the appropriate information for your location and organization.

4、下载 stunnel 的 windows 版本

Latest Version

File Name	Size	Date
stunnel-5.48-android.zip	1234167	2nd July 2018
stunnel-5.48-android.zip.asc	963	2nd July 2018
stunnel-5.48-android.zip.sha256	91	2nd July 2018
stunnel-5.48-win32-installer.exe	3130792	2nd July 2018
stunnel-5.48-win32-installer.exe.asc	963	2nd July 2018
stunnel-5.48-win32-installer.exe.sha256	99	2nd July 2018
stunnel-5.48.tar.gz	708356	2nd July 2018
stunnel-5.48.tar.gz.asc	963	2nd July 2018
stunnel-5.48.tar.gz.sha256	86	2nd July 2018


5、下载 stunnel 文件




二、安装 stunnel

The stunnel.zip file contains the TTFIX.crt public cert file and an example stunnel client config file which is used to configure the stunnel proxy.







第一次启动 stunnel 会出现 dos 窗口,填写信息。可随便填写:zd。

三、更改 stunnel 配置文件

1、解压 stunnel 文件

□ 木媧叭 o1012.cruowiiioau	Z010-4-13 11:40	CKDOWINLOAD	An'ota VD
stunnel-5.44-win32-installer.exe	2018-4-20 13:37	应用程序	3,048 KB
stunnel.zip	2018-4-20 13:43	好压 ZIP 压缩文件	11 KB

- 2、拷贝TTFIX.crt 到 C:\Program Files (x86)\stunnel\config
- 3、修改 stunnel.conf

打开路径 C:\Program Files (x86)\stunnel\config,

a-certs.pem	2017-11-25 12:42	PEM 文件	234 KB
openssl.cnf	2017-1-17 4:12	CNF 文件	2 KB
🦳 stunnel - 副本.conf	2017-1-28 17:04	CONF 文件	5 KB
stunnel -uat.conf	2018-4-23 17:23	CONF 文件	5 KB
stunnel.conf	2018-7-25 11:18	CONF 文件	5 KB
stunnel.pem	2018-4-20 15:40	PEM 文件	3 KB
TTFIX.crt	2018-5-29 4:07	安全证书	24 KB

- 4、添加 TT 文档里的合约定义和下单配置
- a、添加行情模块的配置: 复制 TT 文档下图红色字体到 stunnel.conf

```
[sdfix-tcp]
client = yes
accept = 127.0.0.1:11703
connect = FullyQualifiedDomainName:port
CAfile = TTFIX.crt
verify = 3
```

```
accept = 127.0.0.1:11702
connect = FullyQualifiedDomainName:port
CAfile = TTFIX.crt
verify = 3

[sdfix-tcp]
client = yes
accept = 127.0.0.1:11703
connect = FullyQualifiedDomainName:port
CAfile = TTFIX.crt
verify = 3

; Encrypted HTTP proxy authenticated with a client certificate
; located in the Windows certificate store
; [example-proxy]
; client = yes

102.0.0.1.0000
```

b、复制下单的配置

```
[orfix-tcp]
client = yes
accept = 127.0.0.1:11702
connect = FullyQualifiedDomainName:port
CAfile = TTFIX.crt
verify = 3
 [sdfix-tcp]
 client = yes
 accept = 127.0.0.1:11703
 connect = FullyQualifiedDomainName:port
 CAfile = TTFIX.crt
 verify = 3
  [orfix-tcp]
 client = yes
 accept = 127.0.0.1:11702
 connect =fixorderrouting-ext-prod-live.trade.tt:11702
  CAfile =TTFIX.crt
  verify = 3
 ; Encrypted HTTP proxy authenticated with a client certificate
 ; located in the Windows certificate store
  ; [example-proxy]
;client = yes
```

c、修改 stunnel.conf 行情、下单生产环境的配置

```
[sdfix-tcp]
client = yes
accept = 127.0.0.1:11703

connect = fixsecurityinfo-ext-prod-live.trade.tt:11703

CAfile = TTFIX.crt
verify = 3

[orfix-tcp]
client = yes
accept = 127.0.0.1:11702
connect = fixorderrouting-ext-prod-live.trade.tt:11702

CAfile = TTFIX.crt
verify = 3

; Encrypted HTTP proxy authenticated with a client certificate
; located in the Windows certificate store
```

四、修改 TT 项目配置

1、修改 quickfix_market.cfg 配置

```
DataDictionary=config\FIX42.xml
SocketConnectHost=127.0.0.1
SocketConnectPort=11703
ResetOnLogon=Y
```

2、修改 quickfix. cfg 配置

```
StartDay=sun
EndDay=sat
StartTime=00:00:00
EndTime=00:00:00
UseDataDictionary=Y
DataDictionary=config\FIX42.xml
SocketConnectHost=127.0.0.1
SocketConnectPort=11702
ResetOnLogon=N
PersistMessages=Y
RefreshOnLogon=N
```

五、调试



, 再启动 VS 对应的工程。