# **CS 33**

# **Multithreaded Programming III**

**CS33 Intro to Computer Systems** 

XXX-1 Copyright © 2012 Thomas W. Doeppner. All rights reserved.

# Outline

- Thread safety
- Unix signals
- Cancellation

**CS33 Intro to Computer Systems** 

XXX-2 Copyright © 2012 Thomas W. Doeppner. All rights reserved.

```
Global Variables

int IOfunc() {
    extern int errno;
    ...
    if (write(fd, buffer, size) == -1) {
        if (errno == EIO)
            fprintf(stderr, "IO problems ...\n");
            ...
        return(0);
    }
    ...
}
CS33 Intro to Computer Systems XXX-3 Copyright © 2012 Thomas W. Doeppner. All rights reserved.
```

Unix was not designed with multithreaded programming in mind. A good example of the implications of this is the manner in which error codes for failed system calls are made available to a program: if a system call fails, it returns –1 and the error code is stored in the global variable *errno*. Though this is not all that bad for single-threaded programs, it is plain wrong for multithreaded programs.

# Coping

- Fix Unix's C/system-call interface
- Make errno refer to a different location in each thread

```
- e.g.
#define errno __errno[thread_ID]
```

**CS33 Intro to Computer Systems** 

XXX-4


Copyright © 2012 Thomas W. Doeppner, All rights reserved

The ideal way to solve the "ermo problem" would be to redesign the C/system-call interface: system calls should return only an error code. Anything else to be returned should be returned via result parameters. (This is how things are done in the Win32 interface.) Unfortunately, this is not possible (it would break pretty much every Unix program in existence).

So we are stuck with *errno*. What can we do to make *errno* coexist with multithreaded programming? What would help would be to arrange, somehow, that each thread has its own private copy of *errno*. I.e., whenever a thread refers to *errno*, it refers to a different location from any other thread when it refers to *errno*.

What can we do? As shown in the slide, we might use the C preprocessor to redefine *errno* as something a bit more complicated — references to *errno* result in accessing an array of *errno*s, one for each thread. This might turn out to be impractical, but we can devise other approaches, as shown in the next slide.

Note: in Linux, when threads are used, errno is defined to be "(\*\_errno\_location())" i.e., it dereferences the result of calling a function which retrieves the thread-specific address of errno.



There are enough other situations analogous to *errno* in which each thread should have its own private copy of an otherwise global variable that a general mechanism to deal with it is important. A data item that is global but private to a thread is called *thread-specific data*. Rather than represent each such item as a separate array, as mentioned in the previous slide, what's done in POSIX threads is, effectively, to give each thread an array of pointer-size values (it doesn't have to be done this way, but the effect must be the same). Each element of the array either holds or points to a thread-specific-data (TSD) item. Thus TSD[0] might contain the address of thread-specific-data item *var1*, TSD[1] might contain the value of *errno*, and TSD[2] might contain the address of *var2*. What's important is that whenever a thread refers to the TSD array, it uses its own private array. This may sound like we're begging the question, but, as seen in the next slide, we introduce special machinery for getting at this array.

# The TSD Array

- pthread key create(&key, cleanup routine)
  - allocates a slot in the TSD arrays
  - provides a function to cleanup when threads terminate
- value = pthread getspecific(key)
  - fetches from the calling thread's array
- · pthread setspecific(key, value)
  - stores into the calling thread's array

**CS33 Intro to Computer Systems** 

XXX-6

Copyright © 2012 Thomas W. Doeppner. All rights reserved.

So that we can be certain that it's the calling thread's array that is accessed, rather than access the TSD array directly, one uses a set of POSIX threads library routines. To find an unused slot, one calls  $pthread\_key\_create$ , which returns the index of an available slot in its first argument. Its second argument is the address of a routine that's automatically called when the thread terminates, so as to do any cleanup that might be necessary (it's called with the key (index) as its sole argument, and is called only if the thread has actually stored a non-null value into the slot). To put a value in a slot, i.e., perform the equivalent of TSD[i] = x, one calls  $pthread\_setspecific(i,x)$ . To fetch from the slot, one calls  $pthread\_getspecific(i)$ .

# **Using Thread-Specific Data (1)**

```
pthread_key_t errno_key; // global
pthread_key_create(&errno_key, 0);
    // done by only one thread

int write(...) { // wrapper for syscall
    int err = syscall(WRITE, ...);
    if (err)
        pthread_setspecific(errno_key, err);
        ...
}

CS33 Intro to Computer Systems

XXX-7 Copyright © 2012 Thomas W. Doeppner. All rights reserved
```

Here we see how we might use thread-specific data to implement *errno* in a thread-safe way. First we allocate a slot in the TSD array to hold each thread's copy of *errno*. It's important that this be done only once, but that the slot's index be placed in a global variable (*errno\_key* in this case) so that all threads can access it. (Since no cleanup is necessary when threads terminate, we don't supply a cleanup routine.) Next we see a sketch of the write library routine, which is actually a wrapper for an instruction that traps into the kernel to make the actual call. On return from the trap, if there was an error, we put its code into the TSD slot that was allocated for *errno*.

# #define errno pthread\_getspecific(errno\_key) // make things easy to read and type ... if (write(fd, buffer, size) == -1) { if (errno == EIO) fprintf(stderr, "IO problems ...\n"); ... return(0); } CS33 Intro to Computer Systems XXX-8 Copyright © 2012 Thomas W. Doeppner, All rights reserved.

We repeat our earlier example that used *errno*, however this time we've redefined references to *errno* to use *pthread\_getspecific*.

```
Example (1)
#define cred \
                                     void *server start(req t req) {
  pthread getspecific(cred key)
                                        cred t *credp;
pthread_key_t cred_key;
void free cred(void *);
                                       credp = (cred_t *)malloc(
                                           sizeof(*credp));
mainline() {
                                        make cred(credp);
                                        pthread setspecific (cred key,
  pthread key create (&cred key,
     free cred);
                                        handle request (req);
  while (more requests) {
                                        return(0);
   pthread create (&thread, 0,
       server start, request);
  CS33 Intro to Computer Systems
                                  XXX-9
                                         Copyright © 2012 Thomas W. Doeppner. All rights reserved
```

As another example of the use of thread-specific data, consider a server application in which threads perform requests on behalf of clients. Some of these requests require some degree of *privilege*; thus we need to know the client's *credentials* before performing a request on its behalf. Rather than pass these credentials around as an argument to every routine, it would be convenient to treat them as global data. However, since we have many threads, we must treat them instead as thread-specific data.

To make our accesses to *cred*, the per-thread client credentials, appear to be accesses to global data, we define a macro called *cred* that in turn calls *pthread\_getspecific*. Its argument is *cred\_key*, the data-item-key that we have somehow associated with the credentials. To create the key in the first place, we call *pthread\_key\_create*. This takes two parameters. The first is an output parameter that returns the key, the second is the address of a function that will be called to "clean up" when the thread terminates. The idea is that if a thread instantiates its own value of *cred*, then when the thread terminates, the cleanup function does whatever is necessary to uninstantiate the thread's value of *cred*.

As each thread is created, it calls *pthread\_setspecific* to give its instance of *cred* a value. After this initialization, whenever the thread refers to *cred*, it actually calls *pthread\_getspecific* and gets its own private value of *cred*.

This is the remainder of the credentials example.

# Static Local Storage struct hostent \*gethostbyname(const char \*name) { static struct hostent hostent; ... // lookup name; fill in hostent return(&hostent); }

Another ramification of Unix's single-thread mentality is the use of static local storage in a number of library routines. An example of this is the *gethostbyname* routine, which, given the name of a network host, returns the address of a data structure that contains information about how to contact that host. This data structure is built on storage that is statically allocated inside the *gethostbyname* routine. This is a reasonable way to do things in the single-threaded world, but it fails miserably in the multithreaded world.

# Coping

- · Use thread-specific data
- · Allocate storage internally; caller frees it
- · Redesign the interface

**CS33 Intro to Computer Systems** 

XXX-12

Copyright © 2012 Thomas W. Doeppner. All rights reserved

As the slide shows, there are at least three techniques for coping with this problem. We could use thread-specific data, but this would entail associating a fair amount of storage with each thread—perhaps this is viable if just a few bytes are involved, but not for a large data structure such as a *struct hostent* which is used only by the occasional thread. We might simply allocate storage (via *malloc*) inside *gethostbyname* and return a pointer to this storage. The problem with this is that the calls to *malloc* and *free* could turn out to be expensive. Furthermore, this makes it the caller's responsibility to free the storage, introducing a likely storage leak.

The solution taken is to redesign the interface. The new, "thread-safe" version is called *gethostbyname\_r* (the *r* stands for *reentrant*, an earlier term for "thread-safe"); it takes additional parameters that describe storage passed by the caller into which *gethostbyname\_r* places the result. Thus the caller is responsible for both the allocation and the liberation of the storage containing the result; this storage is typically a local variable (allocated on the stack), so that its allocation and liberation overhead is negligible, at worst.

# Shared Data • Thread 1: printf("goto statement reached"); • Thread 2: printf("Hello World\n"); • Printed on display: go to Hell CS33 Intro to Computer Systems XXX-13 Copyright © 2012 Thomas W. Doeppner. All rights reserved.

Yet another problem that arises when using libraries that were not designed for multithreaded programs concerns synchronization. The slide shows what might happen if one relied on the single-threaded versions of the standard I/O routines.

# Coping

- · Wrap library calls with synchronization constructs
- · Fix the libraries

**CS33 Intro to Computer Systems** 

XXX-14 Copyright © 2012 Thomas W. Doeppner. All rights reserved.

To deal with this printf problem, we must somehow add synchronization to printf (and all of the other standard I/O routines). A simple way to do this would be to supply wrappers for all of the standard I/O routines ensuring that only one thread is operating on any particular stream at a time. A better way would be to do the same sort of thing by fixing the routines themselves, rather than supplying wrappers (this is what is done in most implementations).

# **Efficiency**

- Standard I/O example
  - getc() and putc()
    - » expensive and thread-safe?
    - » cheap and not thread-safe?
  - two versions
    - » getc() and putc()
      - · expensive and thread-safe
    - » getc\_unlocked() and putc\_unlocked()
      - · cheap and not thread-safe
      - made thread-safe with flockfile() and funlockfile()

**CS33 Intro to Computer Systems** 

XXX-15 Copyright © 2012 Thomas W. Doeppner. All rights reserved.

After making a library thread-safe, we may discover that many routines have become too slow. For example, the standard-I/O routines getc and putc are normally expected to be fast—they are usually implemented as macros. But once we add the necessary synchronization, they become rather sluggish — much too slow to put in our innermost loops. However, if we are aware of and willing to cope with the synchronization requirements ourselves, we can produce code that is almost as efficient as the single-threaded code without synchronization requirements.

The POSIX-threads specification includes unsynchronized versions of getc and putc getc unlocked and putc unlocked. These are exactly the same code as the single-threaded getc and putc. To use these new routines, one must take care to handle the synchronization oneself. This is accomplished with flockfile and funlockfile.

### What's Thread-Safe? Everything except gethostent() getutxline() asctime() ecvt() putc\_unlocked() getlostent() getlogin() getnetbyaddr() getnetbyname() getnetent() encrypt() putchar\_unlocked() basename() gmtime() endgrent() endpwent() hcreate() hdestroy() putenv() pututxline() catgets() crypt() ctime() rand() readdir() hsearch() endutxent() dbm\_clearerr() fcvt() getopt() inet\_ntoa() dbm\_close() dbm\_delete() getprotobyname() setenv() Igamma() gcvt() getprotobynumber() setgrent() getc\_unlocked() getchar\_unlocked() getdate() setkey() dbm\_error() getprotoent() Igammaf() getpwent() getpwnam() getpwuid() getservbyname() Igammal() localeconv() dbm\_fetch() dbm\_firstkey() dbm\_nextkey() setpwent() setutxent() getenv() localtime() strerror() dbm\_open() getgrent() Irand48() strtok() dbm\_store() getgrgid() getservbyport() mrand48() ttyname() dirname() getgrnam() getservent() nftw() unsetenv() nl\_langinfo() gethostbyaddr() dlerror() getutxent() wcstombs() drand48() gethostbyname() getutxid() ptsname() wctomb() **CS33 Intro to Computer Systems** XXX-16 Copyright © 2012 Thomas W. Doeppner. All rights reserved.

According to IEEE Std. 1003.1 (POSIX), all functions they specify must be thread-safe, except for those listed above.

# Beyond POSIX TLS Extensions for ELF and gcc

- Thread Local Storage (TLS)
  - synonym for TSD

```
__thread int x=6;

// Each thread has its own copy of x,

// each initialized to 6.

// Linker and compiler do the setup.

// May be combined with static or extern.

// Doesn't make sense for local variables!
```

**CS33 Intro to Computer Systems** 

XXX-17

Copyright © 2012 Thomas W. Doeppner. All rights reserved.

ELF stands for "executable and linking format" and is the standard format for executable and object files used on most Unix (and other) systems. The \_\_thread attribute tells gcc that the item being declared is to be thread-local, which is the same thing as thread-specific. A detailed description of how it is implemented can be found at http://people.redhat.com/drepper/tls.pdf.

# **Performance Concerns**

- Referencing TLS
  - involves finding it: levels of indirection
- Each module
  - potentially defines TLS
- · Each thread
  - potentially needs private copy of each module's
- · Creating a thread
  - requires setup of TLS
- · Loading a module
  - adds TLS to current and future threads

**CS33 Intro to Computer Systems** 


XXX-18 Copyright © 2012 Thomas W. Doeppner. All rights reserved.

# **Optimizations**

- · Allocate/initialize TLS on demand
  - not all threads use all modules
- · Short-circuit access to TLS where possible
  - staticly linked modules
  - intra-module access


**CS33 Intro to Computer Systems** 

XXX-19 Copyright © 2012 Thomas W. Doeppner. All rights reserved.



Deviations are things that modify a thread's normal flow of control. Unix has long had *signals*, and these must be dealt with in multithreaded improvements to Unix. There are actually two fairly different classes of signals: *asynchronous signals* and *synchronous signals*. The former are caused by events beyond the process's control, such as I/O events, clock events, system calls issued by other processes, etc. The latter are responses to what the current thread has just done, such as divide by zero, addressing exceptions, etc.

Cancellation is a new concept that pertains strictly to multithreaded programming. It is the means by which one thread can request the termination of another and provides a way for the terminating thread to terminate cleanly.



Asynchronous signals were designed (like almost everything else) with single-threaded processes in mind. A signal is delivered to the process; if the signal is *caught*, the process stops whatever it is doing, deals with the signal, and then resumes normal processing. But what happens when a signal is delivered to a multithreaded process? Which thread or threads deal with it?

Asynchronous signals, by their very nature, are handled asynchronously. But one of the themes of multithreaded programming is that threads are a cure for asynchrony. Thus we should be able to use threads as a means of getting away from the "drop whatever you are doing and deal with me" approach to asynchronous signals.

Synchronous signals often are an indication that something has gone wrong: there really is no point continuing execution in this part of the program because you have already blown it. Traditional Unix approaches for dealing with this bad news are not terribly elegant.

## **Dealing with Signals**

- Per-thread signal masks
- Per-process signal vectors
- · One delivery per signal

**CS33 Intro to Computer Systems** 

XXX-22

Copyright © 2012 Thomas W. Doeppner. All rights reserved

The standard Unix model has a process-wide signal mask and a vector indicating what is to be done in response to each kind of signal. When a signal is delivered to a process, an indication is made that this signal is pending. If the signal is unmasked, then the vector is examined to determine the response: to suspend the process, to resume the process, to terminate the process, to ignore the signal entirely, or to invoke a signal handler.

A number of issues arise in translating this model into a multithreaded-process model. First of all, if we invoke a signal handler, which thread or threads should execute the handler? What seems to be closest to the spirit of the original signal semantics is that exactly one thread should execute the handler. Which one? The consensus is that it really does not matter, just as long as exactly one thread executes the signal handler. But what about the signal mask? Since one sets masks depending on a thread's local behavior, it makes sense for each thread to have its own private signal mask. Thus a signal is delivered to any one thread that has the signal unmasked (if more than one thread has the signal unmasked, a thread is chosen randomly to handle the signal). If all threads have the signal masked, then the signal remains pending until some thread unmasks it.

A related issue is the vector indicating the response to each signal. Should there be one such vector per thread? If so, what if one thread specifies process termination in response to a signal, while another thread supplies a handler? For reasons such as this, it was decided that, even for multithreaded processes, there would continue to be a single, process-wide signal-disposition vector.

# 

Signals may be sent to individual threads using *pthread\_kill*. Though the targeted thread will handle the signal, the behavior is as set for the entire process (or clone group in Linux) using *sigaction*. Each thread may independently block and unblock signals using *pthread\_sigmask*. Note that there is no thread equivalent of *sigqueue*.

# Asynchronous Signals (1) main() { void handler(int); sigset(SIGINT, handler); ... // long-running buggy code } void handler(int sig) { ... // die gracefully exit(1); } CS33 Intro to Computer Systems XXX-24 Copyright © 2012 Thomas W. Doeppner. All rights reserved.

Let's look at some of the typical uses for asynchronous signals. Perhaps the most common is to force the termination of the process. When the user types control-C, the program should terminate. There might be a handler for the signal, so that the program can clean up and then terminate.

# 

Here we are using a signal to send a request to a running program: when the user types control-C, the program prints out its current state and then continues execution. If synchronization is necessary so that the state is printed only when it is stable, it must be provided by appropriate settings of the signal mask.

# 

In this example, the signal handler calls *printf*. This is usually not a problem, except when the mainline code is interrupted while in the middle of *printf*—the *printf* called from the signal handler might destructively interfere with the *printf* called from the mainline code.

Similarly, it's dangerous (fatally so) to call *malloc* and *free* from within signal handlers: the handler might have interrupted another call to *malloc* or *free* and the result could be a corrupted heap.

## Synchronizing Asynchrony void \*monitor(void \*dummy) { computation state t state; int sig; sigset t set; while (1) { main() { sigwait (&set, &sig); pthread\_t thread; display(&state); sigemptyset(&set); return(0); sigaddset(&set, SIGINT); pthread sigmask (SIG BLOCK, &set, 0); pthread create (&thread, 0, monitor, 0); long running procedure(); **CS33 Intro to Computer Systems** XXX-27 Copyright © 2012 Thomas W. Doeppner. All rights reserved

In this slide we go back to the earlier problem and use a different technique for dealing with the signal. Rather than have the thread performing the long-running computation be interrupted by the signal, we dedicate a thread to dealing with the signal. We make use of a new signal-handling routine, sigwait. This routine puts its caller to sleep until one of the signals specified in its argument occurs, at which point the call returns and the number of the signal that occurred is stored in the location pointed to by the second argument. As is done here, sigwait is normally called with the signals of interest masked off; sigwait responds to signals even if they are masked. (Note also that a new thread inherits the signal mask of its creator.) (The system call sigprocmask is identical in effect to pthread\_sigmask and could be used here instead.)

Among the advantages of this approach is that there are no concerns about async-signal safety since a signal handler is never invoked. The signal-handling thread waits for signals synchronously — it is not interrupted. Thus it is safe for it to use even mutexes, condition variables, and semaphores from inside of the *display* routine. Another advantage is that, if this program is run on a multiprocessor, the "signal handling" can run in parallel with the mainline code, which could not happen with the previous approach.

# Killing Time ...

```
struct timespec timeout, remaining time;
timeout.tv sec = 3;
                          // seconds
timeout.tv nsec = 1000;
                         // nanoseconds
nanosleep (&timeout, &remaining time);
```

**CS33 Intro to Computer Systems** 

XXX-28 Copyright © 2012 Thomas W. Doeppner. All rights reserved.

It is sometimes useful for a thread to wait for a certain period of time before continuing. The traditional Unix approach of using alarm and SIGALRM not only is not suitable for multithreaded programming, but also does not provide fine enough granularity. The routine nanosleep provides a better approach. A thread calls it with two arguments; the first indicates (in seconds and nanoseconds) how long the thread wishes to wait. The second argument is relevant only if the thread is interrupted by a signal: it indicates how much additional time remains until the originally requested time period expires.


Note that most Unix implementations do not have a clock that measures time in nanoseconds: the first argument to nanosleep is rounded up to an integer multiple of whatever sleep resolution is supported.

## **Timeouts**

```
struct timespec relative timeout, absolute timeout;
struct timeval now;
relative timeout.tv sec = 3;
                                    // seconds
relative timeout.tv nsec = 1000;
                                      // nanoseconds
gettimeofday(&now, 0);
absolute timeout.tv sec = now.tv sec + relative timeout.tv sec;
absolute timeout.tv nsec = 1000*now.tv usec +
  relative timeout.tv nsec;
if (absolute_timeout.tv_nsec >= 1000000000) { // deal with the carry
  absolute timeout.tv nsec -= 1000000000;
  absolute timeout.tv sec++;
pthread mutex lock(&m);
while (!may_continue)
  pthread cond timedwait(&cv, &m, &absolute timeout);
pthread mutex unlock (&m);
 CS33 Intro to Computer Systems
                                  XXX-29 Copyright © 2012 Thomas W. Doeppner. All rights reserved.
```

POSIX threads provides a version of *pthread\_cond\_wait* that has a timeout: *pthread\_cond\_timedwait*. It takes an additional argument indicating when the thread should give up on being awoken by a *pthread\_cond\_signal*. This argument is an absolute time, as opposed to a relative time (as used in the previous slide); i.e., it is the clock time at which the call times out. To convert from an relative time to an absolute time, one must perform the machinations shown in the slide (or something similar)—note that *gettimeofday* returns seconds and *microseconds*, whereas *pthread\_cond\_timedwait* wants seconds and *nanoseconds*.

Why is it done this way? Though at first (and most subsequent) glances it seems foolish to require an absolute timeout value rather than a relative one, the use of the former makes some sense if you keep in mind that *pthread\_cond\_timedwait* could return with the "may\_continue" condition false even before the timeout has expired (either because it's returned spontaneously or because the "may\_continue" was falsified after the thread was released from the condition-variable queue). By having the timeout be absolute, there's no need to compute a new relative timeout when *pthread\_cond\_timedwait* is called again.



In a number of situations one thread must tell another to cease whatever it is doing. For example, suppose we've implemented a chess-playing program by having multiple threads search the solution space for the next move. If one thread has discovered a quick way of achieving a checkmate, it would want to notify the others that they should stop what they're doing, the game has been won.

One might think that this is an ideal use for per-thread signals, but there's a cleaner mechanism for doing this sort of thing in POSIX threads, called *cancellation*.

# **Cancellation Concerns**

- · Getting cancelled at an inopportune moment
- · Cleaning up

**CS33 Intro to Computer Systems** 

XXX-31 Copyright © 2012 Thomas W. Doeppner. All rights reserved.

We have two concerns about the forced termination of threads resulting from cancellation: a thread might be in the middle of doing something important that it must complete before self-destructing; and a canceled thread must be given the opportunity to clean up.

## **Cancellation State**

- Pending cancel
  - pthread cancel (thread)
- Cancels enabled or disabled

```
- int pthread_setcancelstate(
    {PTHREAD_CANCEL_DISABLE
    PTHREAD_CANCEL_ENABLE},
    &oldstate)
```

- · Asynchronous vs. deferred cancels
  - int pthread\_setcanceltype(
     {PTHREAD\_CANCEL\_ASYNCHRONOUS,
     PTHREAD\_CANCEL\_DEFERRED},
     &oldtype)

**CS33 Intro to Computer Systems** 

XXX-32

Copyright © 2012 Thomas W. Doeppner. All rights reserved

A thread issues a cancel request by calling <code>pthread\_cancel</code>, supplying the ID of the target thread as the argument. Associated with each thread is some state information known as its <code>cancellation state</code> and its <code>cancellation type</code>. When a thread receives a cancel request, it is marked indicating that it has a pending cancel. The next issue is when the thread should notice and act upon the cancel. This is governed by the cancellation state: whether cancels are <code>enabled</code> or <code>disabled</code> and by the cancellation type: whether the response to cancels is <code>asynchronous</code> or <code>deferred</code>. If cancels are <code>disabled</code>, then the cancel remains pending but is otherwise ignored until cancels are enabled. If cancels are <code>enabled</code>, they are acted on as soon as they are noticed if the cancellation type is <code>asynchronous</code>. Otherwise, i.e., if the cancellation type is <code>deferred</code>, the cancel is acted upon only when the thread reaches a <code>cancellation point</code>.

Cancellation points are intended to be well defined points in a thread's execution at which it is prepared to be canceled. They include pretty much all system and library calls in which the thread can block, with the exception of *pthread\_mutex\_lock*. In addition, a thread may call *pthread\_testcancel*, which has no function other than being a cancellation point.

The default is that cancels are enabled and deferred. One can change the cancellation state of a thread by using the routines shown in the slide. Calls to *pthread\_setcancelstate* and *pthread\_setcanceltype* return the previous value of the affected portion of the cancellability state.

### **Cancellation Points** pthread\_testcancel · aio\_suspend close read creat sem\_wait fcntl (when F\_SETLCKW is sigwait the command) · sigwaitinfo fsync sigsuspend mq\_receive sigtimedwait mq\_send sleep msync system nanosleep tcdrain open wait pause waitpid pthread\_cond\_wait write pthread\_cond\_timedwait pthread join **CS33 Intro to Computer Systems** XXX-33 Copyright © 2012 Thomas W. Doeppner. All rights reserved.

The slide lists all of the required cancellation points in POSIX. Note that *pthread\_mutex\_lock* is not a cancellation point. This is because if it were, then its use in any routine would make that routine a cancellation point, which would make pretty much any routine a cancellation point.

The routine *pthread\_testcancel* is strictly a cancellation point — it has no other function. If there are no pending cancels when it is called, it does nothing and simply returns.

# **Cleaning Up**

- pthread\_cleanup\_push((void)(\*routine)(void \*),void \*arg)
- pthread cleanup pop(int execute)

**CS33 Intro to Computer Systems** 

XXX-34

Copyright © 2012 Thomas W. Doeppner. All rights reserved.

When a thread acts upon a cancel, its ultimate fate has been established, but it first gets a chance to clean up. Associated with each thread may be a stack of *cleanup handlers*. Such handlers are pushed onto the stack via calls to *pthread\_cleanup\_push* and popped off the stack via calls to *pthread\_cleanup\_pop*. Thus when a thread acts on a cancel or when it calls *pthread\_exit*, it calls each of the cleanup handlers in turn, giving the argument that was supplied as the second parameter of *pthread\_cleanup\_push*. Once all the cleanup handlers have been called, the thread terminates.

The two routines *pthread\_cleanup\_push* and *pthread\_cleanup\_pop* are intended to act as left and right parentheses, and thus should always be paired (in fact, they may actually be implemented as macros: the former contains an unmatched "{", the latter an unmatched "}"). The argument to the latter routine indicates whether or not the cleanup function should be called as a side effect of calling *pthread\_cleanup\_pop*.

# fd = open(file, O\_RDONLY); pthread\_cleanup\_push( close\_file, fd); while(1) { read(fd, buffer, buf\_size); // ... } pthread\_cleanup\_pop(0); void close\_file(int fd) { close(fd); close(fd); } pthread\_cleanup\_pop(0);

Here is a simple example of the use of a cleanup handler in conjunction with cancellation. The thread executing the code on the left, which has pushed a cleanup handler on its stack, makes successive calls to *read*, which is a cancellation point. Assuming the thread has cancellation enabled and set to deferred, if the thread is canceled, it will notice the cancel within *read*. It will then walk through its stack of cleanup handlers, first calling *close\_file*, then any others that might be on the stack. Finally, the thread terminates.

XXX-35 Copyright © 2012 Thomas W. Doeppner. All rights reserved.

**CS33 Intro to Computer Systems** 

## **Cancellation and Conditions**

```
pthread_mutex_lock(&m);
pthread_cleanup_push(
    pthread_mutex_unlock, &m);
while(should_wait)
    pthread_cond_wait(&cv, &m);

// ... (code containing other cancellation points)
pthread_cleanup_pop(1);
CS33 Intro to Computer Systems

XXX-36 Copyright © 2012 Thomas W. Doeppner. All rights reserved.
```

In this example we handle cancels that might occur while a thread is blocked within <code>pthread\_cond\_wait</code>. Again we assume the thread has cancels enabled and deferred. The thread first pushes a cleanup handler on its stack—in this case the cleanup handler unlocks the mutex. The thread then loops, calling <code>pthread\_cond\_wait</code>, a cancellation point. If it receives a cancel, the cleanup handler won't be called until the mutex has been reacquired. Thus we are certain that when the cleanup handler is called, the mutex is locked.

What's important here is that we make sure the thread does not terminate without releasing its lock on the mutex m. If the thread acts on a cancel within  $pthread\_cond\_wait$  and the cleanup handler were invoked without first taking the mutex, this would be difficult to guarantee, since we wouldn't know if the thread had the mutex locked (and thus needs to unlock it) when it's in the cleanup handler.

### Cleaning Up and Asynchrony node\_t \*makenode(int val) { node mangler() { node t \*node = NULL; pthread setcanceltype( pthread cleanup push ( CANCEL ASYNCHRONOUS, remove node, node); node = (node t \*) malloc( pthread cleanup push ( sizeof(\*node)); cleanup, node); ... // initialize node node = makenode(value); pthread cleanup pop(0); return (node); pthread cleanup pop(0); void remove node(node t \*node) { void cleanup(node\_t \*node) { if (node != NULL) free (node); **CS33 Intro to Computer Systems** Copyright © 2012 Thomas W. Doeppner. All rights reserved

Here is another example of the use of cleanup handlers. We have set the response to cancels to be *asynchronous*, established a cleanup handler, and called the routine *makenode*. This routine pushes its own cleanup handler on the stack, calls *malloc*, does some further initialization of the node, and then pops its cleanup handler from the stack and returns to the caller.

Unfortunately, the fact that we have set the cancellation response to be *asynchronous* has made this program unsafe. For example, suppose a cancel occurs while the thread is in *malloc*: memory has been allocated but its address has not yet been assigned to *node*. We enter the cleanup handler, but because *node*'s value is still NULL, no cleanup takes place. Similarly, if a cancel occurs while the thread is in *makenode*, just after it pops its cleanup handler but before it returns, we again cannot clean up the storage that had been allocated.

If, on the other hand, we had left the response to cancels as *deferred*, none of these problems would be present — a cancel would not be acted upon inside *malloc* or just before we return from *makenode*. Similar to the notion of *async-signal safety* there is also a notion of *async-cancel safety*. *Malloc* and *makenode* are examples of routines that are not *async-cancel-safe*: it is not safe to call them when the response to cancels is asynchronous.

As a general rule, asynchronous cancellability should be used sparingly, if at all. It perhaps makes sense to use it only if a thread is performing a long computation that contains no cancellation points and if, of course, it calls only async-cancel-safe routines.

# What's Async-Cancel-Safe?

- · What can be terminated at an arbitrary moment with no ill effects?
  - pure functions
    - » no modification of anything with a lifetime longer than the function call
    - » no modification of anything visible to other threads
    - » produce a value or an error indication

**CS33 Intro to Computer Systems** 

XXX-38 Copyright © 2012 Thomas W. Doeppner. All rights reserved.