














HUMERAL INTRAOSSEOUS (EZ-IO®)


Continued...



GENTLY PIERCE the skin and power or manually advance the needle set until the needle tip touches the bone.



With consistent steady downward pressure, twist the needle set back and forth (or squeeze the driver's trigger) until you penetrate the bone cortex.




UNSCREW the stylet counterclockwise and remove stylet from catheter. If using a mechanical driver, gently remove the drill from the needle.


STEP 12 NOTE: An obvious give or pop is felt when the desired depth is obtained.



PLACE the stylet in a sharps container.




SECURE the site with an EZ-IO stabilizer, if available.
NOTE: If a stabilizer is unavailable, secure with bulky dressing and tape to prevent elevated extension tubing from becoming dislodged during casualty care or movement.




CONNECT primed extension set through the 90-degree IO tubing to the Luer lock EZ-IO hub.




17 ASPIRATE to confirm needle is in the marrow (should see flash of blood-tinged material) and flush catheter with 10 ml flush using a rapid infusion.



ASSESS for signs of infiltration or complications.



19 PREPARE for fluid or medication administration.



DOCUMENT all findings and treatments on a DD Form 1380 TCCC Casualty Card and attach it to the casualty.