the trusted technology learning source

<u>Home</u> > <u>Articles</u> > <u>Operating Systems, Server</u> > <u>Linux/UNIX/Open Source</u>

# **Linux Scheduling and Kernel Synchronization**

By <u>Gordon Fischer</u>, <u>Claudia Salzberg Rodriguez</u>, <u>Claudia Salzberg</u>, <u>Steven Smolski</u> Nov 11, 2005



Page 1 of 6 Next >

The Linux kernel is a multitasking kernel, which means that many processes can run as if they were the only process on the system. The way in which an operating system chooses which process at a given time has access to a system's CPU(s) is controlled by a scheduler. This chapter covers the Linux scheduler, preemption in Linux, and the Linux system clock and timers.

# This chapter is from the book



<u>Linux Kernel Primer, The: A Top-Down Approach for x86 and PowerPC Architectures</u>

Learn More 📜 Buy

# **Related Resources**



# Unux Kernel Development

# Development,, 3rd Edition

By <u>Robert Love</u> eBook (Watermarked) \$31.99



# <u>Linux Kernel Development,</u> <u>3rd Edition</u>

By <u>Robert Love</u> Book \$39.99



# <u>Debugging Linux Systems</u> (<u>Digital Short Cut</u>)

By <u>Sreekrishnan</u> <u>Venkateswaran</u>

eBook (Watermarked) \$7.99

See All Related Store Items

For more information on Linux, visit our <u>Linux Reference Guide</u> or sign up for our <u>Linux Newsletter</u>

In this chapter

- 7.1 Linux Scheduler
- 7.2 Preemption
- 7.3 Spinlocks and Semaphores
- 7.4 System Clock: Of Time and Timers
- Summary
- Exercises

The Linux kernel is a multitasking kernel, which means that many processes can run as if they were the only process on the system. The way in which an operating system chooses which process at a given time has access to a system's CPU(s) is controlled by a scheduler.

The scheduler is responsible for swapping CPU access between different processes and for choosing the order in which processes obtain CPU access. Linux, like most operating systems, triggers the scheduler by using a timer interrupt. When this timer goes off, the kernel needs to decide whether to yield the CPU to a process different than the current process and, if a yield occurs, which process gets the CPU next. The amount of time between the timer interrupt is called a timeslice.

System processes tend to fall into two types: interactive and non-interactive. Interactive processes are heavily dependent upon I/O and, as a result, do not usually use their entire timeslice and, instead, yield the CPU to another process. Non-interactive processes are heavily dependent on the CPU and typically use most, if not all, of their timeslice. The scheduler has to balance the requirements of these two types of processes and attempt to ensure every process gets enough time to accomplish its task without detrimentally affecting the execution of other processes.

Linux, like some schedulers, distinguishes between one more type of process: a real-time process. Real-time processes must execute in real time. Linux has support for real-time processes, but those exist outside of the scheduler logic. Put simply, the Linux scheduler treats any process marked as real-time as a higher priority than any other process. It is up to the developer of the real-time processes to ensure that these processes do not hog the CPU and eventually yield.

Schedulers typically use some type of process queue to manage the execution of processes on the system. In Linux, this process queue is called the run queue. The run queue is described fully in Chapter 3, "Processes: The Principal Model of Execution," but let's recap some of the fundamentals here because of the close tie between the scheduler and the run queue.

In Linux, the run queue is composed of two priority arrays:

- Active. Stores processes that have not yet used up their timeslice
- Expired. Stores processes that have used up their timeslice

From a high level, the scheduler's job in Linux is to take the highest priority active processes, let them use the CPU to execute, and place them in the expired array when they use up their timeslice. With this high-level framework in mind, let's closely look at how the Linux scheduler operates.

# 7.1 Linux Scheduler

The 2.6 Linux kernel introduces a completely new scheduler that's commonly referred to as the O(1) scheduler. The scheduler can perform the scheduling of a task in constant time.<sup>2</sup> Chapter 3 addressed the basic structure of the scheduler and how a newly created process is initialized for it. This section describes how a task is executed on a single CPU system. There are some mentions of code for scheduling across multiple CPU (SMP) systems but, in general, the same scheduling process applies across CPUs. We then describe how the scheduler switches out the currently running process, performing what is called a context switch, and then we touch on the other significant change in the 2.6 kernel: preemption.

From a high level, the scheduler is simply a grouping of functions that operate on given data structures. Nearly all the code implementing the scheduler can be found in kernel/sched.c and include/linux/sched.h. One important point to mention early on is how the scheduler code uses the terms "task" and "process" interchangeably. Occasionally, code comments also use "thread" to refer to a task or process. A task, or process, in the scheduler is a collection of data structures and flow of control. The scheduler code also refers to a task struct, which is a data structure the Linux kernel uses to keep track of processes.<sup>2</sup>

# 7.1.1 Choosing the Next Task

After a process has been initialized and placed on a run queue, at some time, it should have access to the CPU to execute. The two functions that are responsible for passing CPU control to

different processes are schedule() and scheduler\_tick(). scheduler\_tick() is a system timer that the kernel periodically calls and marks processes as needing rescheduling. When a timer event occurs, the current process is put on hold and the Linux kernel itself takes control of the CPU. When the timer event finishes, the Linux kernel normally passes control back to the process that was put on hold. However, when the held process has been marked as needing rescheduling, the kernel calls schedule() to choose which process to activate instead of the process that was executing before the kernel took control. The process that was executing before the kernel took control. The process that was executing before the kernel took control from the kernel; this is called kernel preemption. In the following sections, we assume that the scheduler decides which of two user space processes gains CPU control.

#### **Figure**



Figure 7.1 Scheduling Processes

*Process B* executes for a while and then voluntarily yields the CPU. This commonly occurs when a process waits on some resource. *B* calls schedule(), which chooses *Process C* to execute next.

*Process C* executes until scheduler\_tick() occurs, which does not mark *C* as nee rescheduling. This results in schedule() not being called and *C* regains control of t

*Process C* yields by calling schedule(), which determines that *Process A* should gai the CPU and A starts to execute again.

We first examine schedule(), which is how the Linux kernel decides which process next, and then we examine scheduler\_tick(), which is how the kernel determin processes need to yield the CPU. The combined effects of these functions demonstra of control within the scheduler:

# This chapter is from the book



<u>Linux Kernel Primer, The: A Top-Down Approach for</u> x86 and PowerPC Architectures

Learn More 📜 Buy

```
kernel/sched.c
2184 asmlinkage void schedule(void)
2185 {
2186 long *switch_count;
     task_t *prev, *next;
2187
2188 runqueue_t *rq;
2189 prio_array_t *array;
2190 struct list_head *queue;
2191 unsigned long long now;
2192
     unsigned long run time;
2193
     int idx;
2194
2195
2196 * Test if we are atomic. Since do_exit() needs to call into
     * schedule() atomically, we ignore that path for now.
2197
     * Otherwise, whine if we are scheduling when we should not be.
2198
2199 */
2200 if (likely(!(current->state & (TASK_DEAD | TASK_ZOMBIE)))) {
      if (unlikely(in_atomic())) {
2201
2202
       printk(KERN_ERR "bad: scheduling while atomic!\n ");
2203
       dump_stack();
2204
      }
2205
2206
2207 need_resched:
2208 preempt_disable();
```

```
2209 prev = current;
2210 rq = this_rq();
2211
2212 release_kernel_lock(prev);
2213 now = sched_clock();
2214 if (likely(now - prev->timestamp < NS_MAX_SLEEP_AVG))
2215
      run_time = now - prev->timestamp;
2216 else
2217
      run_time = NS_MAX_SLEEP_AVG;
2218
2219 /*
2220 * Tasks with interactive credits get charged less run_time
     * at high sleep_avg to delay them losing their interactive
2221
2222
2223 */
2224 if (HIGH_CREDIT(prev))
2225 run_time /= (CURRENT_BONUS(prev) ? : 1);
```

# Lines 2213-2218

We calculate the length of time for which the process on the scheduler has been active. If the process has been active for longer than the average maximum sleep time (NS\_MAX\_SLEEP\_AVG), we set its runtime to the average maximum sleep time.

This is what the Linux kernel code calls a timeslice in other sections of the code. A timeslice refers to both the amount of time between scheduler interrupts and the length of time a process has spent using the CPU. If a process exhausts its timeslice, the process expires and is no longer active. The timestamp is an absolute value that determines for how long a process has used the CPU. The scheduler uses timestamps to decrement the timeslice of processes that have been using the CPU.

For example, suppose Process A has a timeslice of 50 clock cycles. It uses the CPU for 5 clock cycles and then yields the CPU to another process. The kernel uses the timestamp to determine that Process A has 45 cycles left on its timeslice.

# Lines 2224-2225

Interactive processes are processes that spend much of their time waiting for input. A good example of an interactive process is the keyboard controller—most of the time the controller is waiting for input, but when it has a task to do, the user expects it to occur at a high priority.

Interactive processes, those that have an interactive credit of more than 100 (default value), get their effective run\_time divided by (sleep\_avg/ max\_sleep\_avg \* MAX\_BONUS(10)):<sup>2</sup>

```
kernel/sched.c
2226
2227
     spin_lock_irq(&rq->lock);
2228
2229 /*
2230 * if entering off of a kernel preemption go straight
2231 * to picking the next task.
2232
     switch_count = &prev->nivcsw;
2233
2234 if (prev->state && !(preempt_count() & PREEMPT_ACTIVE)) {
      switch_count = &prev->nvcsw;
2235
      if (unlikely((prev->state & TASK_INTERRUPTIBLE) &&
2236
2237
        unlikely(signal_pending(prev))))
2238
       prev->state = TASK_RUNNING;
2239
      else
2240
       deactivate_task(prev, rq);
2241 }
```

#### Line 2227

The function obtains the run queue lock because we're going to modify it.

#### Lines 2233-2241

If we have entered <code>schedule()</code> with the previous process being a kernel preemption, we leave the previous process running if a signal is pending. This means that the kernel has preempted normal processing in quick succession; thus, the code is contained in two <code>unlikely()</code> statements. If there is no further preemption, we remove the preempted process from the run queue and continue to choose the next process to run.

```
kernel/sched.c
2243 cpu = smp_processor_id();
2244 if (unlikely(!rq->nr_running)) {
      idle_balance(cpu, rq);
      if (!rq->nr_running) {
2246
2247
       next = rq->idle;
2248
       rq->expired_timestamp = 0;
2249
       wake_sleeping_dependent(cpu, rq);
2250
       goto switch_tasks;
2251
2252
2253
2254
     array = rq->active;
2255
     if (unlikely(!array->nr_active)) {
2256
       * Switch the active and expired arrays.
2257
      */
2258
2259
      rq->active = rq->expired;
2260
      rq->expired = array;
      array = rq->active;
2261
2262
      rq->expired_timestamp = 0;
      rq->best_expired_prio = MAX_PRIO;
2263
2264 }
```

# Line 2243

We grab the current CPU identifier via smp\_processor\_id().

# Lines 2244-2252

If the run queue has no processes on it, we set the next process to the idle process and reset the run queue's expired timestamp to 0. On a multiprocessor system, we first check if any processes are running on other CPUs that this CPU can take. In effect, we load balance idle processes across all CPUs in the system. Only if no processes can be moved from the other CPUs do we set the run queue's next process to idle and reset the expired timestamp.

# Lines 2255-2264

If the run queue's active array is empty, we switch the active and expired array pointers before choosing a new process to run.

```
kernel/sched.c
2266  idx = sched_find_first_bit(array->bitmap);
2267  queue = array->queue + idx;
2268  next = list_entry(queue->next, task_t, run_list);
2269
2270  if (dependent_sleeper(cpu, rq, next)) {
2271   next = rq->idle;
2272   goto switch_tasks;
2273  }
2274
2275  if (!rt_task(next) && next->activated > 0) {
2276  unsigned long long delta = now - next->timestamp;
```

```
2277
2278
      if (next->activated == 1)
       delta = delta * (ON_RUNQUEUE_WEIGHT * 128 / 100) / 128;
2279
2280
2281
      array = next->array;
      dequeue_task(next, array);
2282
      recalc_task_prio(next, next->timestamp + delta);
2283
2284
      enqueue_task(next, array);
2285 }
next->activated = 0;
```

# Lines 2266-2268

The scheduler finds the highest priority process to run via sched\_find\_first\_bit() and then sets up queue to point to the list held in the priority array at the specified location. next is initialized to the first process in queue.

# Lines 2270-2273

If the process to be activated is dependent on a sibling that is sleeping, we choose a new process to be activated and jump to switch\_tasks to continue the scheduling function.

Suppose that we have Process A that spawned Process B to read from a device and that Process A was waiting for Process B to finish before continuing. If the scheduler chooses Process A for activation, this section of code, dependent\_sleeper(), determines that Process A is waiting on Process B and chooses an entirely new process to activate.

# Lines 2275-2285

If the process' activated attribute is greater than 0, and the next process is not a real-time task, we remove it from queue, recalculate its priority, and enqueue it again.

# Line 2286

We set the process' activated attribute to 0, and then run with it.

```
kernel/sched.c
2287 switch_tasks:
2288 prefetch(next);
2289 clear_tsk_need_resched(prev);
2290 RCU_qsctr(task_cpu(prev))++;
2291
2292
      prev->sleep_avg -= run_time;
2293 if ((long)prev->sleep_avg <= 0) {
2294
      prev->sleep_avg = 0;
      if (!(HIGH_CREDIT(prev) || LOW_CREDIT(prev)))
2295
2296
       prev->interactive_credit--;
2297 }
2298
     prev->timestamp = now;
2299
2300 if (likely(prev != next)) {
2301
      next->timestamp = now;
2302
      rq->nr switches++;
      rq->curr = next;
2303
2304
      ++*switch_count;
2305
2306
      prepare_arch_switch(rq, next);
2307
      prev = context_switch(rq, prev, next);
2308
      barrier();
2309
2310
      finish_task_switch(prev);
2311 } else
2312
       spin_unlock_irq(&rq->lock);
2313
2314
     reacquire_kernel_lock(current);
2315
     preempt_enable_no_resched();
2316 if (test_thread_flag(TIF_NEED_RESCHED))
      goto need_resched;
```

```
2318 }
```

#### Line 2288

We attempt to get the memory of the new process' task structure into the CPU's L1 cache. (See include/linux/prefetch.h for more information.)

#### Line 2290

Because we're going through a context switch, we need to inform the current CPU that we're doing so. This allows a multi-CPU device to ensure data that is shared across CPUs is accessed exclusively. This process is called read-copy updating. For more information, see <a href="http://lse.sourceforge.net/locking/rcupdate.html">http://lse.sourceforge.net/locking/rcupdate.html</a>.

#### Lines 2292-2298

We decrement the previous process' sleep\_avg attribute by the amount of time it ran, adjusting for negative values. If the process is neither interactive nor non-interactive, its interactive credit is between high and low, so we decrement its interactive credit because it had a low sleep average. We update its timestamp to the current time. This operation helps the scheduler keep track of how much time a given process has spent using the CPU and estimate how much time it will use the CPU in the future.

#### Lines 2300-2304

If we haven't chosen the same process, we set the new process' timestamp, increment the run queue counters, and set the current process to the new process.

#### Lines 2306-2308

These lines describe the assembly language context\_switch(). Hold on for a few paragraphs as we delve into the explanation of context switching in the next section.

# Lines 2314-2318

We reacquire the kernel lock, enable preemption, and see if we need to reschedule immediately; if so, we go back to the top of schedule().

It's possible that after we perform the context\_switch(), we need to reschedule. Perhaps scheduler\_tick() has marked the new process as needing rescheduling or, when we enable preemption, it gets marked. We keep rescheduling processes (and context switching them) until one is found that doesn't need rescheduling. The process that leaves schedule() becomes the new process executing on this CPU.

# 7.1.2 Context Switch

Called from schedule() in /kernel/sched.c, context\_switch() does the machinespecific work of switching the memory environment and the processor state. In the abstract, context\_switch swaps the current task with the next task. The function context\_switch() begins executing the next task and returns a pointer to the task structure of the task that was running before the call:

```
kernel/sched.c
1048 /*
1049 * context_switch - switch to the new MM and the new
1050 * thread's register state.
1051 */
1052 static inline
1053 task_t * context_switch(runqueue_t *rq, task_t *prev, task_t *next
1054 {
1055 struct mm_struct *mm = next->mm;
1056 struct mm_struct *oldmm = prev->active_mm;
...
1063 switch_mm(oldmm, mm, next);
...
1072 switch_to(prev, next, prev);
```

```
1073
1074 return prev;
1075 }
```

Here, we describe the two jobs of context\_switch: one to switch the virtual memory mapping and one to switch the task/thread structure. The first job, which the function switch\_mm() carries out, uses many of the hardware-dependent memory management structures and registers:

```
/include/asm-i386/mmu context.h
026 static inline void switch_mm(struct mm_struct *prev,
027
     struct mm_struct *next,
028
     struct task_struct *tsk)
029 {
030 int cpu = smp_processor_id();
031
032 if (likely(prev != next)) {
033 /* stop flush ipis for the previous mm */
034 cpu_clear(cpu, prev->cpu_vm_mask);
035 #ifdef CONFIG_SMP
036 cpu_tlbstate[cpu].state = TLBSTATE_OK;
037 cpu_tlbstate[cpu].active_mm = next;
038 #endif
039 cpu_set(cpu, next->cpu_vm_mask);
040
041 /* Re-load page tables */
042 load_cr3(next->pgd);
043
044
045
    * load the LDT, if the LDT is different:
046 */
047 if (unlikely(prev->context.ldt != next->context.ldt))
048
     load LDT nolock(&next->context, cpu);
049 }
050 #ifdef CONFIG_SMP
051 else {
```

# Line 39

Bind the new task to the current processor.

# Line 42

The code for switching the memory context utilizes the x86 hardware register cr3, which holds the base address of all paging operations for a given process. The new page global descriptor is loaded here from next->pgd.

# Line 47

Most processes share the same LDT. If another LDT is required by this process, it is loaded here from the new next->context structure.

The other half of function context\_switch() in /kernel/sched.c then calls the macro switch\_to(), which calls the C function \_\_switch\_to(). The delineation of architecture independence to architecture dependence for both x86 and PPC is the switch\_to() macro.

# 7.1.2.1

Following the x86 Trail of switch\_to()

The x86 code is more compact than PPC. The following is the architecture-dependent code for \_\_switch\_to(). task\_struct (not thread\_struct) is passed to \_\_switch\_to(). The code discussed next is inline assembler code for calling the C function \_\_switch\_to() (line

23) with the proper task\_struct structures as parameters.

The context\_switch takes three task pointers: prev, next, and last. In addition, there is the current pointer.

Let us now explain, at a high level, what occurs when switch\_to() is called and how the task pointers change after a call to switch\_to().

# **Figure**

7.2 shows three switch\_to() calls using three processes: A, B, and C.



Figure 7.2 switch\_to Calls

We want to switch A and B. Before, the first call we have

- Current → A
- Prev  $\rightarrow$  A, next  $\rightarrow$  B

After the first call:

- Current → B
- Last → A

Now, we want to switch B and C. Before the second call, we have

- Current → B
- Prev  $\rightarrow$  B, next  $\rightarrow$  C

After the second call:

- Current  $\rightarrow$  C
- Last  $\rightarrow$  B

Returning from the second call, current now points to task (C) and last points to (B).

The method continues with task (A) being swapped in once again, and so on.

The inline assembly of the switch\_to() function is an excellent example of assembly magic in the kernel. It is also a good example of the gcc C extensions. See Chapter 2, "Exploration Toolkit," for a tutorial featuring this function. Now, we carefully walk through this code block.

```
/include/asm-i386/system.h

012 extern struct task_struct * FASTCALL(__switch_to(struct task_struct struct task_struct *next));

015 #define switch_to(prev,next,last) do {
016 unsigned long esi,edi; \
017 asm volatile("pushfl\n\t" \
018 "pushl %%ebp\n\t" \
019 "movl %%esp,%0\n\t" /* save ESP */ \
020 "movl %5,%%esp\n\t" /* restore ESP */ \
021 "movl $1f,%1\n\t" /* save EIP */ \
022 "pushl %6\n\t" /* restore EIP */ \
023 "jmp __switch_to\n" \
```

```
023 "1:\t" \
024 "popl %%ebp\n\t" \
025 "popfl" \
026 :"=m" (prev->thread.esp),"=m" (prev->thread.eip), \
027 "=a" (last),"=S" (esi),"=D" (edi) \
028 :"m" (next->thread.esp),"m" (next->thread.eip), \
029 "2" (prev), "d" (next)); \
030 } while (0)
```

#### Line 12

The FASTCALL macro resolves to \_\_attribute\_\_ regparm(3), which forces the parameters to be passed in registers rather than stack.

#### Lines 15-16

The do  $\{\}$  while (0) construct allows (among other things) the macro to have local the variables esi and edi. Remember, these are just local variables with familiar names.

**Current and the Task Structure** 

As we explore the kernel, whenever we need to retrieve or store information on the task (or process) which is *currently* running on a given processor, we use the global variable current to reference its task structure. For example, current->pid holds the process ID. Linux allows for a quick (and clever) method of referencing the current task structure.

Every process is assigned 8K of contiguous memory when it is created. (With Linux 2.6, there is a compile-time option to use 4K instead of 8K.) This 8K segment is occupied by the task structure and the kernel stack for the given process. Upon process creation, Linux puts the task structure at the low end of the 8K memory and the kernel stack pointer starts at the high end. The kernel stack pointer (especially for x86 and r1 for PPC) decrements as data is pushed onto the stack. Because this 8K memory region is page-aligned, its starting address (in hex notation) always ends in 0x000 (multiples of 4k bytes).

As you might have guessed, the clever method by which Linux references the current task structure is to AND the contents of the stack pointer with 0xffff\_f000. Recent versions of the PPC Linux kernel have taken this one step further by dedicating General Purpose Register 2 to holding the current pointer.

#### Lines 17 and 30

The construct asm volatile () encloses the inline assembly block and the volatile keyword assures that the compiler will not change (optimize) the routine in any way.

# Lines 17-18

Push the flags and ebp registers onto the stack. (Note: We are still using the stack associated with the prev task.)

#### Line 19

This line saves the current stack pointer esp to the prev task structure.

# Line 20

Move the stack pointer from the next task structure to the current processor  ${\tt esp}.$ 

NOTE

By definition, we have just made a context switch.

We are now with a new kernel stack and thus, any reference to current is to the new (next) task structure.

#### Line 21

Save the return address for prev into its task structure. This is where the prev task resumes when it is restarted.

#### Line 22

Push the return address (from when we return from \_\_switch\_to()) onto the stack. This is the eip from next. The eip was saved into its task structure (on line 21) when it was stopped, or preempted the last time.

#### Line 23

Jump to the C function \_\_switch\_to() to update the following:

- The next thread structure with the kernel stack pointer
- Thread local storage descriptor for this processor
- fs and gs for prev and next, if needed
- · Debug registers, if needed
- I/O bitmaps, if needed

\_\_switch\_to() then returns the updated prev task structure.

#### Lines 24-25

Pop the base pointer and flags registers from the new (next task) kernel stack.

#### Lines 26-29

These are the output and input parameters to the inline assembly routine. See the "Inline Assembly" section in Chapter 2 for more information on the *constraints* put on these parameters.

## Line 29

By way of assembler magic, prev is returned in eax, which is the third positional parameter. In other words, the input parameter prev is passed out of the switch\_to() macro as the output parameter last.

Because switch\_to() is a macro, it was executed inline with the code that called it in context\_switch(). It does not return as functions normally do.

For the sake of clarity, remember that switch\_to() passes back prev in the eax register, execution then continues in context\_switch(), where the next instruction is return prev (line 1074 of kernel/sched.c). This allows context\_switch() to pass back a pointer to the last task running.

# 7.1.2.2

Following the PPC context\_switch()

The PPC code for context\_switch() has slightly more work to do for the same results. Unlike the cr3 register in x86 architecture, the PPC uses hash functions to point to context environments. The following code for switch\_mm() touches on these functions, but Chapter 4, "Memory Management," offers a deeper discussion.

Here is the routine for switch\_mm() which, in turn, calls the routine set\_context().

```
/include/asm-ppc/mmu_context.h
155 static inline void switch_mm(struct mm_struct *prev, struct
mm_struct *next,struct task_struct *tsk)
```

```
156 {
157  tsk->thread.pgdir = next->pgd;
158  get_mmu_context(next);
159  set_context(next->context, next->pgd);
160 }
```

#### Line 157

The page global directory (segment register) for the new thread is made to point to the next->pgd pointer.

#### Line 158

The context field of the mm\_struct (next->context) passed into switch\_mm() is updated to the value of the appropriate context. This information comes from a global reference to the variable context\_map[], which contains a series of bitmap fields.

#### Line 159

This is the call to the assembly routine set\_context. Below is the code and discussion of this routine. Upon execution of the blr instruction on line 1468, the code returns to the switch\_mm routine.

```
/arch/ppc/kernel/head.S
1437 _GLOBAL(set_context)
1438 mulli r3,r3,897 /* multiply context by skew factor */
1439 rlwinm r3,r3,4,8,27 /* VSID = (context & 0xfffff) << 4 */
1440 addis r3,r3,0x6000 /* Set Ks, Ku bits */
1441 li r0, NUM_USER_SEGMENTS
1442 mtctr r0
1457 3: isync
1461 mtsrin r3,r4
1462 addi r3,r3,0x111 /* next VSID */
1463 rlwinm r3,r3,0,8,3 /* clear out any overflow from VSID field */
1464 addis r4,r4,0x1000 /* address of next segment */
1465 bdnz 3b
1466 sync
1467 isync
1468 blr
```

# Lines 1437-1440

The context field of the mm\_struct (next->context) passed into set\_context() by way of r3, sets up the hash function for PPC segmentation.

# Lines 1461-1465

The pgd field of the mm\_struct (next->pgd) passed into set\_context() by way of r4, points to the segment registers.

Segmentation is the basis of PPC memory management (refer to Chapter 4). Upon returning from set\_context(), the mm\_struct next is initialized to the proper memory regions and is returned to switch\_mm().

# 7.1.2.3 Following the PPC Trail of switch\_to()

The result of the PPC implementation of switch\_to() is necessarily identical to the x86 call; it takes in the current and next task pointers and returns a pointer to the previously running task:

On line 88, \_\_switch\_to() takes its parameters as task\_struct type and, at line 93, \_switch() takes its parameters as thread\_struct. This is because the thread entry within task\_struct contains the architecture-dependent processor register information of interest for the given thread. Now, let us examine the implementation of \_\_switch\_to():

```
/arch/ppc/kernel/process.c

200 struct task_struct *__switch_to(struct task_struct *prev,
    struct task_struct *new)

201 {

202    struct thread_struct *new_thread, *old_thread;

203    unsigned long s;

204    struct task_struct *last;

205    local_irq_save(s);
...

247    new_thread = &new->thread;

248    old_thread = &current->thread;

249    last = _switch(old_thread, new_thread);

250    local_irq_restore(s);

251    return last;

252 }
```

#### Line 205

Disable interrupts before the context switch.

# Lines 247-248

Still running under the context of the *old* thread, pass the pointers to the thread structure to the \_switch() function.

#### Line 249

\_switch() is the assembly routine called to do the work of switching the two thread structures (see the following section).

## Line 250

Enable interrupts after the context switch.

To better understand what needs to be swapped within a PPC thread, we need to examine the thread\_struct passed in on line 249.

Recall from the exploration of the x86 context switch that the switch does not officially occur until we are pointing to a new kernel stack. This happens in \_switch().

# Tracing the PPC Code for \_switch()

By convention, the parameters of a PPC C function (from left to right) are held in r3, r4, r5, ...r12. Upon entry into switch(), r3 points to the thread\_struct for the current task and r4 points to the thread\_struct for the new task:

```
/arch/ppc/kernel/entry.S
437 _GLOBAL(_switch)
438 stwu r1,-INT_FRAME_SIZE(r1)
439 mflr r0
440 stw r0, INT_FRAME_SIZE+4(r1)
441 /* r3-r12 are caller saved -- Cort */
442
    SAVE_NVGPRS(r1)
443 stw r0,_NIP(r1) /* Return to switch caller */
444 mfmsr r11
458 1: stw r11,_MSR(r1)
459 mfcr r10
460 stw r10,_CCR(r1)
461 stw r1,KSP(r3) /* Set old stack pointer */
462
463 tophys(r0,r4)
464 CLR_TOP32(r0)
465 mtspr SPRG3,r0/* Update current THREAD phys addr */
466 lwz r1,KSP(r4) /* Load new stack pointer */
467 /* save the old current 'last' for return value */
468 mr r3, r2
469 addi r2,r4,-THREAD /* Update current */
478 lwz r0,_CCR(r1)
479 mtcrf 0xFF,r0
480 REST_NVGPRS(r1)
481
482 lwz r4,_NIP(r1) /* Return to _switch caller in new task */
483
    mtlr r4
484 addi r1,r1,INT_FRAME_SIZE
485 blr
         -----
```

The byte-for-byte mechanics of swapping out the previous thread\_struct for the new is left as an exercise for you. It is worth noting, however, the use of r1, r2, r3, SPRG3, and r4 in \_switch() to see the basics of this operation.

### Lines 438-460

The environment is saved to the current stack with respect to the current stack pointer, r1.

#### Line 461

The entire environment is then saved into the current thread\_struct pointer passed in by way of r3.

#### Lines 463-465

SPRG3 is updated to point to the thread structure of the new task.

#### Line 466

KSP is the offset into the task structure (r4) of the new task's kernel stack pointer. The stack pointer r1 is now updated with this value. (This is the point of the PPC context switch.)

# Line 468

The current pointer to the previous task is returned from \_switch() in r3. This represents the last task.

#### Line 469

The current pointer (r2) is updated with the pointer to the new task structure (r4).

# Lines 478-486

Restore the rest of the environment from the new stack and return to the caller with the previous task structure in r3.

This concludes the explanation of context\_switch(). At this point, the processor has swapped the two processes prev and next as called by context\_switch in schedule().

```
kernel/sched.c
1709 prev = context_switch(rq, prev, next);
```

prev now points to the process that we have just switched away from and next points to the current process.

Now that we've discussed how tasks are scheduled in the Linux kernel, we can examine how tasks are told to be scheduled. Namely, what causes schedule() to be called and one process to yield the CPU to another process?

# 7.1.3 Yielding the CPU

Processes can voluntarily yield the CPU by simply calling schedule(). This is most commonly used in kernel code and device drivers that want to sleep or wait for a signal to occur. Other tasks want to continually use the CPU and the system timer must tell them to yield. The Linux kernel periodically seizes the CPU, in so doing stopping the active process, and then does a number of timer-based tasks. One of these tasks, scheduler\_tick(), is how the kernel forces a process to yield. If a process has been running for too long, the kernel does not return control to that process and instead chooses another one. We now examine how scheduler\_tick() determines if the current process must yield the CPU:

```
kernel/sched.c
1981 void scheduler_tick(int user_ticks, int sys_ticks)
1982 {
1983   int cpu = smp_processor_id();
1984   struct cpu_usage_stat *cpustat = &kstat_this_cpu.cpustat;
1985   runqueue_t *rq = this_rq();
1986   task_t *p = current;
1987
1988   rq->timestamp_last_tick = sched_clock();
1989
1990   if (rcu_pending(cpu))
1991   rcu_check_callbacks(cpu, user_ticks);
```

# Lines 1981–1986

This code block initializes the data structures that the scheduler\_tick() function needs. cpu, cpu\_usage\_stat, and rq are set to the processor ID, CPU stats and run queue of the current processor. p is a pointer to the current process executing on cpu.

### Line 1988

The run queue's last tick is set to the current time in nanoseconds.

#### Lines 1990-1991

On an SMP system, we need to check if there are any outstanding read-copy updates to perform (RCU). If so, we perform them via rcu\_check\_callback().

```
kernel/sched.c
1993  /* note: this timer irq context must be accounted for as well */
1994  if (hardirq_count() - HARDIRQ_OFFSET) {
1995    cpustat->irq += sys_ticks;
1996    sys_ticks = 0;
1997  } else if (softirq_count()) {
1998    cpustat->softirq += sys_ticks;
1999    sys_ticks = 0;
2000 }
```

```
2001
2002
      if (p == rq \rightarrow idle) {
2003
       if (atomic_read(&rq->nr_iowait) > 0)
2004
        cpustat->iowait += sys_ticks;
2005
       else
2006
        cpustat->idle += sys_ticks;
2007
       if (wake_priority_sleeper(rq))
       goto out;
2008
2009
       rebalance_tick(cpu, rq, IDLE);
2010
       return;
2011
2012 if (TASK\ NICE(p) > 0)
2013
      cpustat->nice += user_ticks;
2014 else
2015
      cpustat->user += user_ticks;
2016 cpustat->system += sys_ticks;
```

#### Lines 1994-2000

cpustat keeps track of kernel statistics, and we update the hardware and software interrupt statistics by the number of system ticks that have occurred.

#### Lines 2002-2011

If there is no currently running process, we atomically check if any processes are waiting on I/O. If so, the CPU I/O wait statistic is incremented; otherwise, the CPU idle statistic is incremented. In a uniprocessor system, rebalance\_tick() does nothing, but on a multiple processor system, rebalance\_tick() attempts to load balance the current CPU because the CPU has nothing to do.

#### Lines 2012-2016

More CPU statistics are gathered in this code block. If the current process was niced, we increment the CPU nice counter; otherwise, the user tick counter is incremented. Finally, we increment the CPU's system tick counter.

```
kernel/sched.c
2019 if (p->array != rq->active) {
2020    set_tsk_need_resched(p);
2021    goto out;
2022 }
2023    spin_lock(&rq->lock);
```

#### Lines 2019-2022

Here, we see why we store a pointer to a priority array within the task\_struct of the process. The scheduler checks the current process to see if it is no longer active. If the process has expired, the scheduler sets the process' rescheduling flag and jumps to the end of the scheduler\_tick() function. At that point (lines 2092–2093), the scheduler attempts to load balance the CPU because there is no active task yet. This case occurs when the scheduler grabbed CPU control before the current process was able to schedule itself or clean up from a successful run.

## Line 2023

At this point, we know that the current process was running and not expired or nonexistent. The scheduler now wants to yield CPU control to another process; the first thing it must do is take the run queue lock.

```
kernel/sched.c
```

```
2024
2025
     * The task was running during this tick - update the
2026
     * time slice counter. Note: we do not update a thread's
     * priority until it either goes to sleep or uses up its
2028 * timeslice. This makes it possible for interactive tasks
2029 * to use up their timeslices at their highest priority levels.
2030 */
     if (unlikely(rt_task(p))) {
2031
2032
2033
       * RR tasks need a special form of timeslice management.
2034
       * FIFO tasks have no timeslices.
2035
      if ((p->policy == SCHED_RR) && !--p->time_slice) {
2036
       p->time_slice = task_timeslice(p);
2037
2038
        p->first_time_slice = 0;
2039
        set_tsk_need_resched(p);
2040
2041
        /* put it at the end of the queue: */
2042
        dequeue_task(p, rq->active);
2043
       enqueue_task(p, rq->active);
2044
2045
      goto out_unlock;
2046 }
```

#### Lines 2031-2046

The easiest case for the scheduler occurs when the current process is a real-time task. Real-time tasks always have a higher priority than any other tasks. If the task is a FIFO task and was running, it should continue its operation so we jump to the end of the function and release the run queue lock. If the current process is a round-robin real-time task, we decrement its timeslice. If the task has no more timeslice, it's time to schedule another round-robin real-time task. The current task has its new timeslice calculated by task\_timeslice(). Then the task has its first timeslice reset. The task is then marked as needing rescheduling and, finally, the task is put at the end of the round-robin real-time tasklist by removing it from the run queue's active array and adding it back in. The scheduler then jumps to the end of the function and releases the run queue lock.

```
kernel/sched.c
2047 if (!--p->time slice) {
2048
      dequeue_task(p, rq->active);
2049
      set_tsk_need_resched(p);
2050
      p->prio = effective_prio(p);
2051
      p->time_slice = task_timeslice(p);
2052
      p->first_time_slice = 0;
2053
      if (!rq->expired_timestamp)
2054
2055
       rq->expired_timestamp = jiffies;
2056
      if (!TASK_INTERACTIVE(p) || EXPIRED_STARVING(rq)) {
2057
        enqueue_task(p, rq->expired);
2058
       if (p->static_prio < rq->best_expired_prio)
2059
         rq->best_expired_prio = p->static_prio;
2060
       } else
2061
        enqueue_task(p, rq->active);
2062
     } else {
```

# Lines 2047-2061

At this point, the scheduler knows that the current process is not a real-time process. It decrements the process' timeslice and, in this section, the process' timeslice has been exhausted and reached 0. The scheduler removes the task from the active array and sets the process' rescheduling flag. The priority of the task is recalculated and its timeslice is reset. Both of these operations take into account prior process activity.<sup>8</sup> If the run queue's expired

timestamp is 0, which usually occurs when there are no more processes on the run queue's active array, we set it to jiffies.

```
Jiffies is a 32-bit variable counting the number of ticks since the system has been booted. This is approximately 497 days before the number wraps around to 0 on a 100HZ system. The macro on line 20 is the suggested method of accessing this value as a u64. There are also macros to help detect wrapping in include/jiffies.h.

include/linux/jiffies.h
017 extern unsigned long volatile jiffies;
020 u64 get_jiffies_64(void);
```

We normally favor interactive tasks by replacing them on the active priority array of the run queue; this is the else clause on line 2060. However, we don't want to starve expired tasks. To determine if expired tasks have been waiting too long for CPU time, we use EXPIRED\_STARVING() (see EXPIRED\_STARVING on line 1968). The function returns true if the first expired task has been waiting an "unreasonable" amount of time or if the expired array contains a task that has a greater priority than the current process. The unreasonableness of waiting is load-dependent and the swapping of the active and expired arrays decrease with an increasing number of running tasks.

If the task is not interactive or expired tasks are starving, the scheduler takes the current process and enqueues it onto the run queue's expired priority array. If the current process' static priority is higher than the expired run queue's highest priority task, we update the run queue to reflect the fact that the expired array now has a higher priority than before. (Remember that high-priority tasks have low numbers in Linux, thus, the (<) in the code.)

```
kernel/sched.c
2062 } else {
2063
2064
       * Prevent a too long timeslice allowing a task to monopolize
2065
       * the CPU. We do this by splitting up the timeslice into
2066
       * smaller pieces.
2067
2068
       * Note: this does not mean the task's timeslices expire or
2069
       ^{st} get lost in any way, they just might be preempted by
       * another task of equal priority. (one with higher
2070
2071
       * priority would have preempted this task already.) We
2072
       * requeue this task to the end of the list on this priority
2073
       * level, which is in essence a round-robin of tasks with
       * equal priority.
2074
2075
2076
       * This only applies to tasks in the interactive
       ^{st} delta range with at least TIMESLICE_GRANULARITY to requeue.
2077
2078
2079
       if (TASK_INTERACTIVE(p) && !((task_timeslice(p)
2080
        p->time_slice) % TIMESLICE_GRANULARITY(p)) &&
        (p->time slice >= TIMESLICE GRANULARITY(p)) &&
2081
2082
        (p->array == rq->active)) {
2083
2084
        dequeue_task(p, rq->active);
2085
        set_tsk_need_resched(p);
2086
        p->prio = effective_prio(p);
2087
        enqueue_task(p, rq->active);
2088
```

```
2089 }
2090 out_unlock:
2091 spin_unlock(&rq->lock);
2092 out:
2093 rebalance_tick(cpu, rq, NOT_IDLE);
2094 }
```

#### Lines 2079-2089

The final case before the scheduler is that the current process was running and still has timeslices left to run. The scheduler needs to ensure that a process with a large timeslice doesn't hog the CPU. If the task is interactive, has more timeslices than

TIMESLICE\_GRANULARITY, and was active, the scheduler removes it from the active queue. The task then has its reschedule flag set, its priority recalculated, and is placed back on the run queue's active array. This ensures that a process at a certain priority with a large timeslice doesn't starve another process of an equal priority.

#### Lines 2090-2094

The scheduler has finished rearranging the run queue and unlocks it; if executing on an SMP system, it attempts to load balance.

Combining how processes are marked to be rescheduled, via scheduler\_tick() and how processes are scheduled, via schedule() illustrates how the scheduler operates in the 2.6 Linux kernel. We now delve into the details of what the scheduler means by "priority."

# 7.1.3.1 Dynamic Priority Calculation

In previous sections, we glossed over the specifics of how a task's dynamic priority is calculated. The priority of a task is based on its prior behavior, as well as its user-specified nice value. The function that determines a task's new dynamic priority is recalc\_task\_prio():

```
kernel/sched.c
381 static void recalc_task_prio(task_t *p, unsigned long long now)
382 {
383 unsigned long long __sleep_time = now - p->timestamp;
384 unsigned long sleep_time;
385
386 if (__sleep_time > NS_MAX_SLEEP_AVG)
      sleep_time = NS_MAX_SLEEP_AVG;
387
388 else
      sleep_time = (unsigned long)__sleep_time;
389
390
391
    if (likely(sleep_time > 0)) {
392
393
      * User tasks that sleep a long time are categorised as
      \ensuremath{^*} idle and will get just interactive status to stay active &
394
395
      * prevent them suddenly becoming cpu hogs and starving
      * other processes.
396
397
      if (p->mm && p->activated != -1 &&
398
399
       sleep_time > INTERACTIVE_SLEEP(p)) {
400
        p->sleep_avg = JIFFIES_TO_NS(MAX_SLEEP_AVG -
401
          AVG_TIMESLICE);
402
        if (!HIGH_CREDIT(p))
403
         p->interactive_credit++;
404
      } else {
405
       * The lower the sleep avg a task has the more
406
407
       * rapidly it will rise with sleep time.
408
409
       sleep time *= (MAX BONUS - CURRENT BONUS(p)) ? : 1;
410
411
       * Tasks with low interactive_credit are limited to
412
       \ ^{st} one timeslice worth of sleep avg bonus.
413
414
```

```
if (LOW_CREDIT(p) &&
415
416
       sleep_time > JIFFIES_TO_NS(task_timeslice(p)))
        sleep_time = JIFFIES_TO_NS(task_timeslice(p));
417
418
419
420
       * Non high_credit tasks waking from uninterruptible
421
       * sleep are limited in their sleep_avg rise as they
       ^{st} are likely to be cpu hogs waiting on I/O
422
423
424
       if (p\rightarrow activated == -1 \&\& !HIGH\_CREDIT(p) \&\& p\rightarrow mm) {
425
        if (p->sleep_avg >= INTERACTIVE_SLEEP(p))
426
         sleep time = 0;
427
        else if (p->sleep_avg + sleep_time >=
          INTERACTIVE_SLEEP(p)) {
428
429
         p->sleep_avg = INTERACTIVE_SLEEP(p);
430
         sleep_time = 0;
431
432
       }
433
434
435
       * This code gives a bonus to interactive tasks.
436
437
       * The boost works by updating the 'average sleep time'
438
       * value here, based on ->timestamp. The more time a
439
       * task spends sleeping, the higher the average gets -
       * and the higher the priority boost gets as well.
440
441
442
       p->sleep_avg += sleep_time;
443
       if (p->sleep_avg > NS_MAX_SLEEP_AVG) {
444
445
        p->sleep_avg = NS_MAX_SLEEP_AVG;
446
        if (!HIGH_CREDIT(p))
447
         p->interactive_credit++;
448
449
      }
450
     }
452
452
     p->prio = effective_prio(p);
453 }
```

# Lines 386-389

Based on the time now, we calculate the length of time the process p has slept for and assign it to sleep\_time with a maximum value of NS\_MAX\_SLEEP\_AVG. (NS\_MAX\_SLEEP\_AVG defaults to 10 milliseconds.)

### Lines 391-404

If process p has slept, we first check to see if it has slept enough to be classified as an interactive task. If it has, when sleep\_time > INTERACTIVE\_SLEEP(p), we adjust the process' sleep average to a set value and, if p isn't classified as interactive yet, we increment p's interactive\_credit.

## Lines 405-410

A task with a low sleep average gets a higher sleep time.

#### Lines 411-418

If the task is CPU intensive, and thus classified as non-interactive, we restrict the process to having, at most, one more timeslice worth of a sleep average bonus.

# Lines 419-432

Tasks that are not yet classified as interactive (not HIGH\_CREDIT) that awake from uninterruptible sleep are restricted to having a sleep average of INTERACTIVE().

#### Lines 434-450

We add our newly calculated sleep\_time to the process' sleep average, ensuring it doesn't go over NS\_MAX\_SLEEP\_AVG. If the processes are not considered interactive but have slept for

the maximum time or longer, we increment its interactive credit.

#### Line 452

Finally, the priority is set using effective\_prio(), which takes into account the newly calculated sleep\_avg field of p. It does this by scaling the sleep average of 0..

MAX\_SLEEP\_AVG into the range of -5 to +5. Thus, a process that has a static priority of 70 can have a dynamic priority between 65 and 85, depending on its prior behavior.

One final thing: A process that is not a real-time process has a range between 101 and 140. Processes that are operating at a very high priority, 105 or less, cannot cross the real-time boundary. Thus, a high priority, highly interactive process could never have a dynamic priority of lower than 101. (Real-time processes cover 0..100 in the default configuration.)

#### 7.1.3.2 Deactivation

We already discussed how a task gets inserted into the scheduler by forking and how tasks move from the active to expired priority arrays within the CPU's run queue. But, how does a task ever get removed from a run queue?

A task can be removed from the run queue in two major ways:

- The task is preempted by the kernel and its state is not running, and there is no signal pending for the task (see line 2240 in kernel/sched.c).
- On SMP machines, the task can be removed from a run queue and placed on another run queue (see line 3384 in kernel/sched.c).

The first case normally occurs when schedule() gets called after a process puts itself to sleep on a wait queue. The task marks itself as non-running (TASK\_INTERRUPTIBLE, TASK\_UNINTERRUPTIBLE, TASK\_STOPPED, and so on) and the kernel no longer considers it for CPU access by removing it from the run queue.

The case in which the process is moved to another run queue is dealt with in the SMP section of the Linux kernel, which we do not explore here.

We now trace how a process is removed from the run queue via deactivate\_task():

```
kernel/sched.c
507 static void deactivate_task(struct task_struct *p, runqueue_t *rq)
508 {
509  rq->nr_running--;
510  if (p->state == TASK_UNINTERRUPTIBLE)
511  rq->nr_uninterruptible++;
512  dequeue_task(p, p->array);
513  p->array = NULL;
514 }
```

#### Line 509

The scheduler first decrements its count of running processes because p is no longer running.

# Lines 510-511

If the task is uninterruptible, we increment the count of uninterruptible tasks on the run queue. The corresponding decrement operation occurs when an uninterruptible process wakes up (see kernel/sched.c line 824 in the function try\_to\_wake\_up()).

# Line 512-513

Our run queue statistics are now updated so we actually remove the process from the run queue. The kernel uses the p->array field to test if a process is running and on a run queue. Because it no longer is either, we set it to NULL.

There is still some run queue management to be done; let's examine the specifics of

dequeue\_task():

```
kernel/sched.c
303 static void dequeue_task(struct task_struct *p, prio_array_t *array
304 {
305 array->nr_active--;
306 list_del(&p->run_list);
307 if (list_empty(array->queue + p->prio))
308 __clear_bit(p->prio, array->bitmap);
309 }
```

# Line 305

We adjust the number of active tasks on the priority array that process p is on—either the expired or the active array.

#### Lines 306-308

We remove the process from the list of processes in the priority array at p's priority. If the resulting list is empty, we need to clear the bit in the priority array's bitmap to show there are no longer any processes at priority p->prio().

list\_del() does all the removal in one step because p->run\_list is a list\_head
structure and thus has pointers to the previous and next entries in the list.

We have reached the point where the process is removed from the run queue and has thus been completely deactivated. If this process had a state of TASK\_INTERRUPTIBLE or TASK\_UNINTERRUPTIBLE, it could be awoken and placed back on a run queue. If the process had a state of TASK\_STOPPED, TASK\_ZOMBIE, or TASK\_DEAD, it has all of its structures removed and

**★** Share This Save To Your Account

Page 1 of 6 Next >