CS 214 / 2021-03-03 =================================
project 1 Three scenarios 1. reading from a file and writing to standard output
 reading from standard input and writing to standard output reading from a file and writing a different file Scenarios 1 and 2 are just special cases of 3
standard input is file descriptor 0 standard output is file descriptor 1 you could create a single function that reads from a file descriptor and writes its output to a file descriptor
You could easily write this function and have it handle all three cases int wrap(unsigned width, int input_fd, int output_fd);
<pre>(e.g., return value indicates whether we exceeded the page width) int error = wrap(page_width, 0, 1); // scenario 2</pre>
when we read/write from a file, we obtain a file descriptor from open Aside: since the width is always zero, why not use assert to check for bugs?
<pre>assert(width > 0); What is the idea of part I?</pre>
What do I mean by efficient? How can we handle arbitrarily long files? Question: how much memory does our program need to use? What in our input affects our memory requirements?
How much do we need to keep track of at any given moment? Answer: we never need to have more than one word in memory at a time as soon as we have complete word, we can decide whether to print it on the current line, or start a new line
once we have printed a word, we don't need it any more so our program's memory requirement is O(n), where n is the length of the longest word
<pre>we can still have additional memory use for variables, buffers, etc., but these can be O(1) size Important: you do not need to read an entire line at once -> there is no easy way to do this! do not even try!</pre>
 you do not need to build the line in memory and print it all at once this is inefficient and unnecessary
But what about buffering? we can call read with a 1-character buffer, but this adds overhead to our program - each call to read involves a system call, which requires passing control to the OS (a "context switch")
if we have a buffer of 128 characters, then we only need to call read every 128 characters (ideally) Idea: choose a buffer size (can be big or small, doesn't matter)
each time we call read, we try to fill the entire buffer e.g., if our buffer is 10 chars, we might get [Hello worl]
we iterate through the buffer - return result from read tells us how much is in the buffer we examine each character and look for the start and end of words
start of a word is a whitespace character followed by a non-WS char end of a word is a non-WS char followed by a WS char When we are in a word, we remember where it started (in the buffer)
Once we reach the end of the word, we know its length and which bytes in the buffer make up the word [Hello worl] ^ first char in word
^ last char in word word is 5 chars long at this point, we can just send that to write
-> remember, we can pass any pointer + size to write write(out_fd, &buf[word_start], word_len); But what happens when we reach the end of the buffer?
[Hello worl] ^ first char in word ^ buffer ended, possibly inside a word
<pre>-> we know how big the partial word is -> stash it somewhere -> call read again (refresh the buffer) -> overwrite the data in the buffer</pre>
-> we don't need it anymore if the new buffer starts with WS, then the stashed text is a complete word otherwise, the stashed text is part of the word we are reading
-> how you manage this is up to you [d!] -> "d!" is the end of the word we stashed
<pre>-> so the complete word was "world!" Beware words that are too large for the buffer! if a word is too big for the buffer, just keep stashing it away use any handy data structure for this</pre>
If your code is written correctly, it shouldn't matter how big the buffer is; the same logic applies for a 1-byte buffer or a 1000-byte buffer
What is "whitespace"? Characters that don't have visible pixels on screen ' ' space '\n' newline
'\t' tab '\r' carriage return '\v' vertical tab etc.
Use isspace() from ctype.h
occur in text files, but are not considered whitespace '\a' bell '\b' backspace etc.
buffering and syscalls
As we said, syscalls are more expensive than regular function calls we require a "context switch" in order pass control to the OS -> changes permissions on the processor (user mode to supervisor mode) -> programs run in virtual memory, OS does not
-> etc. Not a huge burden, but it is slower than a regular function call -> this is why read and write work with a buffer
-> do a lot of work with a single system call The major difference between the Posix file functions (that use file descriptors) and the C file functions (that use FILE*), is that the C functions are buffered
when we call fopen, we get back a FILE * what is FILE? this is a struct defined in stdio.h
contents vary between compilers, but it generally includesa file descriptora buffer (char array)index of current byte in buffer
- other info (e.g., are we at EOF) On most Posix systems, fopen calls open, fread/fscanf/etc. use the buffer in FILE and call read when they need to refresh the buffer
-> this is why fgetc is more efficient than calling read with a 1-char buffer fgetc reads a single character from a file -> but it only makes a syscall when the buffer is empty or completely read
<pre>while ((ch = fgetc(my_file)) != EOF) { // do something with ch }</pre>
<pre>// do something with ch } makes fewer system calls than while ((bytes_read = read(my_fd, &ch, 1)) > 0) { // do something with ch</pre>
// do something with ch } makes fewer system calls than while ((bytes_read = read(my_fd, &ch, 1)) > 0) {
// do something with ch } makes fewer system calls than while ((bytes_read = read(my_fd, &ch, 1)) > 0) {
<pre>// do something with ch } makes fewer system calls than while ((bytes_read = read(my_fd, &ch, 1)) > 0) {</pre>
// do something with ch } makes fewer system calls than while ((bytes_read = read(my_fd, &ch, 1)) > 0) {
<pre>// do something with ch } makes fewer system calls than while ((bytes_read = read(my_fd, &ch, 1)) > 0) {</pre>
makes fewer system calls than while ((bytes_read = read(my_fd, &ch, 1)) > 0) { // do something with ch } On a Posix system, we can actually conver between file descriptors and FILE* fdopen -> create a FILE * for a file descriptor (add buffering!) fileno -> return the file descriptor used by a FILE * Why is this useful? file descriptors can be used to access many things, not just files on disk - standard input/output/error - reading from devices in general - communicating with other processes (e.g., pipes) - communicating over a network (e.g., sockets) The reason project 1 requires read/write is to give you a sense of why buffers are convenient - also, it gives you practice for working with sockets Read/write give us more control about when data is obtained from/sent to the OS How big should your buffer be? the tradeoff is memory use vs how often you call into the OS - smaller buffer uses less space
// do something with ch } makes fewer system calls than while ((bytes read = read(my fd, &ch, 1)) > 0) { // do something with ch } On a Posix system, we can actually conver between file descriptors and FILE* fdopen -> create a FILE * for a file descriptor (add buffering!) fileno -> return the file descriptor used by a FILE * Why is this useful? file descriptors can be used to access many things, not just files on disk
makes fewer system calls than while ((bytes_read = read(my_fd, &ch, 1)) > 0) {
makes fewer system calls than while ((bytes_read = read(my_fd, &ch, 1)) > 0) { // do something with ch } On a Posix system, we can actually conver between file descriptors and FILE* fdopen -> create a FILE * for a file descriptor (add buffering!) fileno -> return the file descriptor used by a FILE * Why is this useful? file descriptors can be used to access many things, not just files on disk - standard input/output/error - reading from devices in general - communicating with other processes (e.g., pipes) - communicating over a network (e.g., sockets) The reason project 1 requires read/write is to give you a sense of why buffers are convenient - also, it gives you practice for working with sockets Read/write give us more control about when data is obtained from/sent to the OS How big should your buffer be? the tradeoff is memory use vs how often you call into the OS - smaller buffer uses less space - bigger buffer requires fewer syscalls Common sizes: 64, 128, 256, 1024 but this is arbitrary
makes fewer system calls than while ((bytes read = read(my_fd, &ch, 1)) > 0) { // do something with ch } On a Posix system, we can actually conver between file descriptors and FILE* fdopen -> create a FILE * for a file descriptor (add buffering!) fileno -> return the file descriptor used by a FILE * why is this useful? file descriptors can be used to access many things, not just files on disk - standard input/output/error - reading from devices in general - communicating with other processes (e.g., pipes) - communicating over a network (e.g., sockets) The reason project 1 requires read/write is to give you a sense of why buffers are convenient - also, it gives you practice for working with sockets Read/write give us more control about when data is obtained from/sent to the OS How big should your buffer be? the tradeoff is memory use vs how often you call into the OS - smaller buffer uses less space - bigger buffer requires fewer syscalls Common sizes: 64, 128, 256, 1024 but this is arbitrary using make to run tests
makes fewer system calls than while ((bytes_read = read(my_fd, sch, 1)) > 0) { } Mon a Posix system, we can actually conver between file descriptors and FILE* fdopen -> create a FILE * for a file descriptor (add buffering!) fileno -> return the file descriptor used by a FILE * Why is this useful? file descriptors can be used to access many things, not just files on disk - standard input/output/error - reading from devices in general - communicating with other processes (e.g., pipes) - communicating vith other processes (e.g., pipes) - communicating over a network (e.g., sockets) The reason project 1 requires read/write is to give you a sense of why buffers are convenient - also, it gives you practice for working with sockets Read/write give us more control about when data is obtained from/sent to the OS How big should your buffer be? the tradeoff is memory use vs how often you call into the OS - smaller buffer uses less space - bigger buffer requires fewer syscalls Common sizes: 64, 128, 256, 1024 but this is arbitrary using make to run tests
while ((bytes_read = read(my_fd, &ch, 1)) > 0) {
makes fewer system calls than while (Dytes_read = read(my_fd, sch, 1)) > 0) { // do something with ch } a Posix system, we can actually conver between file descriptors and FILE* fdopon -> create a FILE * for a file descriptor (add buffering!) fileno -> return the file descriptor used by a FILE * Why is this useful? file descriptors can be used to access many things, not just files on disk - stendard input/output/error - reading from devices in general - communicating over a network (e.g., pipes) - communicating over a network (e.g., schets) The reason project 1 requires read/write is to give you a sense of why buffers are convenient - also, it gives you practice for working with sockets Read/write give us more control about when data is obtained from/sent to the OS How big should your buffer bo? the tradeoff is memory use vs how often you call into the OS - smaller buffer uses less space - bigger buffer requires fewer syscalls Common sizes: 64, 128, 256, 1024 but this is arbitrary using make to run tests **Remember: we can have our recipe run any program test: we ./ww 80 input.txt > output.txt **We can use can or diff to compase the account of two files eng will find the first different byte between two files diff will print out a detailed description of the differences test: we ./ww 80 input.txt > output.txt can preference.lext output.txt can reference.lext output.txt
makes fewer system calls than while ((bytes read = read(my fd, &ch, 1)) > 0) { // do something with ch } On a Posix system, we can actually conver between file descriptors and FILE* fdopon -> create a FILE * for a file descriptor (add buffering!) fileno -> return the file descriptor used by a FILE * why is this useful? file descriptors can be used to access many things, not just files on disk - standard input/output/error - reading from devices in general - communicating with other processes (e.g., pipes) - communicating with other processes (e.g., pipes) - communicating over a network (e.g., sockets) The reason project 1 requires read/write is to give you a sense of why buffers are convenient - also, it gives you practice for working with sockets Read/write give us more control about when data is obtained from/sent to the OS flow big should your buffer be? the tradeoff is memory use vs how often you call into the OS - smaller buffer uses less space - bigger buffer requires fewer syscalls Common sizes: 64, 128, 256, 1024 but this is arbitrary using make to run tests
makes fewer system calls than while ((bytes read = read(ay fd, ich, 1)) > 0) { // do something with ch } On a Posits system, we can actually conver between file descriptors and FILE* fdopon -> croate a FILE + for a file descriptor (add buffering!) fileno -> return the file descriptor used by a FILE * why is this useful? file descriptor can be used to access many things, not just files on disk - standard input/output/error - roading from dovices in general - communicating with other processes (e.g., piges) - communicating with other processes (e.g., piges) - communicating over a network (e.g., sockets) The reason project 1 requires road/write is to give you a sense of why buffers are convenient - also, it gives you practice for working with sockets Read/write give us more control about when data is obtained from/sent to the OS How big should your buffer be? the tradeoff is memory use vs how often you call into the OS - smaller buffer uses less space - bigger buffer requires fewer syscalls Common sizes: 64, 128, 256, 1024 but this is arbitrary using make to run tosts
A commentary with ch ### A commentary with commentary
// do semething with ch } makes fiver system calls then while ((bytes, read = read(ey_fd, sch, 1)) > 0) { // do semething with ch } on a Posix system, we can actually conver between file descriptors and FILE* fdopen -> create a FILE * for a file descriptor (add buffering) filence -> return the file descriptor used by a FILE * why is this useful) file descriptors can be used to access many things, not just files on disk standard input/output/corror - reading from devices in general - communicating with other processes (e.g., pipes) - communicating own a notwark (e.g., sockets) Who fire the goal of the processes (e.g., pipes) - communicating own a notwark (e.g., sockets) Who big should your buffer be? the tradeoff is memory use vs how often you call into the OS - smaller buffer be? the tradeoff is memory use vs how often you call into the OS - smaller buffer use less space - biggor buffer roadins fewer syscalls Common sisses (g. 128, 258, 1024 but this is arbitrary but this is arbitrary using make to run tests Remember: we can have our recipe run any program test: ww ./ww 80 input.txt > output.txt who was a file with the expected output, o.g., "reference.txt" we can use omp or diff to compare the content of two files can proste a file with the expected output, o.g., "reference.txt" wo can use omp or diff to compare the content of two files can proste a file with the expected output, txt deff: "Ww ./ww 80 input.txt > output.txt camp reference.toxt output.txt deff: goal input.txt omp reference.toxt test3 ww ./ww 80 input.txt omp reference.toxt test3 we will be a with status of signal whether t
makes fever system calls than while (bytes mad - monday file (ch, 1)) > 8) { // do semething with the while (bytes med - monday file (ch, 1)) > 8) { // do semething with the fileno -> creates a file ' for a file descriptor used by a file' fileno -> creates the file descriptor used by a file' // do semething with the file descriptor used by a file' // do semething with the descriptor used by a file' // by is this useful? // lie this usef
Makes fewer system calls than while ((bytes reed - reed(ny fd, &ch, 1)) > 5) { makes fewer system calls than while ((bytes reed - reed(ny fd, &ch, 1)) > 5) { // do menching with ch } On a Posix system, we can actually conver between file descriptors and FILE* fileno -> return the file descriptor used by a FILE * May is this useful? The descriptors can be used to access many things, not just files on disk - standard imput/output/error - communicating with other processes (e.g., pipes) - communicating with other used (e.g., cockets) The reason project 1 requires resd/write is to give you a sense of why buffers are nonvenient - club, it gives you practice for working with suckets **Read/writh give us more control about when data in obtained from/annt to the OS **Now big should your buffer hor the trodooff is remory use or how often you call into the OS - smaller buffer uses less space - aliger buffer requires fewer syscalls Common sizes sk, 128, 258, 1024 but this is arolivacy but this is arolivacy but ing make to run tasts **Remember: we can have our recipe run any program test wo **April 10; procomble we if necessary, (b) wrap input.txt, and (c) are the output to 'output.txt' - whis skill requires us to examine output.txt after the test **Be can create a file with the expected output, e.g., "reference.txt" **Recomber: we can be described described output of the differences test: wo **April 20; page.txt' 2 output.txt' - diff reference.txt' output.txt' - diff reference.txt' output.txt' - diff reference.txt' output.txt' - diff reference.txt' output.txt' - as an aryument to offif to have it read standard input - diff cap
Advanced by the collection Advanced by the collection
// do sementing with on
"// do secting with ct."
// do something with on // do something with () // do something
As containing with on the process of the containing with only plan rand - manager (d. was, 1)) > 0) (### As a lock system, we can actually conver actuate it is accompanied with a containing with on the process of the descriptor owed by a Pila ? ### Character of the file descriptor owed by a Pila ? ### As a lock system, we can actually conver actually report of the file descriptor owed by a Pila ? #### As a lock system on the file descriptor owed by a Pila ? ### As a lock system of the file descriptor owed by a Pila ? ### As a lock system of the file descriptor owed by a Pila ? ### As a lock system on the file descriptor owed by a Pila ? ### As a lock system on the file descriptor owed by a Pila ? ### As a lock system on the file descriptor owed by a Pila ? ### As a lock system on the file descriptor owed by a Pila ? ### As a lock system on the file descriptor owed by a Pila ? ### As a lock system on the file descriptor owed by a Pila ? ### As a lock system of file is a lock system of the file owed system of the file owed system
Advance Tower spaces and Tables ### Advanced Tower spaces
A concenting with the capability of the capa
Jackson Sevent System calls than
And the secondary of the design of the company of t
anisot focus protects while the makes focus protects with the makes focus protects and the form of the descriptors (and underling) filters a constant that fill descriptor insend by a fills (filters a constant that fill descriptor insend by a fills (filters a constant that fill descriptor insend by a fills (filters a constant that fill descriptor insend by a fills (filters a constant that fill descriptor insend by a fills (filters a constant that fill descriptor insend by a fills (filters a constant that fill descriptor insend by a fills (filters a constant that fill descriptor insend by a fills (filters a constant that fill descriptor insend by a fills (filters a constant that fill descriptor insend that constant the fill descriptor in the filters and filters a constant that fill descriptor insend the filters and filters and filters a constant that fill descriptor insend that fill descriptor insend that fill descriptor insend that fill descriptor insend that fill descriptor in the constant of the fill descriptor in the fill descriptor in the constant of the fill descriptor in the fill descriptor in the constant of the fill descriptor in the fill descriptor in the constant of the fill descriptor in the fill descriptor in the constant of the fill descriptor in the fill descriptor in the constant of the fill descriptor in the fill descriptor in the constant of the fill descriptor in the fill descriptor in the constant of the fill descriptor in the constant of the fill descriptor in the constant of the fill descriptor in the fill descriptor in the constant of the fill descriptor in the fill descriptor in the constant of the fill descriptor in the fill
And a manufacture with the second property with (1) > 0) (and a force system with the second property with (1) > 0) (and a force system of the second property with (1) > 0) (but so the system can be a continue of the second property (and contenting) force of the second property of the second property (and contenting) force of the second property of the second property (and contenting) force of the second property of the second property (and second property (and second property) force of the second property of the second property (and second property) force of the second property of the second property (and second property) force of the second property of the second (and property) force of the second property of the second (and property) force of the second property of the second (and property) force of the second property of the second (and property) force of the second property of the seco
And the content of th
Two secondary with a manage of the control of the c
The content could be content of the country of the
The content makes the content of the best of the content of the co
And the process of the control of th