Virtual Memory II



Learning Outcomes

- An understanding of TLB refill:
 - in general,
 - and as implemented on the R3000
- An understanding of demand-paged virtual memory in depth, including:
 - Locality and working sets
 - Page replacement algorithms
 - Thrashing



TLB Recap

- Fast associative cache of page table entries
 - Contains a subset of the page table
 - What happens if required entry for translation is not present (a *TLB miss*)?



TLB Recap

- TLB may or may not be under OS control
 - Hardware-loaded TLB
 - On miss, hardware performs PT lookup and reloads TLB
 - Example: Pentium
 - Software-loaded TLB
 - On miss, hardware generates a TLB miss exception, and exception handler reloads TLB
 - Example: MIPS



Aside: even if filled by software

TLB still a hardware-based translator



R3000 TLB Handling

- TLB refill is handled by software
 - An exception handler
- TLB refill exceptions accessing kuseg are expected to be frequent
 - CPU optimised for handling kuseg TLB refills by having a special exception handler just for TLB refills

0xFFFFFFF kseg2 0xC0000000 kseg1 0xA0000000 kseg0 0x80000000 kuseg



0x0000000

Exception Vectors

Program address	"segment"	Physical Address	Description
0x8000 0000x0	kseg0	0x0000 0000x0	TLB miss on <i>kuseg</i> reference only.
0800 0008x0	kse	0x0000 0080	All other exceptions.
0xbfc0 0100	kseg1	0x1fc0 0100	Uncached alternative <i>kuseg</i> TLB miss entry point (used if <i>SR</i> bit BEV set).
0xbfc0 0180	kseg1		alternative for all other s, used if <i>SR</i> bit BEV set).
0xbfc0 0000 Table 4.1.	kseg1 Reset and ex	Special exc vector for TLB re	kuseg exception".



Special Exception Vector

rfe

- Can be optimised for TLB refill only
 - Does not need to check the exception type
 - Does not need to save any registers
 - It uses a specialised assembly routine that only uses k0 and k1.
 - Does not check if PTE exists
 - Assumes virtual linear array see extended OS notes (if interested)
- With careful data structure choice, exception handler can be made very fast



MIPS VM Related Exceptions

- TLB refill
 - Handled via special exception vector
 - Needs to be very fast
- Others handled by the general exception vector
 - TLB Mod
 - TLB modify exception, attempt to write to a read-only page
 - TLB Load
 - Attempt it load from a page with an invalid translation
 - TLB Store
 - Attempt to store to a page with an invalid translation
 - Note: these can be slower as they are mostly either caused by an error, or non-resident page.
 - We never optimise for errors, and page-loads from disk dominate the fault resolution cost.




<Intermezzo>



Amdahl's law

 States that overall performance improvement is limited by the fraction of time an enhancement can be used

Law of diminishing returns



fraction in enhanced mode = 0.5 (based on old system)

THE UNIVERSITY OF NEW SOUTH WALES

Speedup of enhanced mode = 2

Amdahl's law

 States that overall performance improvement is limited by the fraction of time an enhancement can be used

Speed From Case fast!

Make the common case fast!





c0 Registers

- c0_EPC
 - The address of where to restart after the exception
- c0_status
 - Kernel/User Mode bits, Interrupt control
- c0 cause
 - What caused the exception
- c0_badvaddr
 - The address of the fault



The TLB and EntryHi,EntryLo

c0 Registers

c0_EntryHi c0_EntryLo c0_Index

Used to read and write individual TLB entries

Each TLB entry contains

- EntryHi to match page# and ASID
- EntryLo which contains frame# and protection

TLB

EntryHi	EntryLo
EntryHi	EntryLo



c0 Registers

6 31 12 11 5 0 VPN **ASID** 0 EntryHi Register (TLB key fields) 8 31 12 11 10 0 PEN N V G 0.

EntryLo Register (TLB data fields)

- N = Not cacheable
- D = Dirty = Write protect
- G = Global (ignore ASID in lookup)

- V = valid bit
- 64 TLB entries
- Accessed via software through Cooprocessor 0 registers
 - EntryHi and EntryLo



c0 Index Register

- Used as an index to TLB entries
 - Single TLB entries are manipulated/viewed through EntryHi and EntryLo0 registers
 - Index register specifies which TLB entry to change/view



Special TLB management Instructions

TLBR

- TLB read
 - EntryHi and EntryLo are loaded from the entry pointer to by the index register.

TLBP

- TLB probe
- Set EntryHi to the entry you wish to match, index register is loaded with the index to the matching entry

TLBWR

Write EntryHi and EntryLo to a psuedo-random location in the TLB

TLBWI

 Write EntryHi and EntryLo to the location in the TLB pointed to by the Index register.



Cooprocessor 0 registers on a refill exception

```
 \begin{array}{l} \text{c0.EPC} \leftarrow \text{PC} \\ \text{c0.cause.ExcCode} \leftarrow \text{TLBL} \text{ ; if read fault} \\ \text{c0.cause.ExcCode} \leftarrow \text{TLBS} \text{ ; if write fault} \\ \text{c0.BadVaddr} \leftarrow \text{faulting address} \\ \text{c0.EntryHi.VPN} \leftarrow \text{page number of faulting address} \\ \text{c0.status} \leftarrow \text{kernel mode, interrupts disabled.} \\ \text{c0.PC} \leftarrow 0\text{x8000 0000} \\ \end{array}
```



Outline of TLB miss handling

- Software does:
 - Look up PTE corresponding to the faulting address
 - If found:
 - load c0_EntryLo with translation
 - load TLB using TLBWR instruction
 - return from exception
 - Else, page fault
- The TLB entry (i.e. c0_EntryLo) can be:
 - (theoretically) created on the fly, or
 - stored completely in the right format in page table
 - more efficient



OS/161 Refill Handler

- After switch to kernel stack, it simply calls the common exception handler
 - Stacks all registers
 - Can (and does) call 'C' code
 - Unoptimised
 - Goal is ease of kernel programming, not efficiency
- Does not have a page table
 - It uses the 64 TLB entries and then panics when it runs out.
 - Only support 256K user-level address space



Demand Paging/Segmentation



Demand Paging/Segmentation

- With VM, only parts of the program image need to be resident in memory for execution.
- Can transfer presently unused pages/segments to disk
- Reload non-resident pages/segment on demand.
 - Reload is triggered by a page or segment fault
 - Faulting process is blocked and another scheduled
 - When page/segment is resident, faulting process is restarted
 - May require freeing up memory first
 - Replace current resident page/segment
 - How determine replacement "victim"?
 - If victim is unmodified ("clean") can simply discard it
 - This is reason for maintaining a "dirty" bit in the PT



- Why does demand paging/segmentation work?
 - Program executes at full speed only when accessing the resident set.
 - TLB misses introduce delays of several microseconds
 - Page/segment faults introduce delays of several milliseconds
 - Why do it?
- Answer
 - Less physical memory required per process
 - Can fit more processes in memory
 - Improved chance of finding a runnable one
 - Principle of locality



Principle of Locality


- An important observation comes from empirical studies of the properties of programs.
 - Programs tend to reuse data and instructions they have used recently.
 - 90/10 rule
 "A program spends 90% of its time in 10% of its code"
- We can exploit this <u>locality of references</u>
- An implication of locality is that we can reasonably predict what <u>instructions</u> and <u>data</u> a program will use in the near future based on its accesses in the recent past.



- Two different types of locality have been observed:
 - Temporal locality: states that recently accessed items are likely to be accessed in the near future.
 - Spatial locality: says that items whose addresses are near one another tend to be referenced close together in time.



Locality In A Memory-Reference Pattern






Working Set

- The pages/segments required by an application in a time window (Δ) is called its memory **working set**.
- Working set is an approximation of a programs' locality
 - if Δ too small will not encompass entire locality.
 - if Δ too large will encompass several localities.
 - if Δ = ∞ ⇒ will encompass entire program.
 - $-\Delta$'s size is an application specific tradeoff
- System should keep resident at least a process's working set
 - Process executes while it remains in its working set
- Working set tends to change gradually
 - Get only a few page/segment faults during a time window
 - Possible (but hard) to make intelligent guesses about which pieces will be needed in the future
 - May be able to pre-fetch page/segments



Working Set Example






Thrashing

- CPU utilisation tends to increase with the degree of multiprogramming
 - number of processes in system
- Higher degrees of multiprogramming less memory available per process
- Some process's working sets may no longer fit in RAM
 - Implies an increasing page fault rate
- Eventually many processes have insufficient memory
 - Can't always find a runnable process
 - Decreasing CPU utilisation
 - System become I/O limited
- This is called thrashing.



Thrashing



- Why does thrashing occur?
- Σ working set sizes > total physical memory size




Recovery From Thrashing

- In the presence of increasing page fault frequency and decreasing CPU utilisation
 - Suspend a few processes to reduce degree of multiprogramming
 - Resident pages of suspended processes will migrate to backing store
 - More physical memory becomes available
 - Less faults, faster progress for runnable processes
 - Resume suspended processes later when memory pressure eases



What is the difference?

```
/* reset array */
int array[10000][10000];
int i,j;
for (i = 0; i < 10000; i++) {
   for (j = 0; j < 10000; j ++) {
      array[i][j] = 0;
      /* array[j][i] = 0 */
   }
}</pre>
```





VM Management Policies



VM Management Policies

- Operation and performance of VM system is dependent on a number of policies:
 - Page table format (may be dictated by hardware)
 - Multi-level
 - Inverted/Hashed
 - Page size (may be dictated by hardware)
 - Fetch Policy
 - Replacement policy
 - Resident set size
 - Minimum allocation
 - Local versus global allocation
 - Page cleaning policy



Page Size

Increasing page size

- Increases internal fragmentation
 - reduces adaptability to working set size
- ✓ Decreases number of pages
 - Reduces size of page tables
- ✓ Increases TLB coverage
 - Reduces number of TLB misses
- Increases page fault latency
 - Need to read more from disk before restarting process
- ✓ Increases swapping I/O throughput
 - Small I/O are dominated by seek/rotation delays
- Optimal page size is a (work-load dependent) trade-off.



Working Set Size Generally Increases with Increasing Page Size: True/False?



Atlas	512 words (48-bit)
Honeywell/Multics	1K words (36-bit)
IBM 370/XA	4K bytes
DEC VAX	512 bytes
IBM AS/400	512 bytes
Intel Pentium	4K and 4M bytes
ARM	4K and 64K bytes
MIPS R4000	4k – 16M bytes in powers of 4
DEC Alpha	8K - 4M bytes in powers of 8
UltraSPARC	8K – 4M bytes in powers of 8
PowerPC	4K bytes + "blocks"
Intel IA-64	4K – 256M bytes in powers of 4



Page Size

- Multiple page sizes provide flexibility to optimise the use of the TLB
- Example:
 - Large page sizes can be use for code
 - Small page size for thread stacks
- Most operating systems support only a single page size
 - Dealing with multiple page sizes is hard!




Fetch Policy

- Determines when a page should be brought into memory
 - Demand paging only loads pages in response to page faults
 - Many page faults when a process first starts
 - Pre-paging brings in more pages than needed at the moment
 - Improves I/O performance by reading in larger chunks
 - Pre-fetch when disk is idle
 - Wastes I/O bandwidth if pre-fetched pages aren't used
 - Especially bad if we eject pages in working set in order to pre-fetch unused pages.
 - Hard to get right in practice.



Page fault on page 14, physical memory full, which page should we evict? Virtual В Memory THE UNIVERSITY OF NEW SOUTH WALES

Replacement Policy



Physical Address Space

Replacement Policy

- Which page is chosen to be tossed out?
 - Page removed should be the page least likely to be references in the near future
 - Most policies attempt to predict the future behaviour on the basis of past behaviour
- Constraint: locked frames
 - Kernel code
 - Main kernel data structure
 - I/O buffers
 - Performance-critical user-pages (e.g. for DBMS)
- Frame table has a lock (or pinned) bit



Optimal Replacement policy

- Toss the page that won't be used for the longest time
- Impossible to implement
- Only good as a theoretic reference point:
 - The closer a practical algorithm gets to optimal, the better
- Example:
 - Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
 - Four frames
 - How many page faults?



FIFO Replacement Policy

- First-in, first-out: Toss the oldest page
 - Easy to implement
 - Age of a page is isn't necessarily related to usage
- Example:
 - Reference string: 1,2,3,4,1,2,5,1,2,3,4,5
 - Four frames



Least Recently Used (LRU)


- Toss the least recently used page
 - Assumes that page that has not been referenced for a long time is unlikely to be referenced in the near future
 - Will work if locality holds
 - Implementation requires a time stamp to be kept for each page, updated on every reference
 - Impossible to implement efficiently
 - Most practical algorithms are approximations of LRU



Clock Page Replacement


- Clock policy, also called second chance
 - Employs a usage or reference bit in the frame table.
 - Set to one when page is used
 - While scanning for a victim, reset all the reference bits
 - Toss the first page with a zero reference bit.






(a) State of buffer just prior to a page replacement

Figure 8.16 Example of Clock Policy Operation



(a) State of buffer just prior to a page replacement

Figure 8.16 Example of Clock Policy Operation



(b) State of buffer just after the next page replacement

Figure 8.16 Example of Clock Policy Operation

Issue

- How do we know when a page is referenced?
- Use the valid bit in the PTE:
 - When a page is mapped (valid bit set), set the reference bit
 - When resetting the reference bit, invalidate the PTE entry
 - On page fault
 - Turn on valid bit in PTE
 - Turn on reference bit
- We thus simulate a reference bit in software



Simulated Reference Bit

State: Page not referenced

Frame#

R=0

W

V=0

Uses "spare" bits in page table (ignored by hardware), or bit in frame table

Ref. and valid bit

reset by Clock

algorithm

Page fault on access, fault handler sets Ref. and Valid bit.

Frame#

R=1

W

V=1


referenced

State: Page



Hardware Reference Bit

State: Page not referenced



State: Page referenced



Performance

- It terms of selecting the most appropriate replacement, they rank as follows
 - Optimal
 - 2. LRU
 - 3. Clock
 - 4. FIFO
- Note there are other algorithms (Working Set, WSclock, Ageing, NFU, NRU)
 - We don't expect you to know them in this course



Resident Set Size

- How many frames should each process have?
 - Fixed Allocation
 - Gives a process a fixed number of pages within which to execute.
 - Isolates process memory usage from each other
 - When a page fault occurs, one of the pages of that process must be replaced.
 - Achieving high utilisation is an issue.
 - Some processes have high fault rate while others don't use their allocation.
 - Variable Allocation
 - Number of pages allocated to a process varies over the lifetime of the process



Variable Allocation, Global Scope

- Easiest to implement
- Adopted by many operating systems
- Operating system keeps global list of free frames
- Free frame is added to resident set of process when a page fault occurs
- If no free frame, replaces one from any process

Pro/Cons

- Automatic balancing across system
- Does not provide guarantees for important activities




Variable Allocation, Local Scope

- Allocate number of page frames to a new process based on
 - Application type
 - Program request
 - Other criteria (priority)
- When a page fault occurs, select a page from among the resident set of the process that suffers the page fault
- Re-evaluate allocation from time to time!



Page-Fault Frequency Scheme



- Establish "acceptable" page-fault rate.
 - If actual rate too low, process loses frame.
 - If actual rate too high, process gains frame.



Cleaning Policy

Observation

Clean pages are much cheaper to replace than dirty pages

Demand cleaning

- A page is written out only when it has been selected for replacement
- High latency between the decision to replace and availability of free frame.

Precleaning

- Pages are written out in batches (in the background, the pagedaemon)
- Increases likelihood of replacing clean frames
- Overlap I/O with current activity

