




Virtual Address Page-based VM 15 Space 14 13 Virtual Memory 12 · Physical Memory Divided into equal-Ε 11 - Divided into sized pages 10 D equal-sized A mapping is a translation between 9 frames A page and a frame 8 A page and null 7 Mappings defined at 6 6 runtime · They can change 5 D 5 Address space can 4 have holes 3 Process does not 2 В 2 have to be Physical Address contiguous in physical memory 1 Space 4


3 4





6





10

4

3 1

2

⁹0

7 1

Virtual Address 15 Space 15 6 Page 14 14 Table 0 13 S 13 Page table for 12 12 resident part of 11 11 10 address space 10 9 8 8 7 7 6 F 6 Ε 5 5 3 5

4 D

3

0

THE UNIVERSITY OF NEW SOUTH WALES

В 2 1

Α

Shared Pages · Private code and data · Shared code - Each process has own - Single copy of code copy of code and data shared between all Code and data can processes executing it appear anywhere in - Code must not be self the address space modifying - Code must appear at same address in all processes THE UNIVERSITY OF NEW SOUTH WALES 10


9

4

3

Physical

0 Address Space



Page Table Structure · Page table is (logically) an array of 5 frame numbers - Index by page number • Each page-table entry (PTE) also has other bits Caching disabled Present/absent Page frame number 4 Referenced Protection Page 2 Table THE UNIVERSITY OF NEW SOUTH WALES

11 12

PTE Attributes (bits)

- Present/Absent bit
- Also called valid bit, it indicates a valid mapping for the page
- Modified bit
- Also called dirty bit, it indicates the page may have been modified in memory
- Reference bit
 - Indicates the page has been accessed
- Protection bits
- Read permission, Write permission, Execute permission
- Or combinations of the above
- Caching bit
 - Use to indicate processor should bypass the cache when accessing memory

 • Example: to access device registers or memory



13

Address Translation

- · Every (virtual) memory address issued by the CPU must be translated to physical
 - Every load and every store instruction
 - Every instruction fetch
- · Need Translation Hardware
- In paging system, translation involves replace page number with a frame number




14

16

Virtual Memory Summary

virtual and physical mem chopped up in pages/frames



Page Tables

- · Assume we have
 - 32-bit virtual address (4 Gbyte address space)
 - 4 KByte page size
 - How many page table entries do we need for one process?

THE UNIVERSITY OF NEW SOUTH WALES

16

Page Tables

- · Assume we have
 - 64-bit virtual address (humungous address space)
 - 4 KBvte page size
 - How many page table entries do we need for one process?
- Problem:
 - Page table is very large
 - Access has to be fast, lookup for every memory reference
 - Where do we store the page table?

 - Registers?Main memory?

THE UNIVERSITY OF NEW SOUTH WALES

17


Page Tables


- Page tables are implemented as data structures in main
- Most processes do not use the full 4GB address space - e.g., 0.1 - 1 MB text, 0.1 - 10 MB data, 0.1 MB stack
- We need a compact representation that does not waste
 - But is still very fast to search
- Three basic schemes
 - Use data structures that adapt to sparsity
 - Use data structures which only represent resident pages - Use VM techniques for page tables (details left to extended OS)


THE UNIVERSITY OF NEW SOUTH WALES


18


17














Inverted Page Table (IPT)

- · "Inverted page table" is an array of page numbers sorted (indexed) by frame number (it's a frame table).
- Algorithm
 - Compute hash of page number
 - Extract index from hash table
 - Use this to index into inverted page table
 - Match the PID and page number in the IPT entry
 - If match, use the index value as frame # for translation
 - If no match, get next candidate IPT entry from chain field
 - If NULL chain entry \Rightarrow page fault



Properties of IPTs

- IPT grows with size of RAM, NOT virtual address space
- Frame table is needed anyway (for page replacement, more later)
- Need a separate data structure for non-resident pages
- Saves a vast amount of space (especially on 64-bit
- · Used in some IBM and HP workstations

THE UNIVERSITY OF NEW SOUTH WALES

26

25

Given *n* processes

- · how many page tables will the system have for
 - 'normal' page tables
 - inverted page tables?

THE UNIVERSITY OF NEW SOUTH WALES

27

29

Another look at sharing...

28

THE UNIVERSITY OF NEW SOUTH WALES


Proc 1 Address Proc.2 Address Space for normal page tables Physical Address Spag bit of a nightmare for IPT Two (or more) processes running the same program and sharing M the text section THE UNIVERSITY OF NEW SOUTH WALES


Improving the IPT: Hashed Page Table


- · Retain fast lookup of IPT
 - A single memory reference in best case
- · Retain page table sized based on physical memory size (not virtual)
 - Enable efficient frame sharing
 - Support more than one mapping for same frame

THE UNIVERSITY OF NEW SOUTH WALES

30







Sizing the Hashed Page Table · HPT sized based on physical memory size · With sharing


34

- Each frame can have more than one PTE
- More sharing increases number of slots used
 - · Increases collision likelihood
- · However, we can tune HPT size based on:
 - · Physical memory size
 - Expected sharing
 - · Hash collision avoidance.
 - HPT a power of 2 multiple of number of physical memory frame

THE UNIVERSITY OF NEW SOUTH WALES

VM Implementation Issue

- · Performance?
 - Each virtual memory reference can cause two physical memory accesses
 - · One to fetch the page table entry
 - · One to fetch/store the data \Rightarrow Intolerable performance impact!!
- · Solution:
 - High-speed cache for page table entries (PTEs)
 - Called a translation look-aside buffer (TLB)
 - Contains recently used page table entries
 - Associative, high-speed memory, similar to cache memory



TLB operation Page # Offset 36

35

Translation Lookaside Buffer

- Given a virtual address, processor examines the TLB
- If matching PTE found (TLB hit), the address is translated
- Otherwise (TLB miss), the page number is used to index the process's page table
 - If PT contains a valid entry, reload TLB and restart
 - Otherwise, (page fault) check if page is on disk
 - · If on disk, swap it in
 - Otherwise, allocate a new page or raise an exception



37

37

W SOUTH WALES

TLB properties

- Page table is (logically) an array of frame numbers
- · TLB holds a (recently used) subset of PT entries
 - Each TLB entry must be identified (tagged) with the page # it translates
 - Access is by associative lookup:
 - All TLB entries' tags are concurrently compared to the page #
 - TLB is associative (or content-addressable) memory

page #	$frame \ \#$	V	W
	• • •		

38

38

THE UNIVERSITY O NEW SOUTH WALE

TLB properties

- TLB may or may not be under direct OS control
 - Hardware-loaded TLB
 - On miss, hardware performs PT lookup and reloads TLB
 - Example: x86, ARM
 - Software-loaded TLB
 - On miss, hardware generates a TLB miss exception, and exception handler reloads TLB
 - Example: MIPS, Itanium (optionally)
- TLB size: typically 64-128 entries
- Can have separate TLBs for instruction fetch and data access
- TLBs can also be used with inverted page tables (and others)



39

THE UNIVERSITY OF NEW SOUTH WALES 39

TLB and context switching

- TLB is a shared piece of hardware
- Normal page tables are per-process (address space)
- TLB entries are process-specific
 - On context switch need to *flush* the TLB (invalidate all entries)
 - high context-switching overhead (Intel x86)
 - or tag entries with address-space ID (ASID)
 - · called a tagged TLB
 - used (in some form) on all modern architectures
 - TLB entry: ASID, page #, frame #, valid and write-protect bits

THE UNIVERSITY OF NEW SOUTH WALES

40

42

40

TLB effect

- · Without TLB
 - Average number of physical memory references per virtual reference
 - = 2
- With TLB (assume 99% hit ratio)
 - Average number of physical memory references per virtual reference
 - = .99 * 1 + 0.01 * 2
 - = 1.01





41


Recap - Simplified Components of
VM System


Recap - Simplified Components

Recap - Simplified Componen









R3000 Address Space Layout	0xFFFFFFF 0xC0000000	kseg2
kuseg:	0xA0000000	kseg1
TLB translated (mapped) Cacheable (depending on 'N' bit) user-mode and kernel mode	0x80000000	kseg0
accessible - Page size is 4K		kuseg
THE UNIVERSITY OF NEW SOUTH WALES	0x00000000	

