COMP 3331/9331: Computer Networks and Applications Week 5

Transport Layer (Continued)

Reading Guide: Chapter 3, Sections: 3.5 – 3.7



Transport Layer Outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

Recall: Components of a solution for reliable transport

- Checksums (for error detection)
- Timers (for loss detection)
- Acknowledgments
 - cumulative
 - selective
- Sequence numbers (duplicates, windows)
- Sliding Windows (for efficiency)
 - Go-Back-N (GBN)
 - Selective Repeat (SR)



What does TCP do?

Many of our previous ideas, but some key differences

Checksum

TCP Header

Source port **Destination port** Sequence number Acknowledgment Computed HdrLen Receive window Flags 0 over header and data Checksum **Urgent pointer** (SAME AS UDP) Options (variable) Data


What does TCP do?

Many of our previous ideas, but some key differences

- Checksum
- Sequence numbers are byte offsets

TCP "Stream of Bytes" Service ...

Application @ Host A




Application @ Host B




.. Provided Using TCP "Segments"

Host A



TCP Maximum Segment Size



IP packet

- No bigger than Maximum Transmission Unit (MTU)
- E.g., up to 1500 bytes with Ethernet


TCP packet

- IP packet with a TCP header and data inside
- TCP header ≥ 20 bytes long

TCP segment

- No more than Maximum Segment Size (MSS) bytes
- E.g., up to 1460 consecutive bytes from the stream
- MSS = MTU 20 (min IP header) 20 (min TCP header)


Sequence Numbers



Sequence numbers:

• byte stream "number" of first byte in segment's data


Sequence & Ack Numbers




TCP Header

Acknowledgment gives seqno just beyond highest seqno received in order

("What Byte is Next")



TCP seq. numbers, ACKs




simple telnet scenario



Piggybacking

- So far, we've assumed distinct "sender" and "receiver" roles
- In reality, usually both sides of a connection send some data



Without Piggybacking

With Piggybacking



What does TCP do?


Most of our previous tricks, but a few differences

- Checksum
- Sequence numbers are byte offsets
- Receiver sends cumulative acknowledgements (like GBN)

ACKing and Sequence Numbers

- Sender sends packet
 - Data starts with sequence number X
 - Packet contains B bytes [X, X+1, X+2,X+B-1]
- Upon receipt of packet, receiver sends an ACK
 - If all data prior to X already received:
 - ACK acknowledges X+B (because that is next expected byte)
 - If highest in-order byte received is Y s.t. (Y+1) < X
 - ACK acknowledges Y+1
 - Even if this has been ACKed before

TCP seq. numbers, ACKs



Normal Pattern

- Sender: seqno=X, length=B
- ❖ Receiver: ACK=X+B
- Sender: seqno=X+B, length=B
- Receiver: ACK=X+2B
- Sender: seqno=X+2B, length=B
- Seqno of next packet is same as last ACK field

Packet Loss

- Sender: seqno=X, length=B
- Receiver: ACK=X+B
- Sender: seqno=X+B, length=B
- Sender: seqno=X+2B, length=B
- ❖ Receiver: ACK = X+B

Quiz



$$Seq = 101, 2 \text{ KBytes of data}$$

$$Seq = ?, 2 KBytes of data$$

$$ACK = ?$$

What does TCP do?

Most of our previous tricks, but a few differences

- Checksum
- Sequence numbers are byte offsets
- Receiver sends cumulative acknowledgements (like GBN)
- Receivers can buffer out-of-sequence packets (like SR)

Loss with cumulative ACKs

- Sender sends packets with 100Bytes and sequence numbers:
 - **1**00, 200, 300, 400, 500, 600, 700, 800, 900, ...
- * Assume the fifth packet (seq. no. 500) is lost, but no others
- Stream of ACKs will be:
 - **200**, 300, 400, 500, 500, 500, 500,






A TCP Sender is just about to send a segment of size 100 bytes with sequence number 1234 and ack number 436 in the TCP header. What is the highest sequence number up to and including which this sender has received from the receiver?

- A. 1233
- B. 436
- c. 435
- D. 1334
- E. 536

What does TCP do?

Most of our previous tricks, but a few differences

- Checksum
- Sequence numbers are byte offsets
- Receiver sends cumulative acknowledgements (like GBN)
- Receivers do not drop out-of-sequence packets (like SR)
- Sender maintains a single retransmission timer (like GBN) and retransmits on timeout (why single timer?)




- Q: how to set TCP timeout value?
- longer than RTT
 - but RTT varies
- too short: premature timeout, unnecessary retransmissions
- too long: slow reaction to segment loss and connection has lower throughput

- Q: how to estimate RTT?
- SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
 - average several recent measurements, not just current SampleRTT


Why exclude retransmissions in RTT computation?

How do we differentiate between the real ACK, and ACK of the retransmitted packet?



EstimatedRTT = $(1-\alpha)$ *EstimatedRTT + α *SampleRTT

- exponential weighted moving average
- influence of past sample decreases exponentially fast
- * typical value: $\alpha = 0.125$



- * timeout interval: EstimatedRTT plus "safety margin"
 - large variation in EstimatedRTT -> larger safety margin
- estimate SampleRTT deviation from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT| (typically, \beta = 0.25)
```

TimeoutInterval = EstimatedRTT + 4*DevRTT



estimated RTT

"safety margin"

Practice Problem:

http://wps.pearsoned.com/ecs_kurose_compnetw_6/216/55463/14198700.cw/index.html




Figure: Credits Prof David Wetherall UoW

data rcvd from app:

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
 - think of timer as for oldest unacked segment
 - expiration interval:
 TimeOutInterval


timeout:

- retransmit segment that caused timeout
- restart timer


ack rcvd:

- if ack acknowledges previously unacked segments
 - update what is known to be ACKed
 - start timer if there are still unacked segments

TCP: retransmission scenarios



TCP: retransmission scenarios



cumulative ACK

cumulative ACK





A TCP Sender is just about to send a segment of size 100 bytes with sequence number 1234 and ack number 436 in the TCP header. Is it possible that the receiver has already received byte number 1333?

- A. Yes
- B. No

TCP ACK generation [RFC 1122, RFC 2581]

Concept of delayed ACK, cumulative ACK, duplicate ACK


event at receiver	TCP receiver action
arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK [Why delay the ACK?]
arrival of in-order segment with expected seq #. One other segment has ACK pending	immediately send single cumulative ACK, ACKing both in-order segments
arrival of out-of-order segment higher-than-expect seq. # . Gap detected	immediately send duplicate ACK, indicating seq. # of next expected byte
arrival of segment that partially or completely fills gap	immediately send ACK, provided that segment starts at lower end of gap

What does TCP do?

Most of our previous tricks, but a few differences

- * Checksum
- Sequence numbers are byte offsets
- Receiver sends cumulative acknowledgements (like GBN)
- Receivers may not drop out-of-sequence packets (like SR)
- Sender maintains a single retransmission timer (like GBN) and retransmits on timeout
- Introduces fast retransmit: optimisation that uses duplicate ACKs to trigger early retransmission

TCP fast retransmit



Triple dup ACK = same ACK received 4 times back to back

TCP fast retransmit

- time-out period often relatively long:
 - long delay before resending lost packet
- "Duplicate ACKs" are a sign of an <u>isolated</u> loss
 - The lack of ACK progress means that packet hasn't been delivered
 - Stream of ACKs means some packets are being delivered
 - Could trigger resend on receiving "k" duplicate ACKs (TCP uses k = 3)

TCP fast retransmit

if sender receives 3 duplicate ACKs for same data

("triple duplicate ACKs"), resend unacked segment with smallest seq #

likely that unacked segment is lost, so don't wait for timeout

Summary of TCP Reliability

Most of our previous ideas, but some key differences

- Checksum
- Sequence numbers are byte offsets
- Receiver sends cumulative acknowledgements (like GBN)
- Receivers do not drop out-of-sequence packets (like SR)
- Sender maintains a single retransmission timer (like GBN) and retransmits on timeout
- Introduces fast retransmit: optimization that uses duplicate ACKs to trigger early retransmission





A TCP Sender maintains an EstimatedRTT of 100ms. Suppose the next SampleRTT is 108. Which of the following is true about the sender?

- A. It will increase EstimatedRTT but leave timeout unchanged
- B. It will increase the timeout
- C. Whether it increases EstimatedRTT will depend on the deviation
- D. Whether it increases the timeout will depend on the deviation

Transport Layer Outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

Transport Layer Outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

TCP flow control

application may remove data from TCP socket buffers

... slower than TCP receiver is delivering (sender is sending)




receiver protocol stack

flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast


TCP flow control

- receiver "advertises" free buffer space by including rwnd value in TCP header of receiver-to-sender segments
 - RcvBuffer size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust RcvBuffer
- sender limits amount of unacked ("in-flight") data to receiver's rwnd value
- guarantees receive buffer will not overflow



receiver-side buffering

TCP Header



Transport Layer Outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

Connection Management

before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters




```
Socket clientSocket =
  newSocket("hostname","port
  number");
```

```
connection state: ESTAB connection Variables:
    seq # client-to-server
        server-to-client
    rcvBuffer size
    at server,client


network
```

```
Socket connectionSocket =
  welcomeSocket.accept();
```


TCP 3-way handshake




Step 1: A's Initial SYN Packet




Step 2: B's SYN-ACK Packet



Step 3: A's ACK of the SYN-ACK



TCP 3-way handshake: FSM



What if the SYN Packet Gets Lost?

- Suppose the SYN packet gets lost
 - Packet is lost inside the network, or:
 - Server discards the packet (e.g., it's too busy)
- Eventually, no SYN-ACK arrives
 - Sender sets a timer and waits for the SYN-ACK
 - ... and retransmits the SYN if needed
- How should the TCP sender set the timer?
 - Sender has no idea how far away the receiver is
 - Hard to guess a reasonable length of time to wait
 - SHOULD (RFCs 1122,2988) use default of 3 second,
 RFC 6298 use default of 1 second


SYN Loss and Web Downloads

- User clicks on a hypertext link
 - Browser creates a socket and does a "connect"
 - The "connect" triggers the OS to transmit a SYN
- If the SYN is lost...
 - 1-3 seconds of delay: can be very long
 - User may become impatient
 - ... and click the hyperlink again, or click "reload"
- User triggers an "abort" of the "connect"
 - Browser creates a new socket and another "connect"
 - Essentially, forces a faster send of a new SYN packet!
 - Sometimes very effective, and the page comes quickly


TCP: closing a connection

- client, server each close their side of connection
 - send TCP segment with FIN bit = I
- respond to received FIN with ACK
 - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled


Normal Termination, One at a Time




Normal Termination, Both Together



Simultaneous Closure




Abrupt Termination



- A sends a RESET (RST) to B
 - E.g., because application process on A crashed
- That's it
 - B does not ack the RST
 - Thus, RST is not delivered reliably
 - And: any data in flight is lost
 - But: if B sends anything more, will elicit another RST

TCP Finite State Machine



TCP SYN Attack (SYN flooding)

- Miscreant creates a fake SYN packet
 - Destination is IP address of victim host (usually some server)
 - Source is some spoofed IP address
- Victim host on receiving creates a TCP connection state i.e allocates buffers, creates variables, etc and sends SYN ACK to the spoofed address (half-open connection)
- * ACK never comes back
- After a timeout connection state is freed
- However for this duration the connection state is unnecessarily created
- Further miscreant sends large number of fake SYNs
 - Can easily overwhelm the victim
- Solutions:
 - Increase size of connection queue
 - Decrease timeout wait for the 3-way handshake
 - Firewalls: list of known bad source IP addresses
 - TCP SYN Cookies (explained on next slide)

TCP SYN Cookie

- On receipt of SYN, server does not create connection state
- It creates an initial sequence number (init_seq) that is a hash of source & dest IP address and port number of SYN packet (secret key used for hash)
 - Replies back with SYN ACK containing init_seq
 - Server does not need to store this sequence number
- If original SYN is genuine, an ACK will come back
 - Same hash function run on the same header fields to get the initial sequence number (init_seq)
 - Checks if the ACK is equal to (init_seq+1)
 - Only create connection state if above is true
- If fake SYN, no harm done since no state was created

http://etherealmind.com/tcp-syn-cookies-ddos-defence/

Quiz: TCP Connection Management?



Roughly how much time does it take for both the TCP Sender and Receiver to establish connection state since the connect() call?

- A. RTT
- B. I.5RTT
- c. 2RTT
- D. 3RTT

Transport Layer: Outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer


- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

Principles of congestion control

congestion:

- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- a top-10 problem!

Congestion



Incoming rate is faster than outgoing link can support.

Quiz: What's the worst that can happen?





A: This is no problem. Senders just keep transmitting, and it'll all work out.


B: There will be retransmissions, but the network will still perform without much trouble.


C: Retransmissions will become very frequent, causing a serious loss of efficiency


D: The network will become completely unusable













that has no hope of crossing link B.)

Congestion Collapse



Congestion Collapse



Without congestion control


congestion:

- Increases delivery latency
 - Variable delays
 - If delays > RTO, sender retransmits
- Increases loss rate
 - Dropped packets also retransmitted
- Increases retransmissions, many unnecessary
 - Wastes capacity of traffic that is never delivered
 - Increase in load results in decrease in useful work done
- Increases congestion, cycle continues ...

Cost of Congestion

- Knee point after which
 - Throughput increases slowly
 - Delay increases fast

- Cliff point after which
 - Throughput starts to drop to zero (congestion collapse)
 - Delay approaches infinity



Congestion Collapse

This happened to the Internet (then NSFnet) in 1986

- Rate dropped from a blazing 32 Kbps to 40bps
- This happened on and off for two years
- In 1988, Van Jacobson published "Congestion Avoidance and Control"
- The fix: senders voluntarily limit sending rate

Approaches towards congestion control

two broad approaches towards congestion control:

end-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

network-assisted congestion control:

- routers provide feedback to end systems
 - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
 - explicit rate for sender to send at

Transport Layer: Outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

TCP's Approach in a Nutshell

- TCP connection has window
 - Controls number of packets in flight
- TCP sending rate:
 - roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

rate
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec



Vary window size to control sending rate

All These Windows...

- Congestion Window: CWND
 - How many bytes can be sent without overflowing routers
 - Computed by the sender using congestion control algorithm
- Flow control window: Advertised / Receive Window (RWND)
 - How many bytes can be sent without overflowing receiver's buffers
 - Determined by the receiver and reported to the sender
- Sender-side window = minimum(CWND, RWND)
 - Assume for this lecture that RWND >> CWND



- This lecture will talk about CWND in units of MSS
 - (Recall MSS: Maximum Segment Size, the amount of payload data in a TCP packet)
 - This is only for pedagogical purposes

 Keep in mind that real implementations maintain CWND in bytes

Two Basic Questions

* How does the sender detect congestion?

How does the sender adjust its sending rate?



Quiz: What is a "congestion event"

A: A segment loss (but how can the sender be sure of this?)

B: Increased delays

C: Receiving duplicate acknowledgement(s)

D: A retransmission timeout firing

E: Some subset of A, B, C & D (what is the subset?)



Quiz: How should we set CWND?

A: We should keep raising it until a "congestion event" then back off slightly until we notice no more events

B: We should raise it until a "congestion event", then go back to I and start raising it again


C: We should raise it until a "congestion event", then go back to median value and start raising it again

D: We should sent as fast as possible at all times

Not All Losses the Same

- Duplicate ACKs: isolated loss
 - dup ACKs indicate network capable of delivering some segments
- Timeout: much more serious
 - Not enough dup ACKs
 - Must have suffered several losses
- Will adjust rate differently for each case

RECAP: TCP fast retransmit




Rate Adjustment

- Basic structure:
 - Upon receipt of ACK (of new data): increase rate
 - Upon detection of loss: decrease rate
- * How we increase/decrease the rate depends on the phase of congestion control we're in:
 - Discovering available bottleneck bandwidth vs.
 - Adjusting to bandwidth variations

TCP Slow Start (Bandwidth discovery)

- when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = I MSS
 - double cwnd every RTT (full ACKs)
 - Simpler implementation achieved by incrementing cwnd for every ACK received
 - cwnd += I for each ACK
- <u>summary:</u> initial rate is slow but ramps up exponentially fast



Adjusting to Varying Bandwidth


- Slow start gave an estimate of available bandwidth
- Now, want to track variations in this available bandwidth, oscillating around its current value
 - Repeated probing (rate increase) and backoff (rate decrease)
 - Known as Congestion Avoidance (CA)
- * TCP uses: "Additive Increase Multiplicative Decrease" (AIMD)
 - We'll see why shortly...

AIMD


- * approach: sender increases transmission rate (window size), probing for usable bandwidth, until another congestion event occurs
 - additive increase: increase cwnd by I MSS every RTT until loss detected
 - For each successful RTT (all ACKS), cwnd = cwnd +1
 - Simple implementation: for each ACK, cwnd = cwnd +
 1/cwnd
 - multiplicative decrease: cut cwnd in half after loss

cwnd: TCP sender

AIMD saw tooth behavior: probing for bandwidth



Leads to the TCP "Sawtooth"



Slow-Start vs. AIMD

- When does a sender stop Slow-Start and start Additive Increase?
- Introduce a "slow start threshold" (ssthresh)
 - Initialized to a large value
- Convert to AI when cwnd = ssthresh, sender switches from slow-start to AIMD-style increase
 - On timeout, ssthresh = CWND/2

Implementation

State at sender

- CWND (initialized to a small constant)
- ssthresh (initialized to a large constant)
- [Also dupACKcount and timer, as before]

Events

- ACK (new data)
- dupACK (duplicate ACK for old data)
- Timeout

Event: ACK (new data)

If CWND < ssthresh
 CWND += +
 2*MSS packets per ACK
 Hence after one RTT (All ACKs with no drops):
 CWND = 2xCWND

Event: ACK (new data)

- If CWND < ssthresh</p>
 - CWND += I

Slow start phase

- Else
 - CWND = CWND +I/CWND

"Congestion
Avoidance" phase
(additive increase)

Hence after one RTT (All ACKs with no drops):

CWND = CWND + I


Event: dupACK

- dupACKcount ++
- If dupACKcount = 3 /* fast retransmit */
 - ssthresh = CWND/2
 - CWND = CWND/2

Event: TimeOut


- On Timeout
 - ssthresh ← CWND/2
 - CWND ← I

Example




Slow-start restart: Go back to CWND = 1 MSS, but take advantage of knowing the previous value of CWND

TCP Flavours



- TCP-Reno (Assumed Default in this course)
 - cwnd = I on timeout
 - cwnd = cwnd/2 on triple dup ACK
- TCP-Tahoe (Old/original version)
 - cwnd = I on both triple dup ACK & timeout
- * Figure 3.52, page 304 of 7th Ed. textbook assumes a special TCP Reno that implements Fast Recovery, which is out of scope in this course.

TCP/Reno (Default in this course): Big Picture



TD: Triple duplicate acknowledgements TO: Timeout


Quiz: TCP Congestion Control?



In the figure how many congestion avoidance intervals

can you identify?

- A. 0
- B.
- C. 2
- D. 3
- E. 4




Quiz: TCP Congestion Control?



In the figure how many slow start intervals can you identify?

- A. 0
- B.
- C. 2
- D. 3
- E. 4








In the figure after the 16th transmission round, segment loss is detected by ______?

- A. Triple Dup Ack
- B. Timeout




Quiz: TCP Congestion Control?



In the figure what is the initial value of sstresh (steady state threshold)?

- A. 0
- B. 28
- C. 32
- D. 42
- E. 64




Quiz: TCP Congestion Control?



In the figure what is the value of sstresh (steady state threshold) at the 18th round?

- Α. Ι
- B. 32
- C. 42
- D. 21
- E. 20



Transport Layer: Summary

- principles behind transport layer services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control
- instantiation, implementation in the Internet
 - UDP
 - TCP

next:

- leaving the network "edge" (application, transport layers)
- into the network "core"