Building Kernels

This page details the process of building custom <u>kernels</u> for Android devices. These instructions guide you through the process of selecting the right sources, building the kernel, and embedding the results into a system image built from the Android Open Source Project (AOSP).

You can acquire more recent kernel sources by using Repo; build them without further configuration by running build/build.sh from the root of your source checkout.

Note: The root of the kernel source checkout contains <code>build/build.sh</code>. The Android tree contains only prebuilt kernel binaries. The kernel trees contain the kernel sources and all tools to build the kernels, including this script.

To build older kernels or kernels not listed on this page, refer to the instructions on how to build legacy kernels.

[Downloading sources and build tools]

For recent kernels, use <u>repo</u> to download the sources, toolchain, and build scripts. Some kernels (for example, the Pixel 3 kernels) require sources from multiple git repositories, while others (for example, the common kernels) require only a single source. Using the <u>repo</u> approach ensures a correct source directory setup.

Download the sources for the appropriate branch:

```
mkdir android-kernel && cd android-kernel
repo init -u https://android.googlesource.com/kernel/manifest -b BRANCH
repo sync
```

The following table lists the BRANCH names for kernels available through this method.

Device	Binary path in AOSP tree	Repo branches
Pixel 6 (oriole) \ android12L Pixel 6 Pro (raven)	device/google/raviole-kernel	android-gs-raviole-5.10-
Pixel 5a (barbet) android12L	device/google/barbet-kernel	android-msm-barbet-4.19-
Pixel 5 (redfin) \ android12L Pixel 4a (5G) (bramble)	device/google/redbull-kernel	android-msm-redbull-4.19-
Pixel 4a (sunfish) android12L	device/google/sunfish-kernel	android-msm-sunfish-4.14-
Pixel 4 (flame)\ android12L Pixel 4 XL (coral)	device/google/coral-kernel	android-msm-coral-4.14-

Pixel 3a (sargo) \ android12L Pixel 3a XL (bonito)	device/google/bonito-kernel	android-msm-bonito-4.9-
Pixel 3 (blueline) \ 4.9-android12 Pixel 3 XL (crosshatch)	device/google/crosshatch-kernel	android-msm-crosshatch-
Pixel 2 (walleye) \ android10-qpr3 Pixel 2 XL (taimen)	device/google/wahoo-kernel	android-msm-wahoo-4.4-
Pixel (sailfish) \ pie-qpr2 Pixel XL (marlin)	device/google/marlin-kernel	android-msm-marlin-3.18-
Hikey960	device/linaro/hikey-kernel	hikey-linaro-android-4.14\hikey-linaro-android-4.19\common-android12-5.4
Beagle x15	device/ti/beagle_x15-kernel	omap-beagle-x15-android-
4.19		omap-beagle-x15-android-
Android Common Kernel	N/A	common-android-4.4\
		common-android-4.9\ common-android-4.14\
		common-android-4.14\ common-android-4.19\
		common-android-4.19\
stable\		Common android 1.17
		common-android11-5.4\
		common-android12-5.4\
		common-android12-5.10\
		common-android-mainline

Note: You can switch among different branches within one Repo checkout. The common kernel manifests (and most others) define the kernel git repository to be cloned fully (not shallow), which enables fast switching among them. Switching to a different branch is similar to initializing a branch; the <code>-u</code> parameter is optional. For example, to switch to <code>common-android-mainline</code> from your existing Repo checkout, run:

```
$ repo init -b common-android-mainline && repo sync.
```

[Building the kernel]

Then build the kernel with this:

```
build/build.sh
```

Note: Common kernels are generic, customizable kernels and therefore don't define a default configuration. See <u>Customize the kernel build</u> to find out how to specify the build configuration for common kernels. For example, to build the GKI kernel for the aarch64 platform, run:

```
$ BUILD CONFIG=common/build.config.gki.aarch64 build/build.sh
```

The kernel binary, modules, and corresponding image are located in the out/BRANCH/dist directory.

[Building the GKI modules]

Android 11 introduced <u>GKI</u>, which separates the kernel into a Google-maintained kernel image and vendor maintained-modules, which are built separately.

This example shows a kernel image configuration:

```
BUILD_CONFIG=common/build.config.gki.x86_64 build/build.sh
```

This example shows a module configuration (Cuttlefish and Emulator):

```
BUILD_CONFIG=common-modules/virtual-device/build.config.cuttlefish.x86_64 build/build.sh
```

In Android 12 Cuttlefish and Goldfish converge, so they share the same kernel: virtual_device . To build that kernel's modules, use this build configuration:

```
BUILD_CONFIG=common-modules/virtual-device/build.config.virtual_device.x86_64 build/build.sh
```

[Running the kernel]

There are multiple ways to run a custom-built kernel. The following are known ways suitable for various development scenarios.

[Embedding into the Android image build]

Copy Image.lz4-dtb to the respective kernel binary location within the AOSP tree and rebuild the boot image.

Alternatively, define the TARGET_PREBUILT_KERNEL variable while using make bootimage (or any other make command line that builds a boot image). This variable is supported by all devices as it's set up via device/common/populate-new-device.sh. For example:

```
export TARGET_PREBUILT_KERNEL=DIST_DIR/Image.lz4-dtb
```

[Flashing and booting kernels with fastboot]

Most recent devices have a bootloader extension to streamline the process of generating and booting a boot image.

To boot the kernel without flashing:

```
adb reboot bootloader
fastboot boot Image.lz4-dtb
```

Using this method, the kernel isn't actually flashed, and won't persist across a reboot.

Note: Kernel names differ by device. To locate the correct filename for your kernel, refer to device/VENDOR/NAMEkernel in the AOSP tree.

Customizing the kernel build

The build process and outcome can be influenced by environment variables. Most of them are optional and each kernel branch should come with a proper default configuration. The most frequently used ones are listed here. For a complete (and up-to-date) list, refer to <code>build/build.sh</code>.

Environment variable	Description	Example
BUILD_CONFIG	Build config file from where you initialize the build environment. The location must be defined relative to the Repo root directory. Defaults to build.config. Mandatory for common kernels.	BUILD_CONFIG=common/build.config.gki.aarch64
СС	Override compiler to be used. Falls back to the default compiler defined by build.config.	CC=clang
DIST_DIR	Base output directory for the kernel distribution.	DIST_DIR=/path/to/my/dist
OUT_DIR	Base output directory for the kernel build.	OUT_DIR=/path/to/my/out
SKIP_DEFCONFIG	Skip make defconfig	SKIP_DEFCONFIG=1
SKIP_MRPROPER	Skip make mrproper	SKIP_MRPROPER=1

[Custom kernel config for local builds]

If you need to switch a kernel configuration option regularly, for example, when working on a feature, or if you need an option to be set for development purposes, you can achieve that flexibility by maintaining a local modification or copy of the build config.

Set the variable POST_DEFCONFIG_CMDS to a statement that is evaluated right after the usual make defconfig step is done. As the build.config files are sourced into the build environment, functions defined in build.config can be called as part of the post-defconfig commands.

A common example is disabling link time optimization (LTO) for crosshatch kernels during development. While LTO is beneficial for released kernels, the overhead at build time can be significant. The following snippet added to the local build.config disables LTO persistently when using build/build.sh.

```
POST_DEFCONFIG_CMDS="check_defconfig && update_debug_config"

function update_debug_config() {

    $/.config \
    -d LTO \
    -d LTO_CLANG \
    -d CFI \
    -d CFI_PERMISSIVE \
    -d CFI_CLANG

(cd $ && \
```

```
make O=$ olddefconfig)
}
```

[Identifying kernel versions]

You can identify the correct version to build from two sources: the AOSP tree and the system image.

[Kernel version from AOSP tree]

The AOSP tree contains prebuilt kernel versions. The git log reveals the correct version as part of the commit message:

```
cd $AOSP/device/VENDOR/NAME
git log --max-count=1
```

If the kernel version isn't listed in the git log, obtain it from the system image, as described below.

[Kernel version from system image]

To determine the kernel version used in a system image, run the following command against the kernel file:

```
file kernel

For Image.lz4-dtb files, run:

grep -a 'Linux version' Image.lz4-dtb
```

[Building a Boot Image]

It's possible to build a boot image using the kernel build environment. To do this you need a ramdisk binary, which you can obtain by downloading a GKI boot image and unpacking it. Any GKI boot image from the associated Android release will work.

```
tools/mkbootimg/unpack_bootimg.py --boot_img=boot-5.4-gz.img
mv tools/mkbootimg/out/ramdisk gki-ramdisk.lz4
```

The target folder is the top-level directory of the kernel tree (the current working directory).

If you're developing with AOSP master, you can instead download the <code>ramdisk-recovery.img</code> build artifact from an aosp_arm64 build on ci.android.com and use that as your ramdisk binary.

When you have a ramdisk binary and have copied it to <code>gki-ramdisk.lz4</code> in the root directory of the kernel build, you can generate a boot image by executing:

```
BUILD_BOOT_IMG=1 SKIP_VENDOR_BOOT=1 KERNEL_BINARY=Image
GKI_RAMDISK_PREBUILT_BINARY=gki-ramdisk.lz4
BUILD_CONFIG=common/build.config.gki.aarch64 build/build.sh
```

If you're working with x86-based architecture, replace Image with bzImage, and aarch64 with x86 64:

```
BUILD_BOOT_IMG=1 SKIP_VENDOR_BOOT=1 KERNEL_BINARY=bzImage
GKI_RAMDISK_PREBUILT_BINARY=gki-ramdisk.lz4
BUILD_CONFIG=common/build.config.gki.x86_64 build/build.sh
```

That file is located in the artifact directory ${\tt gkernel_ROOT/out/gkernel_Version/dist}$.

The boot image is located at $\verb"out"/<kernel branch>/dist/boot.img".$