Establishing a Build Environment

This section describes how to set up your local work environment to build the Android source files. You must use Linux; building under either MacOS or Windows isn't supported. Keep in mind the important change to the //usr/bin/python binary as well.

For an overview of the entire code-review and code-update process, see .

Note: All commands in this site are preceded by a dollar sign (\$) to differentiate them from output or entries within files. Use the *Click to copy* feature located at the top right of each command box to copy all lines without the dollar signs, or triple-click each line to copy it individually without the dollar sign.

Choosing a branch

Some requirements for the build environment are determined by the version of the source code that you plan to compile. For a full list of available branches, see <u>Build Numbers</u>. You can also choose to download and build the latest source code (called <u>master</u>), in which case you simply omit the branch specification when you initialize the repository.

After selecting a branch, follow the appropriate instructions below to set up your build environment.

[Setting up a Linux build environment]

These instructions apply to all branches, including master.

The Android build is routinely tested in house on Ubuntu LTS (14.04) and Debian testing. Most other distributions should have the required build tools available.

For Gingerbread (2.3.x) and higher versions, including the master branch, a 64-bit environment is required. Older versions can be compiled on 32-bit systems.

Note: See <u>Requirements</u> for the complete list of hardware and software requirements, then follow the detailed instructions for Ubuntu below.

Installing required packages (Ubuntu 18.04)

You need a 64-bit version of Ubuntu.

sudo apt-get install git-core gnupg flex bison build-essential zip curl zlib1g-dev gcc-multilib g++-multilib libc6-dev-i386 libncurses5 lib32ncurses5-dev x11proto-coredev libx11-dev lib32z1-dev libg11-mesa-dev libxml2-utils xsltproc unzip fontconfig