An Essential Guide to Oracle Tablespace Group

Summary: In this lab, you will learn about Oracle temporary tablespace group and how to use the tablespace group effectively to optimize internal Oracle operations.

Oracle tablespace groups

A tablespace group typically consists of multiple temporary tablespaces. A tablespace group allows a user to consume temporary space from multiple temporary tablespaces, instead of a single temporary tablespace. By using a tablespace group, you can avoid the problem caused when one temporary tablespace does not have enough space to hold the results of a sort.

The following describes the property of a tablespace group:

- A tablespace group must contain at least one temporary tablespace.
- The name of a tablespace group cannot be the same as any tablespace.
- A tablespace group can be assigned as a *default temporary tablespace* for the database or a temporary tablespace for a user.

Creating a tablespace group

Oracle does not provide a statement to create a tablespace group explicitly. You create a tablespace group when you assign the first temporary tablespace to the group using the CREATE TEMPORARY TABLESPACE statement Or ALTER TABLESPACE statement.

Removing a tablespace group

Oracle automatically drops a tablespace group when you remove the last temporary tablespace from the tablespace group.

Viewing tablespace groups

The view DBA TABLESPACE GROUPS lists all tablespace groups and their member temporary tablespace.

```
SELECT * FROM DBA_TABLESPACE_GROUPS;
```

Oracle tablespace group examples

First, create a new temporary tablespace and assign it to the tablespace group tbs1:

```
CREATE TEMPORARY TABLESPACE temp2

TEMPFILE 'temp2.dbf'

SIZE 100M

TABLESPACE GROUP tbsg1;
```

Because the tablespace group tbsg1 has not existed, the statement also created the tablespace group tbsg1.

Second, assign the temp temporary tablespace temp to the tbsg1 tablespace group:

```
ALTER TABLESPACE temp TABLESPACE GROUP tbsg1;
```

Third, assign the tablespace group gbsg1 as the default temporary tablespace:

```
ALTER DATABASE DEFAULT TEMPORARY TABLESPACE tbsg1;
```

Finally, verify the current default temporary tablespace:

```
SELECT

property_name,

property_value

FROM

database_properties

WHERE

property_name='DEFAULT_TEMP_TABLESPACE';
```



In this lab, you have learned about the Oracle tablespace group and how to use the tablespace group effectively to optimize internal Oracle operations.