# **Oracle STARTUP - How to Start an Oracle Database Instance**

**Summary**: In this lab, you will learn how to use the Oracle STARTUP command to start an Oracle Database instance.

Connect with sqlplus CLI:


sqlplus / as sysdba

To start up a database instance, you use the STARTUP command:

STARTUP

```
[oracle@0f0c8fc405b1 ~]$ sqlplus / as sysdba
SQL*Plus: Release 19.0.0.0.0 - Production on Fri Apr 26 17:16:13 2024
Version 19.3.0.0.0
Copyright (c) 1982, 2019, Oracle. All rights reserved.
Connected to an idle instance.
SQL> SQL>
SQL> STARTUP
ORACLE instance started.
Total System Global Area
                          788526632 bytes
Fixed Size
                             9139752 bytes
                           226492416 bytes
Variable Size
                           545259520 bytes
Database Buffers
Redo Buffers
                             7634944 bytes
Database mounted.
Database opened.
```

When the Oracle Database starts an instance, it goes through the following stages:  ${\tt NOMOUNT}$ ,  ${\tt MOUNT}$ , and  ${\tt OPEN}$ .



The STARTUP command allows you to control the stage of the database instance.

## 1) NOMOUNT stage

In the NOMOUNT stage, Oracle carries the following steps:

- First, search for a server parameter file in the default location. You can override the default behavior by
  using the SPFILE or PFILE parameters in the STARTUP command.
- Next, read the parameter file to get the values of the initialization parameters.
- Then, allocate the system global area (SGA) based on the initialization parameter settings.
- $\bullet$  After that, start the Oracle background processes such as  $\,$  SMON ,  $\,$  PMON , and  $\,$  LGWR .
- Finally, open the alert log and trace files and record all explicit parameters to the alert log in the valid parameter syntax.

At the NOMOUNT stage, Oracle does not associate the database with the instance.

## 2) MOUNT stage

In the MOUNT stage, Oracle associates a database with an instance. In other words, the instance mounts the database.

The instance carries the following steps to mount a database:

- First, get the name of the database control files specified in the CONTROL\_FILE initialization parameter.
- Second, open the control files.
- Third, find the name of the data files and the online redo log files.

When a database is mounted, the database is only available to database administrators, not all users.


## 3) OPEN stage

In the OPEN stage, Oracle performs the following actions:

- First, open the online data files in tablespaces other than the undo tablespaces.
- Then, select an undo tablespace. The instance uses the default undo tablespace if an undo tablespace is
  specified in the UNDO\_TABLESPACE initialization parameter. Otherwise, it will select the first available
  undo tablespace.
- Finally, open the online redo log files.

When Oracle opens a mounted database, the database is available for normal operations.

The following picture illustrates the Oracle database startup process:



# Oracle STARTUP command

**Note:** Run SHUTDOWN command before running each command below first. Otherwise, you will get cannot start already running Oracle error.

The basic syntax of the STARTUP command is as follows:

STARTUP;

It is equivalent to starting the database instance in the OPEN stage:

STARTUP OPEN;

To start up a database instance in the NOMOUNT stage, you use the following command:

STARTUP NOMOUNT;

To bring the database to the next stage, you use the ALTER DATABASE statement. For example, this statement brings the database from the NOMOUNT to the MOUNT stage:

ALTER DATABASE MOUNT;

## **Oracle STARTUP command example**

First, launch the SQL\*Plus program and log in to the Oracle Database as the SYS user.

Second, issue the SHUTDOWN IMMEDIATE command to shut down the database:

shutdown immediate;

Here is the output:


```
Database dismounted.

ORACLE instance shut down.
```

Third, start the database instance at the OPEN stage:

```
startup
```

Here is the output:



Fourth, shut down the instance again:

```
shutdown immediate;
```

Fifth, start the database instance at the MOUNT state:

```
startup mount;
```

## The output is:

```
ORACLE instance started.

Total System Global Area 2550136832 bytes
Fixed Size 3835304 bytes
Variable Size 738200152 bytes
Database Buffers 1795162112 bytes
Redo Buffers 12939264 bytes
```

Sixth, check the current status of the database instance by querying the v\$instance view:

```
SELECT
  instance_name,
  status
FROM
  v$instance;
```

#### Output:

INSTANCE\_NAME STATUS

fenagodb MOUNTED

Seventh, bring the database to the OPEN stage by using the ALTER DATABASE command:

ALTER DATABASE OPEN;

## Output:

Database altered.

Finally, check the status of the database by executing the following statement:

SELECT

instance\_name,

status

FROM

v\$instance;

Now, the database is open and available for normal operations.

INSTANCE NAME STATUS

fenagodb OPEN

In this lab, you have learned how to start a database instance using the Oracle  $\,\,$  STARTUP command.