tsm user-identity-store

You can use the tsm user-identity-store commands to modify the settings of the identity store for Tableau Server after the initial configuration.

The initial configuration of the identity store is part of the installation process. See Configure Initial Node Settings.

For introduction to identity store concepts, see <u>Identity Store</u>.

For LDAP/Active Directory configuration reference table, see External Identity Store Configuration Reference.

- get-group-mappings
- get-user-mappings
- list
- set-connection
- <u>set-group-mappings</u>
- <u>set-user-mappings</u>
- <u>verify-group-mappings</u>
- verify-user-mappings

tsm user-identity-store get-group-mappings [options]

Displays identity store group mappings.

Synopsis

tsm user-identity-store get-group-mappings [global options]

tsm user-identity-store get-user-mappings [options]

Displays identity store user mappings.

Synopsis

tsm user-identity-store get-user-mappings [global options]

tsm user-identity-store list [options]

Lists user-identity configuration.

Synopsis

tsm user-identity-store list [options] [global options]

Options

-v, --verbose

Optional.


Lists all configuration parameters.

tsm user-identity-store set-connection [options]

Sets identity store connection parameters.

Synopsis

tsm user-identity-store set-connection --kerbkeytab <kerbkeytab> [options]
[global options]



-n,--nickname <nickname>

Optional.

NetBIOS name (nickname).

tsm user-identity-store set-group-mappings [options]

Sets identity store group mappings and configures LDAP directories that implement an arbitrary or custom schema.

Synopsis

```
tsm user-identity-store set-group-mappings [options] [global options]
```

Options

-b,--basefilter < groupbasefilter>

Optional.

Set group BaseFilter value.

-cn,--classnames < group_classnames >

Optional.

Override default user classname values (contains "group" string) with the values you set here. You can provide multiple classnames separated by commas.

-d,--description <description>

Optional.

Group description.

-e,--groupemail < groupemail >

Optional.

Group email value.

-m,--member <member>

Optional.

Set the group members.

-n,--groupname < groupname>

Optional.


Name of the group.

tsm user-identity-store set-user-mappings [options]

Sets identity store user mappings and configures LDAP directories that implement an arbitrary or custom schema.

Synopsis

```
tsm user-identity-store set-user-mappings --certificate <certificate> [options]
[global options]
```



Synopsis

tsm user-identity-store verify-group-mappings --verify <group name> [global options]

Options

-v,--verify <group_name>

Optional.

Name of group to search for.

tsm user-identity-store verify-user-mappings [options]

Validates configuration for LDAP user mapping.

Synopsis

```
tsm user-identity-store verify-user-mappings --verify <user name> [global options]
```

Options

-v,--verify <user_name>

Optional.

Name of user to search for.

Global options

-h, --help

Optional.

Show the command help.

-p, --password <password>

Required, along with -u or --username if no session is active.

Specify the password for the user specified in -u or --username.

If the password includes spaces or special characters, enclose it in quotes:

```
--password "my password"
```

-s, --server https://<hostname>:8850

Optional.

Use the specified address for Tableau Services Manager. The URL must start with https://stam_hostname: 8850 . If no server is specified, https://stam_hostname: 8850 is assumed.

--trust-admin-controller-cert

Optional.

Use this flag to trust the self-signed certificate on the TSM controller. For more information about certificate trust and CLI connections, see <u>Connecting TSM clients</u>.

```
-u, --username <user>
```

Specify a user account. If you do not include this option, the command is run using credentials you signed in with.