内核枚举进程使用 PspCidTable 这个未公开的函数,它能最大的好处是能得到进程的EPROCESS地址,由于是未公开的函数,所以我们需要变相的调用这个函数,通过 PsLookupProcessByProcessId 函数查到进程的EPROCESS,如果 PsLookupProcessByProcessId 返回失败,则证明此进程不存在,如果返回成功则把EPROCESS、PID、PPID、进程名等通过DbgPrint打印到屏幕上。

内核枚举进程: 进程就是活动起来的程序,每一个进程在内核里,都有一个名为 EPROCESS 的结构记录 它的详细信息,其中就包括进程名,PID,PPID,进程路径等,通常在应用层枚举进程只列出所有进程 的编号即可,不过在内核层需要把它的 EPROCESS 地址给列举出来。

内核枚举进程使用 PspCidTable 这个未公开的函数,它能最大的好处是能得到进程的EPROCESS地址,由于是未公开的函数,所以我们需要变相的调用这个函数,通过 PsLookupProcessByProcessId 函数查到进程的EPROCESS,如果 PsLookupProcessByProcessId 返回失败,则证明此进程不存在,如果返回成功则把EPROCESS、PID、PPID、进程名等通过DbgPrint打印到屏幕上。

```
#include <ntifs.h>
NTKERNELAPI UCHAR* PSGetProcessImageFileName(IN PEPROCESS Process); //未公开的进行
导出即可
NTKERNELAPI HANDLE PSGetProcessInheritedFromUniqueProcessId(IN PEPROCESS
Process);//未公开进行导出
// 根据进程ID返回进程EPROCESS结构体,失败返回NULL
PEPROCESS LookupProcess(HANDLE Pid)
   PEPROCESS eprocess = NULL;
   NTSTATUS Status = STATUS_UNSUCCESSFUL;
   Status = PsLookupProcessByProcessId(Pid, &eprocess);
   if (NT_SUCCESS(Status))
       return eprocess;
   return NULL;
}
VOID EnumProcess()
    PEPROCESS eproc = NULL;
    for (int temp = 0; temp < 100000; temp += 4)
       eproc = LookupProcess((HANDLE)temp);
       if (eproc != NULL)
            DbgPrint("进程名: %s --> 进程PID = %d --> 父进程PPID =
%d\r\n",PSGetProcessImageFileName(eproc),PSGetProcessId(eproc),
               PsGetProcessInheritedFromUniqueProcessId(eproc));
           ObDereferenceObject(eproc);
       }
    }
}
VOID UnDriver(PDRIVER_OBJECT driver)
   DbgPrint(("Uninstall Driver Is OK \n"));
}
```

```
NTSTATUS DriverEntry(IN PDRIVER_OBJECT Driver, PUNICODE_STRING RegistryPath)
{
    EnumProcess();
    Driver->DriverUnload = UnDriver;
    return STATUS_SUCCESS;
}
```



内核枚举线程: 内核线程的枚举与进程相似,线程中也存在一个ETHREAD结构,但在枚举线程之前需要先来枚举到指定进程的eprocess结构,然后在根据eprocess结构对指定线程进行枚举。

```
#include <ntddk.h>
#include <windef.h>
// 声明API
NTKERNELAPI UCHAR* PSGetProcessImageFileName(IN PEPROCESS Process);
NTKERNELAPI NTSTATUS PSLookupProcessByProcessId(HANDLE Id, PEPROCESS *Process);
NTKERNELAPI NTSTATUS PsLookupThreadByThreadId(HANDLE Id, PETHREAD *Thread);
NTKERNELAPI PEPROCESS IoThreadToProcess(PETHREAD Thread);
//根据进程ID返回进程EPROCESS,失败返回NULL
PEPROCESS LookupProcess(HANDLE Pid)
{
    PEPROCESS eprocess = NULL;
    if (NT_SUCCESS(PsLookupProcessByProcessId(Pid, &eprocess)))
        return eprocess;
   else
        return NULL;
}
//根据线程ID返回线程ETHREAD,失败返回NULL
PETHREAD LookupThread(HANDLE Tid)
{
    PETHREAD ethread;
   if (NT_SUCCESS(PsLookupThreadByThreadId(Tid, &ethread)))
       return ethread;
   else
        return NULL;
}
//枚举指定进程中的线程
VOID EnumThread(PEPROCESS Process)
{
```

```
ULONG i = 0, c = 0;
   PETHREAD ethrd = NULL;
   PEPROCESS eproc = NULL;
   for (i = 4; i<262144; i = i + 4) // 一般来说没有超过100000的PID和TID
       ethrd = LookupThread((HANDLE)i);
       if (ethrd != NULL)
           //获得线程所属进程
           eproc = IoThreadToProcess(ethrd);
           if (eproc == Process)
               //打印出ETHREAD和TID
               DbgPrint("线程: ETHREAD=%p TID=%ld\n",ethrd,
(ULONG)PsGetThreadId(ethrd));
           ObDereferenceObject(ethrd);
   }
}
// 通过枚举的方式定位到指定的进程,这里传递一个进程名称
VOID MyEnumThread(char *ProcessName)
{
   ULONG i = 0;
   PEPROCESS eproc = NULL;
   for (i = 4; i<100000000; i = i + 4)
       eproc = LookupProcess((HANDLE)i);
       if (eproc != NULL)
       {
           ObDereferenceObject(eproc);
           if (strstr(PsGetProcessImageFileName(eproc), ProcessName) != NULL)
               EnumThread(eproc); // 相等则说明是我们想要的进程,直接枚举其中的线程
           }
       }
   }
}
VOID DriverUnload(IN PDRIVER_OBJECT DriverObject){}
NTSTATUS DriverEntry(IN PDRIVER_OBJECT DriverObject, IN PUNICODE_STRING
RegistryPath)
{
   MyEnumThread("calc.exe");
   DriverObject->DriverUnload = DriverUnload;
   return STATUS_SUCCESS;
}
```

内核枚举进程模块: 枚举进程中的所有模块信息,DLL模块记录在 PEB 的 LDR 链表里,LDR 是一个双向链表,枚举链表即可,相应的卸载可使用 MmunmapViewofSection 函数,分别传入进程的 EPROCESS,DLL模块基址即可。

```
#include <ntddk.h>
#include <windef.h>
//声明结构体
typedef struct _KAPC_STATE
    LIST_ENTRY ApcListHead[2];
    PKPROCESS Process;
   UCHAR KernelApcInProgress;
   UCHAR KernelApcPending;
   UCHAR UserApcPending;
} KAPC_STATE, *PKAPC_STATE;
typedef struct _LDR_DATA_TABLE_ENTRY
{
                    InLoadOrderLinks;
    LIST_ENTRY64
   LIST_ENTRY64
                    InMemoryOrderLinks;
   LIST_ENTRY64
                    InInitializationOrderLinks;
    PVOID
                    DllBase;
    PVOID
                    EntryPoint;
   ULONG
                    SizeOfImage;
   UNICODE_STRING FullDllName;
   UNICODE_STRING BaseDllName;
   ULONG
                    Flags;
   USHORT
                    LoadCount;
   USHORT
                    TlsIndex;
    PVOID
                    SectionPointer;
                    CheckSum;
   ULONG
    PVOID
                    LoadedImports;
    PVOID
                    EntryPointActivationContext;
                    PatchInformation;
    PVOID
                    ForwarderLinks;
    LIST_ENTRY64
   LIST_ENTRY64
                    ServiceTagLinks;
                    StaticLinks;
    LIST_ENTRY64
    PVOID
                    ContextInformation;
                    OriginalBase;
    ULONG64
                    LoadTime;
    LARGE_INTEGER
} LDR_DATA_TABLE_ENTRY, *PLDR_DATA_TABLE_ENTRY;
ULONG64 LdrInPebOffset = 0x018;
                                    //peb.ldr
ULONG64 ModListInPebOffset = 0x010; //peb.ldr.InLoadOrderModuleList
```

```
//声明API
NTKERNELAPI UCHAR* PSGetProcessImageFileName(IN PEPROCESS Process);
NTKERNELAPI PPEB PsGetProcessPeb(PEPROCESS Process);
NTKERNELAPI HANDLE PSGetProcessInheritedFromUniqueProcessId(IN PEPROCESS
Process);
//根据进程ID返回进程EPROCESS,失败返回NULL
PEPROCESS LookupProcess(HANDLE Pid)
   PEPROCESS eprocess = NULL;
   if (NT_SUCCESS(PsLookupProcessByProcessId(Pid, &eprocess)))
       return eprocess;
   else
       return NULL;
}
//枚举指定进程的模块
VOID EnumModule(PEPROCESS Process)
   SIZE_T Peb = 0;
   SIZE_T Ldr = 0;
   PLIST_ENTRY ModListHead = 0;
   PLIST_ENTRY Module = 0;
   ANSI_STRING AnsiString;
   KAPC_STATE ks;
   //EPROCESS地址无效则退出
   if (!MmIsAddressValid(Process))
       return;
   //获取PEB地址
   Peb = (SIZE_T)PsGetProcessPeb(Process);
   //PEB地址无效则退出
   if (!Peb)
       return;
   //依附进程
   KeStackAttachProcess(Process, &ks);
   __try
   {
       //获得LDR地址
       Ldr = Peb + (SIZE_T)LdrInPebOffset;
       //测试是否可读,不可读则抛出异常退出
       ProbeForRead((CONST PVOID)Ldr, 8, 8);
       //获得链表头
       ModListHead = (PLIST_ENTRY)(*(PULONG64)Ldr + ModListInPebOffset);
       //再次测试可读性
       ProbeForRead((CONST PVOID)ModListHead, 8, 8);
       //获得第一个模块的信息
       Module = ModListHead->Flink;
       while (ModListHead != Module)
       {
           //打印信息: 基址、大小、DLL路径
           DbgPrint("模块基址=%p 大小=%ld 路径=%wZ\n",(PVOID)
((((PLDR_DATA_TABLE_ENTRY)Module)->DllBase),
               (ULONG)(((PLDR_DATA_TABLE_ENTRY)Module)->SizeOfImage), &
((((PLDR_DATA_TABLE_ENTRY)Module)->FullDllName));
```

```
Module = Module->Flink;
                        //测试下一个模块信息的可读性
                        ProbeForRead((CONST PVOID)Module, 80, 8);
                 }
         }
          __except (EXCEPTION_EXECUTE_HANDLER){;}
          //取消依附进程
         KeUnstackDetachProcess(&ks);
  }
  // 通过枚举的方式定位到指定的进程,这里传递一个进程名称
  VOID MyEnumModule(char *ProcessName)
   {
         ULONG i = 0;
         PEPROCESS eproc = NULL;
          for (i = 4; i<100000000; i = i + 4)
                 eproc = LookupProcess((HANDLE)i);
                 if (eproc != NULL)
                        ObDereferenceObject(eproc);
                        if (strstr(PsGetProcessImageFileName(eproc), ProcessName) != NULL)
                        {
                               EnumModule(eproc); // 相等则说明是我们想要的进程,直接枚举其中的线程
                        }
                 }
          }
  }
  VOID DriverUnload(IN PDRIVER_OBJECT DriverObject){}
  NTSTATUS DriverEntry(IN PDRIVER_OBJECT DriverObject, IN PUNICODE_STRING
  RegistryPath)
   {
         MyEnumModule("calc.exe");
         DriverObject->DriverUnload = DriverUnload;
          return STATUS_SUCCESS;
  }
 X DebugView on \DESKTOP-CCFGJFO (local)
File Edit Capture Options Computer Help
Debug Print
     0.00000000
                     [2084] Suspending
                    模块基址=00007FFCDE950000 大小=720896 路径=C:\Windows\System32\win32calc.exe

模块基址=00007FFCDE070000 大小=733184 路径=C:\Windows\SyStEM32\kteNELBASE.dl1

模块基址=00007FFCDD7F0000 大小=2699264 路径=C:\Windows\System32\kteNELBASE.dl1

模块基址=00007FFCDEE00000 大小=21950464 路径=C:\Windows\System32\xteNELBASE.dl1

模块基址=00007FFCDEE00000 大小=647168 路径=C:\Windows\System32\xtextc.dl1

模块基址=00007FFCDE00000 大小=303104 路径=C:\Windows\System32\xtextc.dl1

模块基址=00007FFCDE00000 大小=303104 路径=C:\Windows\System32\xtextc.dl1

模块基址=00007FFCDE000000 大小=1032192 路径=C:\Windows\System32\xtextc.dl1

模块基址=00007FFCDE000000 大小=187840 路径=C:\Windows\System32\xtextc.dl1

模块基址=00007FFCDEEA00000 大小=187840 路径=C:\Windows\System32\xtextc.dl1


模块基址=00007FFCDEEA00000 大小=1187840 路径=C:\Windows\System32\xtextc.dl1

植块基址=00007FFCDEEA00000 大小=1187840 路径=C:\Windows\System32\xtextc.dl1
     7.90247059
     7.90247297
     7,90247583
     7.90247917
7.90248156
     7,90248394
    7.90248632
7.90248966
10
     7.90249205
```

内核枚举加载SYS文件: 内核中的SYS文件也是通过双向链表的方式相连接的,我们可以通过遍历LDR_DATA_TABLE_ENTRY 结构(遍历自身DriverSection成员),就能够得到全部的模块信息。

```
#include <ntddk.h>
#include <wdm.h>
```

```
typedef struct _LDR_DATA_TABLE_ENTRY {
    LIST_ENTRY InLoadOrderLinks;
    LIST_ENTRY InMemoryOrderLinks;
    LIST_ENTRY InInitializationOrderLinks;
    PVOID DllBase;
    PVOID EntryPoint;
    ULONG SizeOfImages;
    UNICODE_STRING FullDllname;
    UNICODE_STRING BaseDllName;
    ULONG Flags;
    USHORT LoadCount;
    USHORT TlsIndex;
    union {
        LIST_ENTRY HashLinks;
        struct {
            PVOID SectionPointer;
            ULONG CheckSum;
        };
    };
    union {
        struct {
            ULONG TimeDateStamp;
        };
        struct {
           PVOID LoadedImports;
        };
    };
}LDR_DATA_TABLE_ENTRY, *PLDR_DATA_TABLE_ENTRY;
VOID DriverUnload(IN PDRIVER_OBJECT DriverObject){}
NTSTATUS DriverEntry(IN PDRIVER_OBJECT DriverObject, PUNICODE_STRING
RegistryPath)
{
    ULONG count = 0;
    NTSTATUS Status;
    DriverObject->DriverUnload = DriverUnload;
    PLDR_DATA_TABLE_ENTRY pLdr = NULL;
    PLIST_ENTRY pListEntry = NULL;
    PLDR_DATA_TABLE_ENTRY pModule = NULL;
    PLIST_ENTRY pCurrentListEntry = NULL;
    pLdr = (PLDR_DATA_TABLE_ENTRY)DriverObject->DriverSection;
    pListEntry = pLdr->InLoadOrderLinks.Flink;
    pCurrentListEntry = pListEntry->Flink;
    while (pCurrentListEntry != pListEntry)
        pModule = CONTAINING_RECORD(pCurrentListEntry, LDR_DATA_TABLE_ENTRY,
InLoadOrderLinks);
        if (pModule->BaseDllName.Buffer != 0)
            DbgPrint("基址: %p ---> 偏移: %p ---> 结束地址: %p---> 模块名: %wZ \r\n",
pModule->DllBase, pModule->SizeOfImages - (LONGLONG)pModule->DllBase,
```



本书作者: 王瑞 (LyShark) 作者邮箱: <u>me@lyshark.com</u>

作者博客: https://lyshark.cnblogs.com

团队首页: <u>www.lyshark.com</u>