# EI338 Computer Systems Engineering

# Project 1

October 13, 2019

Zhihui Xie, 517030910356

The environment used in this project is **Deepin 15.11**, the latest version of an open source operating system based on Debian's stable branch. The kernel version is **Linux version 4.15.0**.

# Exercise 1

# Question

Design a kernel module that creates a /proc file named /proc/jiffies that reports the current value of **jiffies** when the /proc/jiffies file is read, such as with the command

```
cat /proc/jiffies
```

Be sure to remove /proc/jiffies when the module is removed.

#### Answer

In this exercise, we design a kernel module named *jiffies*. There are mainly three parts or three functions to realize our purpose.

- proc\_init(), the module entry point
- **proc\_exit()**, the module exit point
- proc\_read(), the function called when the specific /proc file is read

```
proc_init()
```

In **proc\_init()**, we create the new /proc/jiffies entry using the **proc\_create()** function. This function is passed **proc\_ops** which contains a reference to a struct **file\_operations**. It serves as a simple interface to create the /proc file system. This struct initializes the **.owner** and **.read** members. The value of **.read** is the name of the function **proc\_read()**. An message is sent to a kernel log buffer using **printk()** to notice that the module is successfully inserted.

```
static int proc_init(void)
{
      // creates the /proc/jiffies entry
      // the following function call is a wrapper for
      // proc_create_data() passing NULL as the last argument
      proc_create(PROC_NAME, 0, NULL, &proc_ops);
      printk(KERN_INFO "/proc/%s created\n", PROC_NAME);
    return 0;
}
```

Listing 1: **proc\_init()** 

```
proc_exit()
```

In **proc\_exit()**, we need to remove the /proc/jiffies using the function **remove\_proc\_entry()**. An message is sent to a kernel log buffer using **printk()** to notice that the module is successfully removed.

```
static void proc_exit(void) {
    // removes the /proc/jiffies entry
    remove_proc_entry(PROC_NAME, NULL);

    printk( KERN_INFO "/proc/%s removed\n", PROC_NAME);
}
```

Listing 2: proc\_exit()

### proc\_read()

In **proc\_read()**, we are dealing with how to report the current value of **jiffies** when the /proc/jiffies file is read. It is not a big deal to get the value of **jiffies** since it is directly declared in the file linux/jiffies.h>. The real problem is about how can we display it in the command line.

The read handler **proc\_read()** receives 4 parameters:

- File object \*file, per process structure with the opened file details (permission, position, etc.)
- User space buffer \*usr\_buf
- Buffer size count
- Requested position \*pos

To implement the read callback, we need to:

- Check the requested position
- Fill the user buffer with a data (max size  $\leq$  buffer size) from the requested position
- Return the number of bytes we filled

We first check if it is the first time we read the file and the user buffer size is bigger than **BUFFER\_SIZE**. If not, we return 0 to indicate that there is nothing to read. Finally, we build the returned buffer, copy it to the user, update the position and return the number of bytes we wrote. And it is worth mentioning why we use the function **copy\_to\_user()**. We use it to memcpy the data from the user space to the kernel space since it is not accessible for us to directly deal with the buffer in kernel space.

```
static ssize_t proc_read
(struct file *file, char __user *usr_buf, size_t count, loff_t *pos)
{
    char buffer[BUFFER_SIZE];
    int len = 0;

    if(*pos > 0 || count < BUFFER_SIZE) return 0;

    len += sprintf(buffer, "The total number of interrupts is %lu\n", jiffies);

    // copies the contents of buffer to userspace usr_buf
    copy_to_user(usr_buf, buffer, len);

    // updates the position and returns the number of bytes we received
    *pos = len;
    return len;
}</pre>
```

Listing 3: proc\_read()

Each time the /proc/jiffies file is read, the proc read() function is called repeatedly until it returns 0.

## Experiment

We directly present the commands in shell.

```
fffffarmer@fffffarmer-PC:~/Documents/OSC10e/ch2$ sudo insmod jiffies.ko
fffffarmer@fffffarmer-PC:~/Documents/0SC10e/ch2$ dmesg
[46432.341436] /proc/jiffies created
fffffarmer@fffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/jiffies
The total number of interrupts is 4306503137
fffffarmer@fffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/jiffies
The total number of interrupts is 4306503967
fffffarmer@fffffarmer-PC:~/Documents/0SC10e/ch2$ cat /proc/jiffies
The total number of interrupts is 4306504285
fffffarmer@fffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/jiffies
The total number of interrupts is 4306504586
fffffarmer@fffffarmer-PC:~/Documents/OSC10e/ch2$ sudo rmmod jiffies
fffffarmer@fffffarmer-PC:~/Documents/OSC10e/ch2$ dmesg
[46432.341436] /proc/jiffies created
[46456.337225] /proc/jiffies removed
fffffarmer@fffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/jiffies
:at: /proc/jiffies: 没有那个文件或目录
 ffffarmer@fffffarmer-PC:~/Documents/0SC10e/ch2$
```

Figure 1: Experiment Result in Exercise 1

## Exercise 2

# Question

Design a kernel module that creates a proc file named /proc/seconds that reports the number of elapsed seconds since the kernel module was loaded. This will involve using the value of **jiffies** as well as the **HZ** rate. When a user enters the command

```
cat /proc/seconds
```

your kernel module will report the number of seconds that have elapsed since the kernel module was first loaded. Be sure to remove /proc/seconds when the module is removed.

### Answer

All three main functions are realized in a way similar to that in Exercise 1. The main difference lies on the output: the output changes depending on when we call the function. Besides this, everything is the same.

To address this, we declare a global variable named **interrupt\_start** to record the value of **jiffies** when the module is loaded.

And in **proc\_init()**, we assign the current value of **jiffies** to it.

Listing 4: proc init()

The function **proc\_exit()** keeps the same. In **proc\_read()**, we need to simply calculate the elapsed seconds using **HZ** and the difference between current **jiffies** and **interrupt\_start**.

Listing 5: proc\_read()

# Experiment

We directly present the commands in shell. To show that our output is correct, we check the system time as reference.

```
fffffarmerefffffarmer-PC:~/Documents/OSC10e/ch2$ sudo insmod seconds.ko
fffffarmerefffffarmer-PC:-/Documents/OSC10e/ch2$ dmesg
[46739.802068] /proc/seconds created
ffffarmerefffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/seconds; time=$(date "+%Y-%m-%d %H:%M:%S"); echo $time
The number of elapsed seconds since the kernel module was loaded is 8s
2019-10-13 17:41:13
fffffarmerefffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/seconds; time=$(date "+%Y-%m-%d %H:%M:%S"); echo $time
The number of elapsed seconds since the kernel module was loaded is 15s
2019-10-13 17:41:13
fffffarmerefffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/seconds; time=$(date "+%Y-%m-%d %H:%M:%S"); echo $time
The number of elapsed seconds since the kernel module was loaded is 19s
2019-10-13 17:41:18
fffffarmerefffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/seconds; time=$(date "+%Y-%m-%d %H:%M:%S"); echo $time
The number of elapsed seconds since the kernel module was loaded is 24s
2019-10-13 17:41:23
fffffarmerefffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/seconds; time=$(date "+%Y-%m-%d %H:%M:%S"); echo $time
The number of elapsed seconds since the kernel module was loaded is 28s
2019-10-13 17:41:26
fffffarmerefffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/seconds; time=$(date "+%Y-%m-%d %H:%M:%S"); echo $time
The number of elapsed seconds since the kernel module was loaded is 30s
2019-10-13 17:41:28
fffffarmerefffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/seconds; time=$(date "+%Y-%m-%d %H:%M:%S"); echo $time
The number of elapsed seconds since the kernel module was loaded is 34s
fffffarmerefffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/seconds; time=$(date "+%Y-%m-%d %H:%M:%S"); echo $time
The number of elapsed seconds since the kernel module was loaded is 34s
fffffarmereffffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/seconds;
fffffarmerefffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/seconds
fffffarmereffffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/seconds
fffffarmereffffffarmer-PC:~/Documents/OSC10e/ch2$ cat /proc/seconds
fff
```

Figure 2: Experiment Result in Exercise 2