

OpenShift Container Platform 3.11 CRI-O Runtime

cri-o Runtime Guide

Last Updated: 2018-12-21

OpenShift Container Platform 3.11 CRI-O Runtime

cri-o Runtime Guide

Legal Notice

Copyright © 2018 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution—Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java ® is a registered trademark of Oracle and/or its affiliates.

XFS ® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat Software Collections is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack ® Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

Learn how to use cri-o

Table of Contents

CHAPTER 1. USING THE CRI-O CONTAINER ENGINE	3
1.1. UNDERSTANDING CRI-O	3
1.2. GETTING CRI-O	3
1.2.1. Installing CRI-O with a new OpenShift Container Platform cluster	4
1.2.2. Adding CRI-O nodes to an OpenShift Container Platform cluster	5
1.3. CONFIGURING CRI-O	6
1.3.1. Configuring CRI-O storage	7
1.3.2. Configuring CRI-O networking	8
1.4. TROUBLESHOOTING CRI-O	8
1.4.1. Checking CRI-O's general health	9
1.4.2. Inspecting CRI-O logs	10
1.4.2.1. Checking crio and origin-node logs	10
1.4.2.2. Turning on debugging for CRI-O	11
1.4.3. Troubleshooting CRI-O pods, and containers	12
1.4.3.1. Listing images, pods, and containers	13
1.4.3.2. Investigating images, pods, and containers	15
Additional resources	17

CHAPTER 1. USING THE CRI-O CONTAINER ENGINE

CRI-O is an open source, community-driven container engine. Its primary goal is to replace the Docker service as the container engine for Kubernetes implementations, such as OpenShift Container Platform.

If you want to start using CRI-O, this guide describes how to install CRI-O during OpenShift Container Platform installation as well as how to add a CRI-O node to an existing OpenShift Container Platform cluster. The guide also provides information on how to configure and troubleshoot your CRI-O engine.

1.1. UNDERSTANDING CRI-O

The CRI-O container engine provides a stable, more secure, and performant platform for running Open Container Initiative (OCI) compatible runtimes. You can use the CRI-O container engine to launch containers and pods by engaging OCI-compliant runtimes like runc, the default OCI runtime, or Kata Containers. CRI-O's purpose is to be the container engine that implements the Kubernetes Container Runtime Interface (CRI) for OpenShift Container Platform and Kubernetes, replacing the Docker service.

CRI-O offers a streamlined container engine, while other container features are implemented as a separate set of innovative, independent commands. This approach allows container management features to develop at their own pace, without impeding CRI-O's primary goal of being a container engine for Kubernetes-based installations.

CRI-O's stability comes from the facts that it is developed, tested, and released in tandem with Kubernetes major and minor releases and that it follows OCI standards. For example, CRI-O 1.11 aligns with Kubernetes 1.11. The scope of CRI-O is tied to the Container Runtime Interface (CRI). CRI extracted and standardized exactly what a Kubernetes service (kubelet) needed from its container engine. The CRI team did this to help stabilize Kubernetes container engine requirements as multiple container engines began to be developed.

There is little need for direct command-line contact with CRI-O. However, to provide full access to CRI-O for testing and monitoring, and to provide features you expect with Docker that CRI-O does not offer, a set of container-related command-line tools are available. These tools replace and extend what is available with the **docker** command and service. Tools include:

- crict1 For troubleshooting and working directly with CRI-O container engines
- runc For running container images
- **podman** For managing pods and container images (run, stop, start, ps, attach, exec, etc.) outside of the container engine
- buildah For building, pushing and signing container images
- skopeo For copying, inspecting, deleting, and signing images

Some Docker features are included in other tools instead of in CRI-O. For example, **podman** offers exact command-line compatibility with many **docker** command features and extends those features to managing pods as well. No container engine is needed to run containers or pods with **podman**.

Features for building, pushing, and signing container images, which are also not required in a container engine, are available in the **buildah** command. For more information about these command alternatives to **docker**, see Finding, Running and Building Containers without Docker.

1.2. GETTING CRI-O

CRI-O is not supported as a stand-alone container engine. You must use CRI-O as a container engine for a Kubernetes installation, such as OpenShift Container Platform. To run containers without Kubernetes or OpenShift Container Platform, use podman.

To set up a CRI-O container engine to use with an OpenShift Container Platform cluster, you can:

- Install CRI-O along with a new OpenShift Container Platform cluster or
- Add a node to an existing cluster and identify CRI-O as the container engine for that node. Both CRI-O and Docker nodes can exist on the same cluster.

The following section describes how to install CRI-O with a new OpenShift Container Platform cluster

1.2.1. Installing CRI-O with a new OpenShift Container Platform cluster

You can choose CRI-O as the container engine for your OpenShift Container Platform nodes on a pernode basis at install time. Here are a few things you should know about enabling the CRI-O container engine when you install OpenShift Container Platform:

- Previously, using CRI-O on your nodes required that the Docker container engine be available
 as well. As of OpenShift Container Platform 3.10 and later, the Docker container engine is no
 longer required in all cases. Now you can now have CRI-O-only nodes in your OpenShift
 Container Platform cluster. However, nodes that do build and push operations still need to have
 the Docker container engine installed along with CRI-O.
- Enabling CRI-O using a CRI-O container is no longer supported. An rpm-based installation of CRI-O is required.

The following procedure assumes you are installing OpenShift Container Platform using Ansible inventory files, such as those described in Configuring Your Inventory File.



NOTE

Do not set /var/lib/docker as a separate mount point for an OpenShift Container Platform node using CRI-O as its container engine. When deploying a CRI-O node, the installer tries to make /var/lib/docker a symbolic link to /var/lib/containers. That action will fail because it won't be able to remove the existing /var/lib/docker to create the symbolic link.

- 1. With the OpenShift Container Platform Ansible playbooks installed, edit the appropriate inventory file to enable CRI-O.
- 2. Locate CRI-O setting in your selected inventory file. To have the CRI-O container engine installed on your nodes during OpenShift Container Platform installation, locate the [OSEv3:vars] section of an Ansible inventory file. A section of CRI-O settings might include the following:

```
[OSEv3:vars]
...
# Install and run cri-o.
#openshift_use_crio=False
#openshift_use_crio_only=False
# The following two variables are used when openshift_use_crio is
True
# and cleans up after builds that pass through docker. When
openshift_use_crio is True
```

```
# these variables are set to the defaults shown. You may override
them here.
# NOTE: You will still need to tag crio nodes with your given
label(s)!
# Enable docker garbage collection when using cri-o
#openshift_crio_enable_docker_gc=True
# Node Selectors to run the garbage collection
#openshift_crio_docker_gc_node_selector={'runtime': 'cri-o'}
```

3. Enable CRI-O settings. You can decide to either enable CRI-O alone or CRI-O alongside Docker. The following settings allow CRI-O and Docker as your node container engines and enables Docker garbage collection on nodes with overlay2 storage:



NOTE

To be able to build containers on CRI-O nodes, you must have the Docker container engine installed. If you want to have CRI-O-only nodes, you can do that and simply designate other nodes to do container builds.

```
[OSEv3:vars]
...
openshift_use_crio=True
openshift_use_crio_only=False
openshift_crio_enable_docker_gc=True
```

4. Set the openshift_node_group_name for each node to a configmap that configures the kubelet for the CRI-O runtime. There's a corresponding CRI-O configmap for all the default node groups. Defining Node Groups and Host Mappings covers node groups and mappings in detail.

```
[nodes]
ocp-crio01 openshift_node_group_name='node-config-all-in-one-crio'
ocp-docker01 openshift_node_group_name='node-config-all-in-one'
```

The resulting OpenShift Container Platform configuration will be running the CRI-O container engine on the nodes of your OpenShift Container Platform installation. Use the **oc** command to check the status of the nodes and identify the nodes running CRI-O:

```
$ oc get nodes -o wide

NAME STATUS ROLES AGE ... CONTAINER-RUNTIME

ocp-crio01 Ready compute, infra, master 16d ... cri-o://1.11.5

ocp-docker01 Ready compute, infra, master 16d ... docker://1.13.1
```

1.2.2. Adding CRI-O nodes to an OpenShift Container Platform cluster

OpenShift Container Platform does not support the direct upgrading of nodes from using the docker container engine to using CRI-O. To upgrade an existing OpenShift Container Platform cluster to use CRI-O, do the following:

- Scale up a node that is configured to use the CRI-O container engine
- Check that the CRI-O node performs as expected
- Add more CRI-O nodes as needed

Scale down Docker nodes as the cluster stabilizes

To see what actions are taken when you create a node with the CRI-O container engine, refer to Upgrading to CRI-O with Ansible.



NOTE

If you are upgrading your entire OpenShift Container Platform cluster to OpenShift Container Platform 3.10 or later, and a containerized version of CRI-O is running on a node, the CRI-O container will be removed from that node and the CRI-O rpm will be installed. The CRI-O service will be run as a systemd service from then on. See BZ#1618425 for details.

1.3. CONFIGURING CRI-O

Because CRI-O is intended to be deployed, upgraded and managed by OpenShift Container Platform, you should only change CRI-O configuration files through OpenShift Container Platform or for the purposes of testing or troubleshooting CRI-O. On a running OpenShift Container Platform node, most CRI-O configuration settings are kept in the /etc/crio/crio.conf file.

Settings in a **crio.conf** file define how storage, the listening socket, runtime features, and networking are configured for CRI-O. Here's an example of the default **crio.conf** file (look in the file itself to see comments describing these settings):

```
[crio]
root = "/var/lib/containers/storage"
runroot = "/var/run/containers/storage"
storage_driver = "overlay"
storage_option = [
        "overlay.override_kernel_check=1",
   1
[crio.api]
listen = "/var/run/crio/crio.sock"
stream_address = ""
stream_port = "10010"
file_locking = true
[crio.runtime]
runtime = "/usr/bin/runc"
runtime_untrusted_workload = ""
default_workload_trust = "trusted"
no_pivot = false
conmon = "/usr/libexec/crio/conmon"
conmon_env = [
"PATH=/usr/local/sbin:/usr/local/bin:/usr/sbin:/usr/bin:/sbin:/bin",
selinux = true
seccomp_profile = "/etc/crio/seccomp.json"
apparmor_profile = "crio-default"
cgroup_manager = "systemd"
hooks_dir_path = "/usr/share/containers/oci/hooks.d"
default_mounts = [
        "/usr/share/rhel/secrets:/run/secrets",
```

```
pids_limit = 1024
enable_shared_pid_namespace = false
log_size_max = 52428800

[crio.image]
default_transport = "docker://"
pause_image = "docker.io/openshift/origin-pod:v3.11"
pause_command = "/usr/bin/pod"
signature_policy = ""
image_volumes = "mkdir"
insecure_registries = [
""
]
registries = [
"docker.io"
]
[crio.network]
network_dir = "/etc/cni/net.d/"
plugin_dir = "/opt/cni/bin"
```

The following sections describe how different CRI-O configurations might be used in the **crio.conf** file.

1.3.1. Configuring CRI-O storage

OverlayFS2 is the recommended (and default) storage driver for OpenShift Container Platform, whether you use CRI-O or Docker as your container engine. See Choosing a graph driver for details on available storage devices.



NOTE

Although devicemapper is a supported storage facility for CRI-O, the CRI-O garbage collection feature does not yet work with devicemapper and so is not recommended for production use. Also, see BZ1625394 and BZ1623944 for other devicemapper issues that apply to how both CRI-O and **podman** use container storage.

Things you should know about CRI-O storage include the facts that CRI-O storage:

- Holds images by storing the root filesystem of each container, along with any layers that go with it.
- Incorporates the same storage layer that is used with the Docker service.
- Uses **container-storage-setup** to manage the container storage area.
- Uses configuration information from the /etc/containers/storage.conf and /etc/crio/crio.conf files.
- Stores data in /var/lib/containers by default. That directory is used by both CRI-O and tools for running containers (such as podman).



NOTE

Although they use the same storage directory, the container engine and the container tools manage their containers separately.

Can store both Docker version 1 and version 2 schemas.

For information on using **container-storage-setup** to configure storage for CRI-O, see Using container-storage-setup.

1.3.2. Configuring CRI-O networking

CRI-O supports networking facilities that are compatible with the Container Network Interface (CNI). Supported networking features include loopback, flannel, and openshift-sdn, which are implemented as network plugins.

By default, OpenShift Container Platform uses openshift-sdn networking. The following settings in the crio.conf file define where CNI network configuration files are stored (/etc/cni/net.d/) and where CNI plugin binaries are stored (/opt/cni/bin/)

```
[crio.network]
network_dir = "/etc/cni/net.d/"
plugin_dir = "/opt/cni/bin/"
```

To understand the networking features needed by CRI-O in OpenShift Container Platform, refer to both Kubernetes and OpenShift Container Platform networking requirements.

1.4. TROUBLESHOOTING CRI-O

To check the health of your CRI-O container engine and troubleshoot problems, you can use the **crictl** command, along with some well-known Linux and OpenShift Container Platform commands. As with any OpenShift Container Platform container engine, you can use commands such as **oc** and **kubect1** to investigate the pods in CRI-O as well.

For example, to list pods, run the following:

```
$ sudo oc get pods -o wide
NAME
                         READY STATUS RESTARTS AGE IP
                                                                    NODE
NOMINATED NODE
docker-registry-1-fb2g8 1/1
                                                5d 10.128.0.4
                                                                    hostA
                               Running 1
<none>
registry-console-1-vktl6 1/1
                               Running 0
                                                5d 10.128.0.6
                                                                    hostA
<none>
                         1/1
                               Running 0
                                                5d 192.168.122.188 hostA
router-1-hjfm7
<none>
```

To ensure that a pod is running in CRI-O, use the **describe** option and **grep** for **cri-o**:

```
$ sudo oc describe pods registry-console-1-vktl6 | grep cri-o
Container ID: cri-
o://9a9209dc0608ce80f62bb4d7f7df61bcf8dd2abd77ef53075dee0542548238b7
```

To query and debug a CRI-O container runtime, run the **crictl** command to communicate directly with CRI-O. The CRI-O instance that **crictl** uses is identified in the **crictl.yaml** file.

```
# cat /etc/crictl.yaml
runtime-endpoint: /var/run/crio/crio.sock
```

By default, the **crictl.yaml** file causes crictl to point to the CRI-O socket on the local system. To see options available with **crictl**, run **crictl** with no arguments. To get help with a particular option, add **--help**. For example:

1.4.1. Checking CRI-O's general health

Log into a node in your OpenShift Container Platform cluster that is running CRI-O and run the following commands to check the general health of the CRI-O container engine:

Check that the CRI-O related packages are installed. That includes the crio (CRI-O daemon and config files) and cri-tools (crictl command) packages:

```
# rpm -qa | grep ^cri-
cri-o-1.11.6-1.rhaos3.11.git2d0f8c7.el7.x86_64
cri-tools-1.11.1-1.rhaos3.11.gitedabfb5.el7_5.x86_64
```

Check that the crio service is running:

```
Daemon.
Oct 16 18:30:55 hostA crio[889]: time="2018-10-16 18:30:55.128074704Z" level=error
```

1.4.2. Inspecting CRI-O logs

Because the CRI-O container engine is implemented as a systemd service, you can use the standard **journalctl** command to inspect log messages for CRI-O.

1.4.2.1. Checking crio and origin-node logs

To check the journal for information from the crio service, use the -u option. In this example, you can see that the service is running, but a pod failed to start:

```
$ sudo journalctl -u crio
-- Logs begin at Tue 2018-10-16 15:01:31 UTC, end at Tue 2018-10-16
19:10:52 UTC. --
Oct 16 15:05:42 hostA systemd[1]: Starting Open Container Initiative
Oct 16 15:05:42 hostA systemd[1]: Started Open Container Initiative
Oct 16 15:06:35 hostA systemd[1]: Stopping Open Container Initiative
Daemon...
Oct 16 15:06:35 hostA crio[4863]: time="2018-10-16 15:06:35.018523314Z"
level=error msg="Failed to start streaming server: http: Server closed"
Oct 16 15:06:35 hostA systemd[1]: Starting Open Container Initiative
Daemon...
Oct 16 15:06:35 hostA systemd[1]: Started Open Container Initiative
Oct 16 15:10:27 hostA crio[6874]: time="2018-10-16 15:10:26.900411457Z"
level=error msq="Failed to start streaming server: http: Server closed"
Oct 16 15:10:26 hostA systemd[1]: Stopping Open Container Initiative
Daemon...
Oct 16 15:10:27 hostA systemd[1]: Stopped Open Container Initiative
Daemon.
-- Reboot --
Oct 16 15:15:48 hostA systemd[1]: Starting Open Container Initiative
Daemon...
Oct 16 15:15:49 hostA systemd[1]: Started Open Container Initiative
Daemon.
Oct 16 18:30:55 hostA crio[889]: time="2018-10-16 18:30:55.128074704Z"
level=error msg="Error adding network: CNI request failed with status 400:
'pods "
```

You can also check the origin-node service for CRI-O related messages. For example:

```
version: 1.11.6, apiVersion: v1alpha1
Oct 16 15:27:27 hostA origin-node[11107]: I1016 15:27:27.507030
                                                                  11107
  factory.go:157] Registering CRI-O factory
Oct 16 19:27:56 hostA origin-node[8326]: I1016 19:27:56.224770
                                                                  8326
   kuberuntime_manager.go:186] Container runtime cri-o initialized,
   version: 1.11.6, apiVersion: v1alpha1
Oct 16 19:27:56 hostA origin-node[8326]: I1016 19:27:56.282138
                                                                  8326
   factory.go:157] Registering CRI-O factory
Oct 16 19:27:57 hostA origin-node[8326]: I1016 19:27:57.783304
                                                                  8326
   status_manager.go:375] Status Manager: adding pod:
   "db1f45e3-d157-11e8-8645-42010a8e0002", with status: ('\x01', {Running
   docker.io/openshift/origin-node:v3.11 docker.io/openshift/origin-
node@sha256:6f9b0fbdd...
     cri-o://c94cc6
     2c27d021d61e8b7c1a82703d51db5847e74f5e57c667432f90c07013e4}]
Burstable}) to
     podStatusChannel
```

If you wanted to further investigate what was happening with one of the pods listed, (such as the last one shown as cri-o//c94cc6), you can use the **crictl logs** command:

```
$ sudo crictl logs c94cc6
/etc/openvswitch/conf.db does not exist ... (warning).
Creating empty database /etc/openvswitch/conf.db [ OK ]
Starting ovsdb-server [ OK ]
Configuring Open vSwitch system IDs [ OK ]
Inserting openvswitch module [ OK ]
Starting ovs-vswitchd [ OK ]
Enabling remote OVSDB managers [ OK ]
```

1.4.2.2. Turning on debugging for CRI-O

To get more details from the logging facility for CRI-O, you can temporarily set the loglevel to debug as follows:

1. Edit the /usr/lib/systemd/system/crio.service file and add --loglevel=debug to the ExecStart= line so it appears as follows:

2. Reload the configuration file and restart the service as follows:

```
# systemctl daemon-reload
# systemctl restart crio
```

3. Run the **journalct1** command again. You should begin to see lots of debug messages, representing the processing going on with your CRI-O service:

```
# journalctl -u crio
Oct 18 08:41:31 mynode01-crio crio[21998]:
   time="2018-10-18 08:41:31.839702058-04:00" level=debug
```

```
msg="ListContainersRequest
&ListContainersRequest{Filter:&ContainerFilter{Id:,State:nil,PodSand
boxId:
   ,LabelSelector:map[string]string{},},}"
Oct 18 08:41:31 mynode01-crio crio[21998]: time="2018-10-18
   08:41:31.839928476-04:00" level=debug msg="no filters were
applied,
   returning full container list"
Oct 18 08:41:31 mynode01-crio crio[21998]: time="2018-10-18"
08:41:31.841814536-04:00"
   level=debug msg="ListContainersResponse:
&ListContainersResponse{Containers:
[&Container{Id:e1934cc46696ff821bc35154f281764e80ac1122563ffd95aa92d
01477225603,
PodSandboxId: d904d45e6e46110a044758f20047805d8832b6859e10dc903c104cf
757894e8d,
   Metadata:&ContainerMetadata{Name:c,Attempt:0,},Image:&ImageSpec{
Image:e72de76ca8d5410497ae3171b6b059e7c7d11e4d1f3225df8d05812f29e205
   ImageRef:docker.io/openshift/origin-template-service-
broker@sha256:fd539 ...
```

4. Remove the **--loglevel=debug** option when you are done investigating, to reduce the amount of messages generated. Then rerun the two **systemctl** commands:

```
# systemctl daemon-reload
# systemctl restart crio
```

1.4.3. Troubleshooting CRI-O pods, and containers

With the **crictl** command, you interface directly with the CRI-O container engine to check on and manipulate the containers, images, and pods associated with that container engine. The **runc** container runtime is another way to interact with CRI-O. If you want to run containers outside of the CRI-O container engine, for example to run support-tools on a node, you can use the **podman** command.

See Crictl vs. Podman for descriptions of those two commands and how they differ.

To begin, you can check the general status of the CRI-O service using the **crictl info** and **crictl version** commands:

1.4.3.1. Listing images, pods, and containers

The **crict1** command provides options for investigating the components in your CRI-O environment. Here are examples of some of the uses of **crict1** for listing information about images, pods, and containers.

To see the images that have been pulled to the local CRI-O node, run the **crictl images** command:

\$ sudo crictl images		
IMAGE	TAG	IMAGE ID
SIZE		
docker.io/openshift/oauth-proxy	v1.1.0	90c45954eb03e
242MB		
docker.io/openshift/origin-haproxy-router	v3.11	13f40ad4d2e21
410MB		
docker.io/openshift/origin-node	v3.11	93d2aeddcd6db
1.17GB	v3.11	89ceff8fb1907
docker.io/openshift/origin-pod 263MB	V3.11	9906119101907
docker.io/openshift/prometheus-alertmanager	ν0 15 2	68bbd00063784
242MB	VO.13.2	00000000704
docker.io/openshift/prometheus-node-exporter	v0.16.0	f9f775bf6d0ef
225MB		
quay.io/coreos/cluster-monitoring-operator	v0.1.1	4488a207a5bca
531MB		
quay.io/coreos/configmap-reload	v0.0.1	3129a2ca29d75
4.79MB		
quay.io/coreos/kube-rbac-proxy	v0.3.1	992ac1a5e7c79
40.4MB		
quay.io/coreos/kube-state-metrics	v1.3.1	a9c8f313b7aad
22.2MB		

To see the pods that are currently active in the CRI-O environment, run **crictl pods**:

```
$ sudo crictl pods

POD ID CREATED STATE NAME NAMESPACE
ATTEMPT

09997515d7729 5 hours ago Ready kube-state-metrics-... openshift-
monitoring 0

958b0789e0552 5 hours ago Ready node-exporter-rkbzp openshift-
monitoring 0
```

```
4ec0498dacec8 5 hours ago Readyalertmanager-main-0openshift-monitoring 00cluster-monitoring-...openshift-2873b697df1d2 5 hours ago Readycluster-monitoring-...openshift-b9e221481fb7e 5 hours ago Readyrouter-1-968t4default0cluster-monitoring-...openshift-sdn0openshift-sdn0ovs-kdvzsopenshift-sdn0ovs-kdvzsopenshift-sdn0openshift-node49dbc57455c8f 5 hours ago Readysync-hgfvbopenshift-node
```

To see containers that are currently running, run the **crictl ps** command:

```
$ sudo crictl ps
CONTAINER ID IMAGE
                                                  CREATED
                                                              STATE
NAME
                    ATTEMPT
376eb13e3cb37 quay.io/coreos/kube-state-metrics... 4 hours ago Running
kube-state-metrics
                   0
72d61c3d393b5 992ac1a5e7c79d627321dc7877f741a00... 4 hours ago Running
kube-rbac-proxy-self 0
5fa8c93484055 992ac1a5e7c79d627321dc7877f741a00... 4 hours ago Running
kube-rbac-proxy-main 0
a2d35508fc0ee quay.io/coreos/kube-rbac-proxy... 4 hours ago Running
kube-rbac-proxy
9adda43f3595f docker.io/openshift/prometheus-no... 4 hours ago Running
node-exporter
7f4ce5b25cfdb docker.io/openshift/oauth-proxy... 4 hours ago Running
alertmanager-proxy
85418badbf6ae quay.io/coreos/configmap-reload... 4 hours ago Running
config-reloader
756f20138381c docker.io/openshift/prometheus-al... 4 hours ago Running
alertmanager
5e6d8ff4852ba quay.io/coreos/cluster-monitoring... 4 hours ago Running
cluster-monitoring- 0
1c96cfcfa10a7 docker.io/openshift/origin-haprox... 5 hours ago Running
route
8f90bb4cded60 docker.io/openshift/origin-node... 5 hours ago Running sdn
59e5fb8514262 docker.io/openshift/origin-node... 5 hours ago Running
openvswitch
73323a2c26abe docker.io/openshift/origin-node... 5 hours ago Running
sync
```

To see both running containers as well as containers that are stopped or exited, run **crictl ps -a**:

```
$ sudo crictl ps -a
```

If your CRI-O service is stopped or malfunctioning, you can list the containers that were run in CRI-O using the **runc** command. This example searches for the existence of a container with CRI-O running and not running. It then shows that you can investigate that container with **runc**, even when CRI-O is stopped:

```
$ crictl ps | grep d36a99a9a40ec
```

```
d36a99a9a40ec
062cd20609d3895658e54e5f367b9d70f42db4f86ca14bae7309512c7e0777fd
    11 hours ago
                        CONTAINER_RUNNING
                                            sync
$ sudo systemctl stop crio
$ sudo crictl ps | grep d36a99a9a40ec
2018/10/25 11:22:16 grpc: addrConn.resetTransport failed to create client
transport:
   connection error: desc = "transport: dial unix /var/run/crio/crio.sock:
connect:
   no such file or directory"; Reconnecting to {/var/run/crio/crio.sock
<nil>}
   FATA[0000] listing containers failed: rpc error: code = Unavailable
desc = grpc:
   the connection is unavailable
$ sudo runc list | grep d36a99a9a40ec
d36a99a9a40ecc4c830f10ed2d5bb3ce1c6deadcb1a4879ff342e315051a71ed
                                                                   19477
running
  /run/containers/storage/overlay-
containers/d36a99a9a40ecc4c830f10ed2d5bb3ce1c6deadcb1a4879ff342e315051a71e
d/userdata
  2018-10-25T04:44:29.47950187Z
                                   root
$ ls /run/containers/storage/overlay-containers/d36*/userdata/
attach config.json ctl pidfile run
$ less /run/containers/storage/overlay-
containers/d36*/userdata/config.json
 "ociVersion": "1.0.0",
 "process": {
  "user": {
   "uid": 0,
   "qid": 0
  "args": [
   "/bin/bash",
   "-C",
   "#!/bin/bash\nset -euo pipefail\n\n# set by the node
                        image\nunset KUBECONFIG\n\ntrap 'kill $(jobs -p);
                        exit 0' TERM\n\n# track the current state of the
$ sudo systemctl start crio
```

As you can see, even with the CRI-O service off, **runc** shows the existence of the container and its location in the file system, in case you want to look into it further.

1.4.3.2. Investigating images, pods, and containers

To find out details about what is happening inside of images, pods or containers for your CRI-O environment, there are several **crictl** options you can use.

With a container ID in hand (from the output of **crictl ps**), you can exec a command inside that container. For example, to see the name and release of the operating system inside of a container, run:

```
$ crictl exec 756f20138381c cat /etc/redhat-release
CentOS Linux release 7.5.1804 (Core)
```

To see a list of processes running inside of a container, run:

```
$ crictl exec -t e47b3a837aa30 ps -ef
UID PID PPID C STIME TTY TIME CMD
1000130+ 1 0 0 0ct17 ? 00:38:14 /usr/bin/origin-web-
console --au
1000130+ 15894 0 0 15:38 pts/0 00:00:00 ps -ef
1000130+ 17518 1 0 0ct23 ? 00:00:00 [curl] <defunct>
```

As an alternative, you can "exec" into a container using the **runc** command:

If there is no **ps** command inside the container, **runc** has the **ps** option, which has the same effect of showing the processes running in the container:

```
$ sudo runc ps
e47b3a837aa3023c748c4c31a090266f014afba641a8ab9cfca31b065b4f2ddd
```

Note that **runc** requires the full container ID, while **crict1** only needs a few unique characters from the beginning.

With a pod sandbox ID in hand (output from **crictl pods**), run **crictl inspectp** to display information about that pod sandbox:

To see status information about an image that is available to CRI-O on the local system, run **crict1 inspecti**:

```
$ sudo crictl inspecti ff5dd2137a4ff
```

```
{
   "status": {
      "id":
   "ff5dd2137a4ffd5ccb9837d5a0aa0a5d10729f9c186df02e54e58748a32d08b0",
      "repoTags": [
            "quay.io/coreos/etcd:v3.2.22"
            ],
            "repoDigests": [

"quay.io/coreos/etcd@sha256:43fbc8a457aa0cb887da63d74a48659e13947cb74b96a5
3ba8f47abb6172a948"
            ],
            "size": "37547599",
            "username": ""
            }
}
```

Additional resources

- CRI-O OCI-based implementation of Kubernetes Container Runtime Interface
- CRI-O Lightweight Container Runtime for Kubernetes
- CRI-O Command Line Interface: crictl
- Finding, Running, and Building Containers without Docker
- Container Commandos Coloring Book
- CRI-O now running production workloads in OpenShift Online
- CRI-O How Standards Power a Container Runtime
- A Practical Introduction to Container Terminology