
## Revision

CS3026 Operating Systems
Lecture 23

## Three Main Areas



# **Process Management**


#### **Process**

- Definitions:
  - A process is a program in execution
  - The entity that can be assigned to and executed on a processor
- Processes are a fundamental concept of an operating system
  - As a unit of execution, it enables the concurrent execution of multiple programs on a system
    - CPU switches between processes
- Process is defined as the unit of resource ownership and protection

#### **Process**

- Process is defined as the unit of resource allocation and protection
  - Protected access to processors, other processes, files, I/O
- Processes embody two characteristic concepts
  - Resource ownership:
    - Processes own and address space (Virtual memory space to hold the process image)
    - Processes own a set of resources (I/O devices, I/O channels, files, main memory)
    - Operating system protects process to prevent unwanted interference between processes
  - Scheduling / execution
    - Process has execution state (running, ready etc.) and dispatching priority
    - Execution follows an execution path (trace) through one or more programs
    - This execution may be interleaved with that of other processes

#### **Process Execution**




- 1. Process blocked for I/O
- 2. Dispatcher schedules another process
- 3. Dispatcher interrupts process because its time slice expired
- 4. Input becomes available, blocked process made ready
- We can distinguish three basic process states during execution
  - Running: actually using the CPU
  - Ready: being runnable, temporarily stopped (time-out) to let another process execute
  - Blocked/Waiting: unable to run until some external event happens, such as I/O completion

#### **State Transitions**

- Transition Running Blocked:
  - Operating systems discovers that process cannot continue right now
    - Unix: process is automatically blocked by dispatcher
    - Other systems: processes may execute a system call such as "pause" to set themselves into blocked state
- Transition Running Ready Running:
  - Performed by dispatcher, without process knowing
  - When the time slice of a process expires, it is set into Ready state
  - Process is transferred back into Running state according to some scheduling policy (performance vs fairness)
- Transition Blocked Ready
  - Process is transferred into Ready state, when external event occurs


# **Process Management**



#### Implementation:

- Using one "Ready" and one "Blocked" queue
- Weakness:
  - When a particular event occurs, ALL processes waiting for this event have to be transferred from the "Blocked" queue to the "Ready" queue
  - Operating system has to look through all the entries in the Blocked queue to select the right processes for transfer

## **Context Switch**



# Multithreading

- Processes have at least one thread of control
  - Is the CPU context, when process is dispatched for execution
- Multithreading is the ability of an operating system to support multiple threads of execution within a single process
- Multiple threads run in the same address space, share the same memory areas
  - The creation of a thread only creates a new thread control structure, not a separate process image

## **Threads**

- The unit of dispatching in modern operating systems is usually a thread
  - Represent a single thread of execution within a process
  - Operating system can manage multiple threads of execution within a process
  - The thread is provided with its own register context and stack space
  - It is placed in the ready queue
  - Threads are also called "lightweight processes"
- The unit of resource ownership is the process
  - When a new process is created, at least one thread within the process is created as well
  - Threads share resources owned by a process (code, data, file handles)

## **Threads**

- All threads share the same address space
  - Share global variables
- All threads share the same open files, child processes, signals, etc.
- There is no protection between threads
  - As they share the same address space they may overwrite each others data
- As a process is owned by one user, all threads are owned by one user

#### Threads vs Processes


- Less time to create a new thread (10-times faster than process creation in Unix)
- Less time to terminate a thread
- Less time to switch between threads
- Threads enhance efficiency in communication between different communicating programs, no need to call kernel routines, as all threads live in same process context

#### Threads vs Processes

- Advantages of Threads
  - Much faster to create a thread than a process
    - Spawning a new thread only involves allocating a new stack and a new thread control block
  - Much faster to switch between threads than to switch between processes
  - Threads share data easily
- Disadvantages
  - Processes are more flexible
    - They don't have to run on the same processor
  - No protection between threads
    - Share same memory, may interfere with each other
  - If threads are implemented as user threads instead of kernel threads
    - If one thread blocks, all threads in process block

# Thread Implementation

- Two main categories of thread implementation
  - User-level Threads (ULTs)
  - Kernel-level Threads (KLTs)
- Characterised by the extent of the kernel being involved in their management



# Scheduling

#### **CPU Scheduler**

- Scheduling can be preemptive or non-preemptive
- Non-preemptive:
  - once a process is scheduled, it continues to execute on the CPU, until
    - it is finished (terminates)
    - It releases the CPU voluntarily (cooperative scheduling behaviour, Ready queue)
    - It blocks due to I/O interrupts or because it waits for another process
    - No scheduling decision is made during clock interrupts, process is resumed after this interruption (unless a process with higher priority becomes ready)

#### Preemptive:

- A scheduled process executes, until its time slice is used up
- Clock interrupt returns control of CPU back to scheduler at end of time slice
  - Current process is suspended and placed in the Ready queue
  - New process is selected from Ready queue and executed on CPU
- Used by most operating systems

# Scheduling Performance Criteria

- CPU utilisation
  - Keep the CPU as busy as possible
- Throughput
  - Number of processes that complete their execution per time unit
- Response time
  - The time it takes from when a request was submitted until the first response is produced by the operating system (latency)
- Turnaround time
  - Total amount of time to execute one process to its completion
- Waiting time
  - Total amount of time a process has been waiting in the Ready queue

# **Optimisation Criteria**

- Maximise CPU utilisation
- Maximise throughput
- Minimise turnaround time
- Minimise waiting time
- Minimise response time

## First Come First Serve Scheduling (FCFS)

#### • Example:

- Three processes arrive at the same time (t = 0)
- They have different CPU burst times
- We assume the arrival order P1, P2, P3

<b>Process</b>	<b>Burst Time</b>			
P1	24			
P2	3			
Р3	3			

P <sub>1</sub>		Р	2		P <sub>3</sub>
0	2	4	2	7	3

- Waiting times
  - P1 has 0 time units waiting time
  - P2 has 24 time units waiting time
  - P3 has 27 time units waiting time
  - Average waiting time: (0 + 24 + 27)/3 = 17

#### First Come First Serve Scheduling (FCFS)

- Favours long processes
- CPU-intensive processes (long burst times)
- Disadvantages
  - Leads to poor utilisation of CPU and I/O devices
  - Average waiting time is highly variable
    - Short jobs may wait behind large ones

# Round Robin (RR, Time Slicing)

- Is a preemptive scheduling policy
- Time quantum
  - Each process gets a fixed unit of CPU (usually 10-100 ms)
  - After time quantum has elapsed, the process is preempted and added to the end of the Ready queue
    - Processes scheduled in a cyclical fashion (always same sequence of processes) – round robin
- Fairness: Each process gets an equal time quantum
  - If the time quantum is q time units and if there are n processes in the Ready queue, each process get 1/n of the CPU time, in chunks with a size of at most q time units
  - No process waits more than (n-1)q time units

# **Lottery Scheduling**

- Basic idea
  - Give processes "lottery tickets" for various resources, such as CPU time
  - For each scheduling decision, a lottery ticket is chosen at random and the process holding that ticket gets resource
  - E.g.: CPU scheduling
    - Scheduler holds lottery 50 times per second
    - Each winner receives 20msec of CPU time

# Scheduling in Real-Time Systems

- In real-time scheduling, time is essential
  - A process has to meet deadlines reliably
- A set of processes has to be scheduled so that all of them meet deadlines reliably
  - How to order / prioritise them?
  - How does the requirement of meeting deadlines and allow a system to reliably react to events impact on CPU utilisation?

#### Hard and Soft Real-Time

- Hard Real-Time
  - There are absolute deadlines that always have to be met
  - If a deadline is missed, there may be unacceptable danger, damage or a fatal error in the system controlled by real-time processing

#### Soft Real-Time

- Each processing of an event has an associated deadline that is desirable, but not mandatory
- System continues to operate, even if a deadline has not been met
  - Missing an occasional deadline for scheduling a process (e.g. missing sensor input) is tolerable, system is able to recover from that

# Effectiveness of a Periodic Scheduling Algorithm

- A periodic scheduling algorithm is effective when it guarantees that all hard deadlines are met
  - In order to meet all deadlines, schedulability must be guaranteed

# **Example Schedulability**

- Three video streams handled by three processes
  - Stream 1 handled by process A:
    - Frame rate: Every 30 msec one frame
    - CPU time needed to decode stream: 10 msec per frame
  - Stream 2 handled by process B:
    - Frame rate: Every 40 msec one frame
    - CPU time: 15 msec
  - Stream 3 handled by process C:
    - Frame rate: Every 50msec one frame
    - CPU time: 5msec
- Each CPU burst handles one frame, must meet deadline (finished before next frame has to be displayed)
- Is our system performance good enough to schedule all three streams without delay?
- $C_i / P_i$  is the fraction of CPU time used by process i  $\frac{10}{30} +$ 
  - E.g.: Process A consumes 10/30 of the CPU time available

# Synchronisation

# Resource Competition


- Concurrent processes come into conflict when they are competing for use of the same resource
  - Beside shared data, this can also be I/O devices, processor time, system clock etc.
- Basic requirement
  - Enforce mutual exclusion between processes
    - Allow one process the execution of a course of actions, while excluding all other processes from performing this course of actions

#### Race Condition

- Occurs when multiple processes / threads read and write shared data items
- The processes race to perform their read / write actions
- The final result depends on the order of execution
  - The "winner" of the race is the process that performs the last update and determines the final value of a shared data item

## The Critical Section Problem

- Avoid race conditions
  - enforce mutual exclusion between processes
  - Strict serialisation
- Avoid deadlock and starvation:
  - Enforcing mutual exclusion may result in deadlocks and starvation – has to be solved



#### The Critical Section Problem

- Avoid race conditions by enforcing mutual exclusion between processes
- Control entry to and exit from critical section
  - We need a Critical Section Protocol:
    - Entry section: Each process must request permission for entering a critical section
      - Requires Inter-process communication
      - has to wait / is suspended until entry is granted
    - Exit section:
      - Requires inter-process communication
      - process communicates that it leaves critical section
- Avoid deadlock and starvation:
  - Enforcing mutual exclusion may result in deadlocks and starvation – has to be solved

# Requirements for Mutual Exclusion

- Serialisation of access:
  - Only one process at a time is allowed in the critical section for a resource
- A process that halts in its noncritical section must do so without interfering with other processes
- No deadlock or starvation
- A process must not be delayed in accessing a critical section
- A process remains inside its critical section for a finite time only

## Solution to Critical Section Problem

- Modern solutions use a "lock"
  - Any solution to the critical section problem requires that critical sections are protected by some form of a "lock"
- Lock
  - A shared data item
  - Processes have to "acquire" such a lock before entering a critical section
  - Processes have to "release" a lock when exiting critical section

```
process ()
{
    acquire lock
        critical_section();

    release lock

    remainder_section();
}
```

# Semaphore

```
process ()
{
    wait(S) {
        while(S <= 0) /* do nothing */;
        S -- ;
    }

    critical_section() ;

signal(S)

signal(S) {
        S ++ ;
    }

remainder_section() ;
}</pre>
```

- Semaphores are based on a decrement / increment mechanism:
  - Initialisation:
    - initialised with a non-negative integer value
  - Wait:
    - If semaphore S<= 0, then process has to wait for signal
    - If semaphore S > 0, then process can proceed, S is decremented
  - Signal:
    - S is incremented

## Counting also the Waiting Processes

```
wait(S) {
  while(S <= 0) /* wait */;

  // when wait is over decrement S
  S -- ;
}</pre>
```

- All processes calling wait(S) first decrement the semaphore, then check whether to wait
- A semaphore showing a negative number indicates, that processes are blocked/waiting and how many processes are waiting

#### Counting also the Waiting Processes

```
wait(S) {
                                        if (S < 0) /* wait in blocked
process ()
                                                       queue */;
   wait(S)
      critical section() ;
                                    signal(S) {
   signal(S)
      remainder section() ;
                                       if (S \le 0) /* wakeup
                                                       process */
```

 For counting waiting processes, we need an implementation that suspends waiting processes and adds them to the Blocked queue

#### **Implementation**

- A semaphore is a data structure that contains
  - A counter
  - A waiting queue

```
typedef struct {
  int counter;
  Queue plist;
} Semaphore;
```

- Semaphore can only be accessed by two atomic functions
  - wait (S) : decrements semaphore counter
    - If a process calls wait(), the counter is decremented, if it is zero – semaphore blocks calling process
  - signal(S): increments semaphore counter
    - processes calling signal(S) wake up other processes

# Counting also the Waiting Processes Change of wait() procedure

```
wait(Semaphore S) {
  if(S.value > 0) S.value -- ;
  else {
     add this process to S.plist;
     block();
                          wait(semaphore S) {
                             S.value-- ;
                             if(S.value < 0) {</pre>
                                 add this process to S.plist;
                                 block();
```

- If a process calls wait(S), it first decrements the semaphore, before it checks whether to wait
- A semaphore set to a negative number indicates, that there are blocked / waiting processes and how many processes are waiting

# Counting also the Waiting Processes Change of signal() Procedure

```
signal(Semaphore S) {
   if(S.plist is empty) S.value ++;
   else {
      remove a process P from S.plist;
      wakeup(P);
   }
}

signal(semaphore S) {
      S.value++;
      if(S.value <= 0) {
        remove a process P from S.plist;
        wakeup(P);
      }
   }
}</pre>
```

- If a process calls signal(), it first increments the semaphore value
- A semaphore value lower or equal 0 indicates that there are processes waiting

## Counting the Waiting Processes

#### Semaphore:

```
typedef struct {
   int value ;
   Queue plist ;
} Semaphore ;
```

```
init(Semaphore S, int val) {
   S.value = val;
   S.plist = empty queue;
}
```

```
process ()
{
    wait(S)

    critical_section();

    signal(S)

    remainder_section();
}
• Semaphore counter:
```

```
wait(semaphore S) {
    S.value-- ;
    if(S.value < 0) {
        add this process to S.plist;
        block();
    }
}</pre>
```

```
S.value++ ;
if(S.value <= 0) {
   remove a process P from S.plist;
   wakeup(P);
}</pre>
```

signal(semaphore S) {

- S.value >= 0
  - Number of available resources
- S.value < 0</li>
  - The negative value expresses the number of processes waiting

# Producer – Consumer Ring Buffer

```
init(mutex,1); init(full,0); init(empty, N);
in = 0; out = 0; buffer[N];
```

```
Producer
                         Consumer
while (TRUE)
                         while (TRUE)
                                                 append(x)
{
   x = produce();
                                                    b[in] = x;
                            wait(full);
                                                    in = (in+1) \mod N;
   wait(empty);
                            wait(mutex);
   wait(mutex);
                                                 take()
                            y = take();
   append(x);
                            signal(mutex);
                                                    y = b[out];
   signal(mutex);
                                                    out = (out+1) \mod N;
                            signal(empty);
                                                    return y;
   signal(full);
                            consume(y);
```

- Bounded buffer:
  - Buffer limited to N places, is managed as a circular buffer

#### Dining Philosophers Problem

#### Solution

- 5 philosophers try to eat, allow only 4 philosophers at the table
- at least one philosopher has access to two forks at a time,
- Only 4 processes at a time are allowed to execute "eat()";
- Semaphores
  - Use a counting semaphore "seated" set to 4
  - One semaphore per fork
- No deadlock, no starvation

```
Semaphore fork[5] = {1,1,1,1,1};
init(seated,4);
```

#### Process i


```
while (TRUE)
   think();
   wait(seated);
   wait(fork[i]);
   wait(fork[(i+1) mod 5]);
   eat();
   signal(fork[(i+1) mod 5]);
   signal(fork[i]);
   signal(seated);
```

#### Monitor

- A monitor is a software construct that serves two purposes:
  - enforces mutual exclusion of concurrent access to shared data objects
    - Processes have to acquire a lock to access such a shared resource
  - Support conditional synchronisation between processes accessing shared data
    - Multiple processes may use monitor-specific wait()/signal() mechanisms to wait for particular conditions to hold

#### Monitor

- Process "enters" a monitor
  - It calls one of the procedures
    - Process acquires lock, may have to wait
- One process currently in the monitor
  - Process may call wait(condition)
    - made to wait for a condition in a condition queue
  - Process may call signal(condition)
    - This resumes one of the processes waiting for this conditional signal



#### Producer – Consumer Ringbuffer Monitor

#### RingBuffer

#### **Producer**

```
while(TRUE)
{
    x = produce();
    append(x);
}
```

#### Consumer

```
while(TRUE)
{
    y = take();
    consume(y);
}
```

```
in = 0;
out = 0;
count = 0;
buffer[N];
notfull;
notempty;

void append(char item) {
    if (count == N) wait(notfull);
    b[in] = item;
    in = (in+1) mod N;
    count++;
    signal(notempty);
}
```

# Memory Management

#### Memory Abstraction: Address Space

- Programs operate with an abstraction of physical memory
  - Is a contiguous sequence of "logical" memory addresses
  - Each process lives within its own address space
  - Logical addresses are translated into actual physical memory addresses, whenever processes access memory locations via logical addresses
- Supports
  - Relocation
  - Protection

#### Memory Abstraction: Address Space

- Address space
  - Is a contiguous sequence of "logical" memory addresses
  - Each process lives within its own address space
  - Size of address space depends on processor architecture
    - 32bit architecture: 4 GB, 4 billion logical addresses

Bytes		Exponent			
	1,024	<b>2</b> <sup>10</sup>	1kb	1024bytes	
	1,048,576	<b>2</b> <sup>20</sup>	1MB	1024kb	1024 x 1024
1,0	73,741,824	<b>2</b> <sup>30</sup>	1GB	1024MB	1024 x 1024 x 1024
4,2	94,967,296	<b>2</b> <sup>32</sup>	4GB	4 x 1024MB	4 x 1024 x 1024 x 1024
1,099,5	11,627,776	<b>2</b> <sup>40</sup>	1TB	1024GB	1024 x 1024 x 1024 x 1024
1,125,899,9	06,842,620	<b>2</b> <sup>50</sup>	1PB	1024TB	1024 x 1024 x 1024 x 1024 x 1024
1,152,921,504,6	06,850,000	<b>2</b> <sup>60</sup>	1EB	1024PB	1024 x 1024 x 1024 x 1024 x 1024 x 1024
18,446,744,073,7	09,600,000	<b>2</b> 64	<b>16EB</b>		16 x 1024 x 1024 x 1024 x 1024 x 1024 x 1024

#### Internal Fragmentation

- Programs may not fit into a partition
- Inefficient use of main memory
  - A program will occupy a complete partition, even if it is small and does not need the complete memory allocated
  - Waste of memory: a partition is internally fragmented, free memory fragments of a partition cannot be given to other processes
- This phenomenon is called *internal* fragmentation
  - the block of data loaded (swapped in) is smaller than the partition

#### **External Fragmentation**

- The memory "holes" between assigned partitions may be too small for any process to fit in – waste of memory
- This phenomenon is called *external* fragmentation
  - Memory external to partitions becomes increasingly fragmented
  - Memory utilisation declines

## Virtual Memory Management

- Modern approach
  - All memory references are logical addresses that are dynamically translated into physical addresses at run time
  - Non-contiguous allocation of memory for processes
    - A process may be broken up into a number of pieces pages and/or segments that don't need to occupy a contiguous area of main memory
  - Processes only partially loaded into physical memory

# **Paging**

- Paging allows non-contiguous allocation of memory
  - Allocation of physical memory for a process image that is non-contiguous
- Break up both virtual address space of process image and physical memory into fixed-sized blocks:
  - Frames: Physical memory is divided into fixed-sized blocks, called "frames" or "page frames"
  - Pages: Virtual address space of a process is divided into fixed-sized blocks called "pages"
  - Any page can be assigned to any free page frame

## **Paging**

- Paging avoids external fragmentation and the need for compaction
- Helps to implement virtual memory
  - Page file on hard disk, is also organised in blocks of the same size as a page
  - Pages of a process can easily been swapped in and out of memory
  - We can implement a process image only being partially loaded, pages are loaded on demand
  - No time-consuming search for free best-fit memory fragments, no external memory fragmentation
- Paging is supported by modern hardware

#### Addressing Virtual Memory


- Pages are typically of sizes between 512 bytes and 16MB
- Consider a 32-bit memory address
  - 4kB per page: we need 12 bits ( $2^{12} = 4096$ ) to address a location within the page
  - 20 bits for the page number: we can have  $2^{20} = 1$  Mio pages
    - Page table must have 1 Mio entries
- Address space: 4GB of virtual memory

Byte	s	Exponent			
	1,024	<b>2</b> <sup>10</sup>	1kb	1024bytes	
	1,048,576	<b>2</b> <sup>20</sup>	1MB	1024kb	1024 x 1024
	1,073,741,824	<b>2</b> <sup>30</sup>	1GB	1024MB	1024 x 1024 x 1024
	4,294,967,296	<b>2</b> <sup>32</sup>	4GB	4 x 1024MB	4 x 1024 x 1024 x 1024
	1,099,511,627,776	<b>2</b> <sup>40</sup>	1TB	1024GB	1024 x 1024 x 1024 x 1024
	17,592,186,044,416	<b>2</b> <sup>44</sup>	16TB	16 x 1024GB	16 x 1024 x 1024 x 1024 x 1024
	1,125,899,906,842,620	<b>2</b> <sup>50</sup>	1PB	1024TB	1024 x 1024 x 1024 x 1024 x 1024
1	1,152,921,504,606,850,000	<b>2</b> <sup>60</sup>	1EB	1024PB	1024 x 1024 x 1024 x 1024 x 1024 x 1024
18	3,446,744,073,709,600,000	<b>2</b> 64	<b>16EB</b>		16 x 1024 x 1024 x 1024 x 1024 x 1024 x 1024

#### Translation Lookaside Buffer (TLB)

- Cache for a subset of page table entries (the most used pages)
- Using the TLB
  - CPU generates logical address
  - "TLB hit": If lookup of page number in TLB is successful:
    - the start address of the frame is immediately available for memory access
  - "TLB miss": If lookup of page number in TLB is not successful:
    - the page table in memory has to be accessed first to retrieve the start address of the frame
    - Page number and found frame are added to the TLB (potentially replacing other entries according to a replacement policy)
- TLB must be loaded with process-specific page table entries at each context switch

## Translation Lookaside Buffer (TLB)




#### Fragmentation

- There is no external fragmentation
  - Any free frame can be allocated to a process that needs it
  - This is due to the fixed page size the correspondence between page size and frame size
- There is internal fragmentation
  - As page / frame sizes are fixed, there may be some waste
    - The last frame allocated to a process may not be needed in its completeness
  - Worst case: process may need n frames plus one additional byte! A complete additional frame has to be allocated just for this additional byte of required memory
  - Expected internal fragmentation: on average one-half page per process

#### Page Table Management

- Size of address space of a process influences the maximum size of the page table
  - Can be huge for address spaces 2<sup>32</sup> (4GByte) or 2<sup>64</sup> (16 Exabytes!)
  - Example:
    - Address space: 32-bit logical address space, 4GB
    - Page size: 4kb (2<sup>12</sup>), address space is composed of 2<sup>20</sup> (2<sup>32</sup> / 2<sup>12</sup>) pages (1 Mio)
    - page table may contain up to 1 Mio entries (as many as the process needs)
    - If each entry in page table is 4 bytes (32-bit), then we may need up to 4MB of physical memory to hold this page table
- We many not be able to allocate a contiguous area of physical memory
- The page table itself may be subject to paging

# Page Fault Handling



#### Resident Set

- Is the number of pages currently loaded into physical memory
- Is restricted by the number of frames a process may maximally use

#### Principle of Locality

- References to memory locations within a program tend to cluster
  - if there is an access to a memory location, the next access is, in all likelihood, very near to the previous one
  - Loading one page may satisfy subsequent memory access, as all required memory locations may be contained within this page
- We can observe that only a few pieces of a process image will be needed during short time periods
  - This is the current memory "locality" of a process
  - It is therefore possible to make informed guesses about which pieces will be needed in the near future
- This principle indicates that virtual memory management can be managed efficiently

## Replacement Policy

- Deals with the selection of a page in main memory to be replaced when a new page must be brought in
- Which page should be replaced?
  - Page removed should be the page least likely to be referenced in the near future
- How is that determined?
  - Most policies predict the future behaviour on the basis of past behaviour
- Metrics
  - Minimize page-fault rate
    - Avoid replacement of pages that are needed for the next memory references

#### Page Replacement Algorithms

- The optimal policy (OPT) as a benchmark
- Algorithms used
  - Least recently used (LRU)
  - First-In-First-Out (FIFO)
  - Clock Algorithm


#### **Optimal Policy OPT**

- The theoretically optimal replacement policy
  - Look into the future: select the page for which the time until it is referenced again is the longest among all other pages
- Is not a realistic strategy
  - This policy is impossible to implement, as it would require an operating system to have perfect knowledge about all future events
- But we can use it as a benchmark
  - Gives us the minimum number of page faults possible
- How to do that
  - Record a finite sequence of page references
  - Replay this sequence: in hindsight, we know now which page can be replaced

## **Optimal Policy OPT**

- Assumption
  - 3 memory frames available
  - Process has 5 pages
  - When process is executed, the following sequence of page references occurs (called a page reference string):

#### Page reference string: 2 3 2 1 5 2 4 5 3 2 5 2



F= page fault occurring after the frame allocation is initially filled

OPT policy results in 3 replacement page faults (minus the initial ones to fill the empty frames, total page faults are 6)

## **Optimal Policy OPT**



Reference to page 2:
- We replace page 4 in
Frame 1




	Page ref.	2	3	2	1	5	2	4	5	3	2	5	2
>	Frame1	2	2	2	2	2	2	<mark>4</mark>	4	4	2	2	2
	Frame2		3	3	3	3	3	3	3	3	3	3	3
	Frame3				1	<mark>5</mark>	5	5	5	5	5	5	5
	Page fault					F		F			F		
	fault												

- In this particular example, the "optimal" policy would create 3 replacement page faults
- In reality, we cannot know the future, therefore we may have more page faults
- OPT is our "benchmark"

## Least Recently Used (LRU)

- Idea: past experience gives us a guess of future behaviour
- Replaces "least recently used" page: replace the page that has not been referenced for the longest time
  - "Least recently used" page should be the page least likely to be referenced in the near future
- Pages that are more frequently used remain in memory
- Good behaviour in terms of page faults
  - Almost as good as OPT
- Difficult to implement
  - Search for oldest page may be costly
  - One approach would be to tag each page with the time of the last reference
  - Requires great deal of overhead to manage

#### LRU Policy



F= page fault occurring after the frame allocation is initially filled

- The LRU policy does almost as well as the theoretical optimal policy OPT
  - LRU recognises that pages 2 and 5 are referenced more frequently than other pages, whereas FIFO does not
- We have to look into the past to guess what trend future page references may follow

#### LRU Policy




Reference to pages 4:

- We replace page 1 in Frame 3



	Page ref.	2	3	2	1	5	2	4	5	3	2	5	2
	Frame1	2	2	2	2	2	2	2					
	Frame2		3	3	3	<mark>5</mark>	5	5					
>	Frame3				1	1	1	<mark>4</mark>					
	Page fault					F		F					



We replace page 2 in Frame 1

Reference to page 2:

We replace page 4
 in Frame 3



Page ref.	2	3	2	1	5	2	4	5	3	2	5	2
Frame1	2	2	2	2	2	2	2	2	3	3	3	3
Frame2		3	3	3	<mark>5</mark>	5	5	5	5	5	5	5
Frame3				1	1	1	<mark>4</mark>	4	4	2	2	2
Page fault					F		F		F	F		

- With LRU, we replace page 2 with page 3, and immediately afterwards, we need page 2 again
- LRU is not able to detect this situation
- However, it is a strategy that comes close to OPT


#### First-In-First-Out (FIFO)

- Treats memory frames allocated to a process as a circular buffer
- Pages are replaced in a round-robin style
  - Is the simplest replacement policy to implement
- When a page has to be replaced, then the "oldest" page will be chosen
  - What if this page is immediately needed again?
- Problem
  - Does not indicate how heavily a page is actually used

#### **Clock Policy**

#### Implementation of Second-Chance Algorithm

- The set of frames is considered as laid out like a circular buffer
  - contains a FIFO list of pages
  - Can be circulated in a roundrobin fashion
- Each page has a reference bit
  - When a page is first referenced (a page fault that leads to its load), the use bit of the frame is set to 1
- Each subsequent reference to this page again sets this bit to 1



(a) State of buffer just prior to a page replacement

### Clock Algorithm

#### Implementation of Second-Chance Algorithm

- Initially, all frames in circular buffer are empty
  - Each frame entry has a use bit (reference bit)
- Frame pointer: is regarded the "clock hand", is called the "next frame" pointer
- Procedure
  - Occurrence of page fault:
    - Progress position pointer to first unused frame (use bit == 0)
    - During this progression: set use bit of visited frame entries to 0
  - Load page into free frame, set use bit to 1
  - Move position pointer to next frame
- When the circular buffer is filled with pages, the "next frame" pointer has made one full circle
  - it will be back at the first page loaded
    - points to the "oldest" page

## Thrashing

- Thrashing is a situation where a process is repeatedly page faulting
  - The process does not have enough frames to support the set of pages needed for fully executing an instruction
  - It may have to replace a page that itself or another process may need again immediately
- A process is thrashing if it is spending more time on paging than execution

## Thrashing

- Important: need of clever page replacement algorithms
  - Don't replace a page you may need in the immediate future
  - Avoid unnecessary writes for unchanged pages
- Thrashing
  - A state in which the system spends most of its time swapping pieces rather than executing instructions
- Operating tries to avoid thrashing by guessing which loaded pages are least likely to be used in the near future – candidates for being replaced

### **Prevent Thrashing**

- If we want to prevent thrashing, we must provide a process with as many frames as it "needs"
- How many frames are needed?
- Principle of Locality
  - A "locality" is a set of pages that are actively used together during program execution
  - A program is generally composed of several different localities that may overlap
  - As a process executes, it moves from locality to locality

#### Frame Allocation to Processes

- Each process is allocated free memory
  - Each process has a Free-frame list
  - Demand-paging will allocate frames from this list due to page faults
  - When the free-frame list is exhausted, a page replacement algorithm will choose a page to be replaced
- With multiple processes: how many free frames should be allocated to each process?

#### Minimum Number of Frames

- Performance depends on a minimum number of frames allocated
  - If number of free frames decreases, page faults increase
  - Increase of page faults slows process execution
    - I/O operations
    - Instruction that leads to a page fault has to be restarted (effectively executing instructions twice)
- We need enough frames to hold all the pages in memory that are referenced by any single instruction – principle of locality
- We have to manage the size of the resident set

#### Resident Set

- Is the number of pages currently loaded into physical memory
- Is restricted by the number of frames a process may maximally use

### Working Set

Working Set

Set of pages a process is currently working with and which should be resident in memory to avoid thrashing

- A working set is an approximation of a program's locality
- It is the set of pages actively used by a process and all these pages should be held in memory
- The size of this set gives us an estimate how many frames should be allocated to a process – how large the resident should be

### Working Set

- Provides insight in the required amount of page frames for a process
- What to do if the Resident set is too small
  - Consult the "working set": Add more frames
  - If we ran out of frames, suspend process and try to allocate again later
- Periodic discarding of pages from the resident set that are not in the working set
  - These are pages that are loaded into memory, but haven't been referenced for a long time

### Working Set

- A working set is an approximation of a program's locality
- Uses the most recent page references from a program to determine which pages are most important
  - Parameter  $\Delta$ : the most recent  $\Delta$  page references
- Defines a "working set window"
  - The set of pages that are referenced within the recent Δ page references
  - A page in active use is part of the working set window
  - If a page is not used for Δ time units, it will be dropped from the working set window

### Working Set Size WSS

- Parameter Δ : number of most recent page reference observations
  - If  $\Delta$  is too small, not all actively used pages will be in the working set window
  - If  $\Delta$  is too large, it may overlap several localities
- Working set size WSS<sub>i</sub>
  - Size of the working set for process i
  - Depends on how many past observations Δ are taken into account
  - Process is actively using all the pages in its working set
- Therefore, a process needs at least WSS<sub>i</sub> frames to avoid thrashing
- Operating system monitors the working set of a process and allocates WSS<sub>i</sub> frames to the process

# File Management

### Files

- Files provide a way to store information on disk
- Files are an abstraction concept
  - Users operate with a simple model of a byte stream being written to or read from disk
  - Operating system hides details how disk space is allocated to store the information represented by a file

### File System

- Provides an organised, efficient and secure access to data on secondary storage
- Organisation
  - Organises data into files, directories
  - Supports APIs to manipulate these management objects
- Efficiency
  - Perform I/O in blocks rather than bytes, random access to any block on a disk
- Security and integrity
  - Define ownership of files, permissions
  - Allow recovery from failures, avoid data loss


#### File Allocation Method


- Disks are organised in a block structure, each block of a particular size
- A file is stored on disk as a collection of these blocks
  - Blocks are allocated to files
- Block allocation strategies
  - Contiguous allocation
  - Non-contiguous allocation:
    - chained allocation
    - Indexed allocation
    - FAT, i-Nodes

#### File Allocation Methods


- File Allocation Table (FAT)
  - Is a linked-list allocation form
  - Eliminates disadvantages by taking the pointer of the block and holding it in an extra table – the File Allocation Table
  - File Allocation Table held in memory, used to find file
    - Actual blocks don't waste space for pointers
    - All pointers now in main memory, can easily be followed for find a block address and performing one I/O action to load block

### File Allocation Table FAT





### File Allocation Table FAT



### Size of FAT

- Storage: 8GB USB drive, Block size: 4KB
- How many blocks do we need on the disk for the FAT?
- Remember:
  - 8GB = 8 x 1024 x 1024 x 1024 bytes
  - 4KB = 4 x 1024 bytes
- We calculate:
  - 8GB / 4KB = 8 x 1024 x 1024 x 1024 bytes / 4 x 1024 bytes = 2 x 1024 x 1024 = 2 Mio blocks
- Addressing:
  - We need at least 2<sup>21</sup> entries in the FAT to address all 2 Mio blocks (2 x 2<sup>20</sup>)
  - We choose a 32-bit format for FAT entries (4 bytes), 1 block can hold 1024 entries: 4 x 1024 bytes / 4 bytes = 1024 entries
- Space for FAT on disk
  - 2 x 1024 x 1024 entries / 1024 entries = 2 x 1024 = 2048 blocks for the FAT

Ву	tes	Exponent			
	1,024	<b>2</b> <sup>10</sup>	1kb	<b>1024bytes</b>	
	1,048,576	<b>2</b> <sup>20</sup>	1MB	1024kb	1024 x 1024
	1,073,741,824	<b>2</b> <sup>30</sup>	1GB	1024MB	1024 x 1024 x 1024
	4,294,967,296	<b>2</b> <sup>32</sup>	4GB	4 x 1024MB	4 x 1024 x 1024 x 1024
	1,099,511,627,776	<b>2</b> <sup>40</sup>	1TB	1024GB	1024 x 1024 x 1024 x 1024
	1,125,899,906,842,620	<b>2</b> <sup>50</sup>	1PB	1024TB	1024 x 1024 x 1024 x 1024 x 1024
	1,152,921,504,606,850,000	<b>2</b> <sup>60</sup>	1EB	1024PB	1024 x 1024 x 1024 x 1024 x 1024 x 1024
	18,446,744,073,709,600,000	<b>2</b> 64	<b>16EB</b>		16 x 1024 x 1024 x 1024 x 1024 x 1024 x 1024

#### Indexed Allocation

- Addresses problems of contiguous and linkedlist allocation
  - Fast load of complete file
  - Random access to a particular block
- Indexes are hierarchical
  - One block can only contain a small list of addresses to disk blocks
  - Solution: multiple levels
    - Entry in index table points to another index table


### Inodes

- All types of Unix files are managed by the operating system by means of inodes
  - Is a control structure (index node) that contains the key information needed by the operating system for a particular file
    - Describes its attributes
    - Describes the layout of the file (allocated blocks)
- There can be several file names for a single inode
- But:
  - An active inode is associated with exactly one file
  - Each file is controlled by exactly one inode

#### File Allocation with Inodes

- Inode contains index referencing allocated blocks
  - First N entries point directly to the first N blocks allocated for the file
  - If file is longer than N blocks, more levels of indirection are used
  - Inode contains three index entries for "indirect" addressing
    - "single indirect" address:
      - Points to an intermediate block containing a list of pointers
    - "double indirect" address:
      - Points to two levels of intermediate pointer lists
    - "triple indirect" address:
      - Points to three levels of intermediate pointer lists
- The initial direct addresses and the three multi-level indirect addressing means form the index

#### Inode Indexed References of Disk Blocks



#### File Allocation with i-Nodes

- What is maximum size of a file that can be indexed:
  - Depends of the capacity of a fixed-sized block
- Example implementation with 15 index entries:
  - 12 direct, single (13) / double (14) / triple (15) indirect
  - Block size 4kb, holds 512 block addresses (32-bit addresses)

Level	Number of Blocks	Number of Bytes
Direct	12	48K
Single Indirect	512	2M
<b>Double Indirect</b>	$512 \times 512 = 256$ K	1G
<b>Triple Indirect</b>	$512 \times 256$ K = $128$ M	512G

## Journaling File System

- Idea
  - Keep a small circular log on disk
  - Record in this what write actions will be performed on the file system, before actual disk operations occur
- Log file helps to recover from system crashes
  - After a system crash, operating system can take information from log file and perform a "roll forward":
    - Finish write operations as recorded in journal

### Journaling File System

- Manipulation done in the form of transactions
  - First, recording of operations in log (begin of transaction)
    - All three actions necessary for deleting a file are recorded
    - Log entry is written to disk
  - Second, after log recordings, actual write operations begin
  - Third, when all write operation on disk successful (across system crashes), log entry is deleted (end of transaction)

### Journaling File Systems

- Robust in case of system crashes
  - Logs are checked after recovery and logged actions redone
  - this can be done multiple times if there are multiple system crashes
- Changes to file system are atomic
- Logged operations must be "idempotent"
  - Can be repeated as often without harm
  - E.g.: "mark i-node k as free" can be done over and over again

### Deadlock

#### **Deadlock Conditions**

 There are 4 deadlock conditions that, when they all hold, will necessarily lead to a deadlock

#### (Three pre-conditions)

- 1. Mutual Exclusion
  - There are mechanisms to enforce mutual exclusion between processes
- Hold and Wait
  - Process can hold resources, while it is waiting for other resources to become available
- 3. No Preemption
  - Processes cannot be interrupted to free their resources by force

#### (Occurrence of a particular sequence of events)

- 4. Circular Wait
  - Processes wait for each other to release resources they want to acquire, they form a kind of "closed chain of processes"

### Handling Deadlocks

- Deadlock prevention
  - Avoid at least one of the 4 deadlock conditions
- Deadlock avoidance
  - The reservation of resources that would lead to deadlock, are not granted
- Deadlock detection
  - There is no restriction on resource allocation
  - There is a periodic check whether a deadlock is occurring
  - In case of a detected deadlock, recovery mechanisms are employed