Chapter 06 Synchronization Tools

Concepts and solutions to synchronization problems

Outline

- Background
- ◆ The Critical-Section Problem
- Peterson's Solution
- Hardware Support for Synchronization
- Mutex Locks
- Semaphores
- Monitors
- Liveness
- Evaluation

Objectives

- Describe the critical-section problem and illustrate a race condition.
- Illustrate hardware solutions to the critical-section problem using memory barriers, compare-and-swap operations, and atomic variables.
- Demonstrate how mutex locks, semaphores, monitors, and condition variables can be used to solve the critical-section problem.
- ◆ Evaluate tools that solve the critical-section problem in low-, moderate-, and high-contention scenarios.

Background

- Processes can execute concurrently
 - May be interrupted at any time, partially completing execution
- Concurrent access to shared data may result in data inconsistency
- Maintaining data consistency requires mechanisms to ensure the orderly execution of cooperating processes
- ◆ Illustration of the problem: Suppose that we wanted to provide a solution to the consumer-producer problem that fills all the buffers. We can do so by having an integer counter that keeps track of the number of full buffers. Initially, counter is set to 0. It is incremented by the producer after it produces a new buffer and is decremented by the consumer after it consumes a buffer.

Background

Producer

```
while (true) {
   /* produce an item in next produced */
   while (counter == BUFFER_SIZE) ; /* do nothing */
   buffer[in] = next_produced;
   in = (in + 1) % BUFFER_SIZE;
   counter++;
```

◆ Consumer

```
while (true) {
  while (counter == 0); /* do nothing */
  next_consumed = buffer[out];
  out = (out + 1) % BUFFER_SIZE;
  counter--;
  /* consume the item in next consumed */
```

Race Condition

- counter++ could be implemented as register₁ = counter register₁ = register₁ + 1 counter = register₁
- counter-- could be implemented as register₂ = counter register₂ = register₂ - 1 counter = register₂
- ◆ Consider this execution interleaving with "count = 5" initially:

```
\begin{array}{ll} T_0: \ producer\ execute\ register_1 = counter \\ T_1: \ producer\ execute\ register_1 = register_1 + 1 \\ T_2: \ consumer\ execute\ register_2 = counter \\ T_3: \ consumer\ execute\ register_2 = register_2 - 1 \\ T_4: \ producer\ execute\ counter = register_1 \\ T_5: \ consumer\ execute\ counter = register_2 \end{array} \quad \begin{cases} register_1 = 5 \\ register_2 = 5 \\ register_2 = 4 \\ register_2 = 4 \end{cases}
```

- Several processes access and manipulate the same data concurrently and the outcome of the execution depends on the particular order in which the access takes place, is called a race condition.
- We devote a major portion of this chapter to process synchronization and coordination among cooperating processes.

Critical Section Problem

- lacktriangle Consider system of n processes $\{p_0, p_1, \dots p_{n-1}\}$
- ◆ Each process has critical section segment of code
 - □ Process may be changing common variables, updating table, writing file, etc.
 - When one process in critical section, no other may be in its critical section
 while (true) {
- Critical section problem is to design protocol to solve this.
- Each process must ask permission to enter critical section in entry section, may follow critical section with exit section, then remainder section

 $entry\ section$

critical section

 $exit\ section$


remainder section

Solution to Critical-Section Problem

- Mutual Exclusion If process Pi is executing in its critical section, then no other processes can be executing in their critical sections
- Progress If no process is executing in its critical section and there exist some processes that wish to enter their critical section, then the selection of the processes that will enter the critical section next cannot be postponed indefinitely
- 3. Bounded Waiting A bound must exist on the number of times that other processes are allowed to enter their critical sections after a process has made a request to enter its critical section and before that request is granted
 - Assume that each process executes at a nonzero speed
 - No assumption concerning relative speed of the n processes

Solution to Critical-Section Problem

 Race condition on the variable kernel variable next available pid



- No problem in single core environment
 - □ Achieve by prevent interrupts from occurring while a shared variable was being modified
 - Time consuming and thus infeasible

Critical-Section Handling in OS

- Two approaches depending on if kernel is preemptive or non-preemptive
 - Preemptive allows preemption of process when running in kernel mode
 - Non-preemptive runs until exits kernel mode, blocks, or voluntarily yields CPU
 - Essentially free of race conditions in kernel mode

Peterson's Solution

- Good algorithmic description of solving the problem
- Two-process solution
- Assume that the load and store machinelanguage instructions are atomic; that is, cannot be interrupted
- The two processes share two variables:
 - □ int turn;
 - ☐ Boolean flag[2]
- The variable turn indicates whose turn it is to enter the critical section
- The flag array is used to indicate if a process is ready to enter the critical section. flag[i] = true implies that process P_i is ready!

Peterson's Solution

Algorithm for Process P;
do {
 flag[i] = true;
 turn = j;
 while (flag[j] && turn = = j);
 critical section
 flag[i] = false;
 remainder section
} while (true);

- Provable that the three CS requirement are met:
 - 1. Mutual exclusion is preserved
 P_i enters CS only if:
 either flag[j] = false or turn = i
 - 2. Progress requirement is satisfied
 - 3. Bounded-waiting requirement is met

Peterson's Solution

- Peterson's solution is not guaranteed to work on modern computer architectures.
 - □ Processors and/or compilers may reorder read and write operations with no dependency for performance.
- Consider the following example:

What are the results?

Hardware Support for Synchronization

- The solution we have just described is softwarebased.
 - No special support from the operating system
 - No specific hardware instructions to ensure mutual exclusion
 - Not necessary work on contemporary computer architectures

Memory Barriers

- How a computer architecture determines what memory guarantees it will provide to an application program is known as its memory model, which has two categories:
 - ☐ Strongly ordered- memory modification is immediately visible
 - Weakly ordered- memory modification is **not** immediately visible
- Memory models vary- we cannot assume the type.
- Addressed by memory barriers (memory fences)instructions that can force any changes in memory to be propagated to all other processors.

Memory Barriers

- Consider the previous example with memory barriers
 - Thread 1
 while (!flag)
 memory_barrier();
 print x;

 Thread 2
 x = 100;
 memory_barrier();
 flag = true;
- Memory barriers are low-level operations
 - Typically only used by kernel developers

- Modern machines provide special atomic hardware instructions
 - Atomic = non-interruptible
 - □ test and set(): test memory word and set value
 - □ compare and swap(): swap contents of two words

test_and_set() instruction:
boolean test_and_set (boolean *target)
{
 boolean rv = *target;
 *target = TRUE;
 return rv:
}

- 1. Executed atomically
- 2. Returns the original value of passed parameter
- 3. Set the new value of passed parameter to "TRUE".

◆ Use of test_and_set() for processor P;

□ Shared Boolean variable lock, initialized to false do {
 while (test_and_set(&lock))
 ; /* do nothing */
 /* critical section */
 lock = false;
 /* remainder section */
} while (true);

compare and swap () CAS instruction:

- 1. Executed atomically
- 2. Returns the original value of passed parameter "value"
- 3. Set the variable "value" the value of the passed parameter "new_value" but only if "value" =="expected". That is, the swap takes place only under this condition.

◆ Use of compare_and_swap() for processor P;:

□ Shared integer lock initialized to 0
do {
 while (compare_and_swap(&lock, 0, 1) != 0)
 ; /* do nothing */
 /* critical section */
 lock = 0;
 /* remainder section */
} while (true);

 Bounded-waiting mutual exclusion with test and set(): ☐ Shared data: boolean waiting[n]; int lock; ■ Solution while (true) { waiting[i] = true; while (waiting[i] && key)
 key = test_and_set(&lock); waiting[i] = False; critical section */ j != i) && !waiting[j]) lock = false: else waiting[j] = false;
/* remainder section */

 Bounded-waiting mutual exclusion with compare and swap(): ☐ Shared data: boolean waiting[n]; int lock; ■ Solution while (true) { waiting[i] = true; while (waiting[i] && key == 1)
 key = compare and swap(&lock,0,1); waiting[i] = false; /* critical section */ (j != i) && !waiting[j])
(j + 1) % n; else waiting[j] = false;
/* remainder section */

Atomic Variables

- ◆ Typically, the compare_and_swap() instruction is used to build tools for solving critical-section problem such as the atomic variable.
 - Provide atomic operation
 - Ensure mutual exclusion
- For example, increment (&sequence); increment the atomic integer sequence as follows:

```
void increment(atomic_int *v) {
   int temp;
   do {
   temp = *v;
   } while (temp != compare_and_swap(v, temp,
temp+1));
}
```

Mutex Locks

- Previous solutions are complicated and generally inaccessible to application programmers
- OS designers build software tools to solve critical section problem
- Simplest is mutex lock (abbr. for mutual exclusion)
- Protect a critical section by first acquire() a lock then release() the lock
 - Boolean variable indicating if lock is available or not
- Calls to acquire() and release() must be atomic
 - Usually implemented via hardware atomic instructions

```
do {
   acquire lock
      critical section
   release lock
      remainder section
} while (TRUE);
```

Mutex Locks

- acquire() and release()
 - Boolean variable indicating if lock is available or not

```
acquire() {
   while (!available)
    ; /* busy wait */
   available = false;
}
```

```
release() {
   available = true;
}
```

Mutex Locks

- But this solution requires busy waiting
 - This lock therefore called a spinlock
- Lock contention
 - Contended- a thread blocks while trying to acquire the lock
 - High contention decreases concurrency.
 - Uncontended- a lock is available when a thread attempts to acquire it
- What is meant by "short duration"?
 - □ Generally, less than 2 context switches (one to wait and one to restore)

Semaphore

- Synchronization tool that provides more sophisticated ways (than Mutex locks) for process to synchronize their activities.
- ◆ Semaphore S integer variable
- Can only be accessed via two indivisible (atomic) operations
 - wait() and signal()
 - ☐ Originally called P() and V()
 - Represent proberen, and verhogen
- Definition of the wait() operation

```
wait(S) {
    while (S <= 0)
     ; // busy wait
    S--;
}</pre>
```

Definition of the signal() operation
signal(S) {
 S++;
}

Semaphore Usage

- Counting semaphore integer value can range over an unrestricted domain
- Binary semaphore integer value ranges between 0 and 1
 Same as a mutex lock
- Can solve various synchronization problems
- Consider P₁ and P₂ that require S₁ to happen before S₂
 Create a semaphore "synch" initialized to 0

```
P1:
S<sub>1</sub>;
signal(synch);
P2:
wait(synch);
S<sub>2</sub>;
```

Can implement a counting semaphore S as a binary semaphore

Semaphore Implementation

- With each semaphore there is an associated waiting queue
- Two operations:
 - sleep— place the process invoking the wait() on the appropriate waiting queue if the semaphore value is not positive
 - wakeup remove one process in the waiting queue and place it to the ready queue when some process executes signal()
- ◆ Each entry in a waiting queue has two data items:
 - value (of type integer)
 - pointer to next record in the list

```
typedef struct{
   int value;
   struct process *list;
} semaphore;
```

Semaphore Implementation

wait() semaphore operation:

```
wait(semaphore *S) {
    S->value--;
    if (S->value < 0) {
        add this process to S->list;
        sleep();
    }
    system call
}
```

signal() semaphore operation:

```
signal(semaphore *S) {
    S->value++;
    if (S->value <= 0) {
        remove a process P from S->list;
        wakeup(P);
    }
    system call
}
```

Semaphore Implementation

- Must guarantee that no two processes can execute the wait() and signal() on the same semaphore at the same time
- Thus, the implementation becomes the critical section problem where the wait and signal code are placed in the critical section
 - Could now have busy waiting in critical section implementation
 - But implementation code is short
 - Little busy waiting if critical section rarely occupied
- Note that applications may spend lots of time in critical sections and therefore this is not a good solution

Monitors

- Incorrect use of semaphore operations:
 - □ signal(mutex); ... critical section ... wait(mutex);
 - wait(mutex); ... critical section ... wait(mutex);
 - Omit of wait (mutex) or signal (mutex) or both
- Address by incorporating simple synchronization tool as high-level language constructs: the monitor type.

Monitor Usage


- A high-level abstraction that provides a convenient and effective mechanism for process synchronization
- Abstract data type, internal variables only accessible by code within the procedure

```
monitor monitor-name {
    /* shared variable declarations */
    function F1 (...) {...}

function Fn (...) {...}


initialization_code (...) {...}
}
```

- Only one process may be active within the monitor at a time
- But not powerful enough to model some synchronization schemes



Monitor Usage

- Condition Variables
 - Two operations are allowed on a condition variable
 - x.wait() a process that invokes the operation is suspended until x.signal()
 - mathred x.signal() resumes one of processes (if any) that
 invoked x.wait()
 - If no x.wait() on the variable, then it has no effect on the variable



Monitor Usage

- Condition Variables Choices
 - If process P invokes x.signal(), and process Q is suspended in x.wait(), what should happen next?
 - Both Q and P cannot execute in parallel. If Q is resumed, then P must wait
 - Options include
 - Signal and wait P waits until Q either leaves the monitor or it waits for another condition
 - Signal and continue Q waits until P either leaves the monitor or it waits for another condition
 - Both have pros and cons language implementer can decide
 - A compromise: P executing signal immediately leaves the monitor, Q is resumed
 - Implemented in other languages including C#, Java

Implementing a Monitor Using Semaphores

- Variables semaphore mutex; // (initially = 1) semaphore next; // (initially = 0) int next count = 0; Each function F will be replaced by wait(mutex); body of F; if (next count > 0) signaT(next) else signal(mutex);
- Mutual exclusion within a monitor is ensured

Implementing a Monitor Using Semaphores

For each condition variable x, we have: semaphore x sem; // (initially = 0) int x count = 0;The operation x.wait can be implemented as: x count++; if (next count > 0) signal(next); else signal(mutex); wait(x sem); x count--; The operation x.signal can be implemented as if (x count > 0) { next count++; signal(x sem); wait(next); next count--;

Resuming Processes within a Monitor

- If several processes queued on condition x, and
 x.signal() executed, which should be resumed?
 FCFS frequently not adequate
- conditional-wait construct of the form x.wait(c)
 - ☐ Where c is priority number
 - Process with lowest number (highest priority) is scheduled next

Resuming Processes within a Monitor

Resource Allocator

```
monitor ResourceAllocator{
   boolean busy;
   condition x;
   void acquire(int time) {
      if (busy)
         x.wait(time);
      busy = TRUE;
   void release() {
      busy = FALSE;
      x.signal();
   initialization code(){
      busy = FALSE;
```

Resuming Processes within a Monitor

Allocate a single resource among competing processes using priority numbers that specify the maximum time a process plans to use the resource R.acquire(t);

```
access the resource;
...
R.release();
```

Where R is an instance of type ResourceAllocator

- ◆ The monitor concept cannot guarantee that the preceding access sequence will be observed.
 - Access without first gaining access permission
 - Never release once it has been granted access
 - Attempt to release yet it never requested.
 - ☐ Request the same resource twice without first releasing it

Liveness

- Liveness refers to a set of properties that a system must satisfy to ensure that processes make progress during their execution life cycle.
 - Waiting indefinitely is an example of a "liveness failure."
- Forms of liveness failure
 - Infinite loop
 - Busy wait presents the possibility of starvation
 - Deadlock
 - Priority inversion

Deadlock

- Deadlock two or more processes are waiting indefinitely for an event that can be caused by only one of the waiting processes
- Let S and Q be two semaphores initialized to 1

Priority Inversion

- Priority Inversion Scheduling problem when lowerpriority process holds a lock needed by higher-priority process
- For example, consider three processes L, M, and H
 - \square Priorities: L < M < H
 - ☐ H requires semaphore S belonging to L
 - If M preempts L: it decides how long H must wait for L
- Solved via priority-inheritance protocol
 - □ All processes that are accessing resources needed by a higher-priority process inherit the higher priority until they are finished using the resources.
 - Let L inherit the priority of H during the time when holding L

Evaluation

- There has been a recent focus on using the CAS instruction to construct lock-free algorithms that provide protection from race conditions without requiring the overhead of locking.
 - ☐ CAS-based approaches are considered as an *optimistic* approach
 - Mutex lock is considered a pessimistic strategy
- The following guidelines identify general rules concerning performance differences
 - ☐ Uncontended. CAS protection will be somewhat faster than traditional synchronization.
 - Moderate contention. CAS protection will be faster—possibly much faster—than traditional synchronization.
 - ☐ High contention. Under very highly contended loads, traditional synchronization will ultimately be faster than CAS-based synchronization.

Evaluation

- The choice of a mechanism that addresses race conditions can also greatly affect system performance.
 - Atomic integers is good at sharing counters.
 - ☐ Spinlock are held for short duration.
 - Mutex locks better binary semaphores.
 - ☐ Counting semaphore is proper for controlling access to resources than mutex locks.
- Much ongoing research toward developing scalable, efficient tools that address the demands of concurrent programming.
 - Design compilers able to generate more efficient code.
 - Develop languages which support concurrent programming.
 - Improve the performance of existing libraries and APIs.