

Création VM GLPI

Create: Virtual Machine

General OS System Disks CPU Memory Network Confirm

Node: SRVDEPLOY-S4P2 Resource Pool: SIO1

VM ID: 103

Name: SRV-GLPI

Add to HA: ☐

Start at boot: ☐

Start/Shutdown order: any

Startup delay: default

Shutdown timeout: default

Tags

No Tags +

Help Advanced ☒ Back Next

Choisir ISO « unbutu server 24.04.4 »

Create: Virtual Machine

General OS System Disks CPU Memory Network Confirm

☒ Use CD/DVD disc image file (iso)

Storage: local

ISO image: ubuntu-24.04.4-live-se

Guest OS:


Type: Linux

Version: 6.x - 2.6 Kernel

☐ Use physical CD/DVD Drive


☐ Do not use any media

Advanced ☒ Back Next



Clic sur « Advanced », BUS/ Device: “SATA”, Disk size(Gib): “20”

Et cocher la case « SSD emulation »



Create: Virtual Machine

General OS System Disks **CPU** Memory Network Confirm

Sockets: 1 Type: x86-64-v2-AES

Cores: 1 Total cores: 1

VCPUs: 1 CPU units: 100

CPU limit: unlimited Enable NUMA: ☐

CPU Affinity: All Cores

Extra CPU Flags:

Default	- ☐ ☐ ☐ ☐ +	nested-virt	Controls nested virtualization, namely 'svm' for AMD CPUs and 'vmx' for Intel CPUs. Live migration still only works if it's the same flag on both sides. For Windows, use a CPU model similar to the host, with the same vendor!
Default	- ☐ ☐ ☐ ☐ +	md-clear	Required to let the guest OS know if MDS is mitigated correctly.
Default	- ☐ ☐ ☐ ☐ +	pcid	Meltdown fix cost reduction on Westmere, Sandy-, and IvyBridge Intel CPUs.
Default	- ☐ ☐ ☐ ☐ +	spec-ctrl	Allows improved Spectre mitigation with Intel CPUs.
Default	- ☐ ☐ ☐ ☐ +	ssbd	Protection for 'Speculative Store Bypass' for Intel models.

Help Advanced ☒ Back Next

Memory(MiB) : 2 go

Create: Virtual Machine

General OS System Disks CPU **Memory** Network Confirm

Memory (MiB): 2048

Minimum memory (MiB): 2048

Shares: Default (1000)

Ballooning Device: ☒

Allow KSM: ☒

Help Advanced ☒ Back Next

Bridge : mettre « vmbrSIO1 »

Create: Virtual Machine

General OS System Disks CPU Memory **Network** Confirm

☐ No network device

Bridge: Model:

VLAN Tag: MAC address:

Firewall: ☒

Disconnect: ☐ Rate limit (MB/s):

MTU: Multiqueue:

☒ Advanced

Faire « FINISH »

Create: Virtual Machine

General OS System Disks CPU Memory Network **Confirm**


Key ↑	Value
cores	1
cpu	x86-64-v2-AES
ide2	local:iso/ubuntu-24.04.4-live-server-amd64.iso,media=cdrom
memory	2048
name	SRV-GLPI
net0	virtio,bridge=vmbrSIO1,firewall=1
nodename	SRVDEPLOY-S4P2
numa	0
ostype	l26
pool	SIO1
sata0	local-lvm:20,ssd=on
scsihw	virtio-scsi-single
sockets	1
vmid	1003

☐ Start after created


☒ Advanced

Installation Unbutu server

Choisir la langue ici « Français »



Sélectionner « Mise à jour vers le nouveau programme d'installation »



Par défaut c'est « Français » clic « Done »

Keyboard configuration

[Help]

Please select your keyboard layout below, or select "Identify keyboard" to detect your layout automatically.

Layout: [French ▼]


Variant: [French - French (legacy, alt.) ▼]

[Identify keyboard]


[Done]

[Back]

« Unbutu Server » est sélectionner par défaut clic « done »




Clic sur « ens18 »




Clic « Ipv4 »



Sélectionner « Manual »



Mettre la config qui correspond à son infra



Skip cette étape

Proxy configuration

[Help]

If this system requires a proxy to connect to the internet, enter its details here.

Proxy address:

If you need to use a HTTP proxy to access the outside world, enter the proxy information here. Otherwise, leave this blank.

The proxy information should be given in the standard form of "http://[user][:pass]@host[:port]/".

Attendre qui s'affiche « Lecture des Paquets » vérifier si il n'y a pas d'erreur puis clic sur « Done »

Ubuntu archive mirror configuration

[Help]

If you use an alternative mirror for Ubuntu, enter its details here.

Mirror address:

You may provide an archive mirror to be used instead of the default.

This mirror location passed tests.

```
Atteint :1 http://archive.ubuntu.com/ubuntu noble InRelease
Réception de :2 http://archive.ubuntu.com/ubuntu noble-updates InRelease [126 kB]
Réception de :3 http://archive.ubuntu.com/ubuntu noble-backports InRelease [126 kB]
252 ko réceptionnés en 1s (280 ko/s)
Lecture des listes de paquets...
```

[Done]

[Back]

« Done »

Configure a guided storage layout, or create a custom one:

(X) Use an entire disk

[X] Set up this disk as an LVM group

[] Encrypt the LVM group with LUKS

Passphrase:

Confirm passphrase:

[] Also create a recovery key
The key will be stored as ~/recovery-key.txt in the live system and will be copied to /var/log/installer/ in the target system.

() Custom storage layout

« Done »

FILE SYSTEM SUMMARY

MOUNT POINT	SIZE	TYPE	DEVICE TYPE
[/	10.000G	new ext4	new LVM logical volume ▶]
[/boot	1.771G	new ext4	new partition of local disk ▶]

AVAILABLE DEVICES

DEVICE	TYPE	SIZE
[ubuntu-vg (new)	LVM volume group	18.222G ▶]
free space		8.222G ▶]
[Create software RAID (md) ▶]		
[Create volume group (LVM) ▶]		

USED DEVICES

DEVICE	TYPE	SIZE
[ubuntu-vg (new)	LVM volume group	18.222G ▶]
ubuntu-lv	new, to be formatted as ext4, mounted at /	10.000G ▶]
[QEMU_HARDDISK_QM00005	local disk	20.000G ▶]
partition 1	new, BIOS grub spacer	1.000M ▶]
partition 2	new, to be formatted as ext4, mounted at /boot	1.771G ▶]
partition 3	new, PV of LVM volume group ubuntu-vg	18.225G ▶]

[Done]
[Reset]
[Back]

Mettre sa config et son ID et son MDP

Profile configuration [Help]

Enter the username and password you will use to log in to the system. You can configure SSH access on a later screen, but a password is still needed for sudo.

Votre nom :

Your servers name:
The name it uses when it talks to other computers.

Choisir un nom d'utilisateur :

Choisir un mot de passe :

Confirmer votre mot de passe:

Laisser sur « Skip for now » et « Done »

Upgrade to Ubuntu Pro

Upgrade this machine to Ubuntu Pro for security updates on a much wider range of packages, until 2034. Assists with FIPS, STIG, HIPAA and other compliance or hardening requirements.

[\[About Ubuntu Pro ► \]](#)

☐ Enable Ubuntu Pro

☒ Skip for now

You can always enable Ubuntu Pro later using the 'pro attach' command.

Sélectionner « Install OpenSSH server »

SSH configuration

You can choose to install the OpenSSH server package to enable secure remote access to your server.


☒ Install OpenSSH server

☒ Allow password authentication over SSH


[\[Import SSH key ► \]](#)

AUTHORIZED KEYS

No authorized key



Ne rien sélectionner et « Done »



On a lancer l'installation attendre la fin et vérifier s'il y a des erreurs

```
configuring partition: partition-2
configuring lvm_volgroup: lvm_volgroup-0
configuring lvm_partition: lvm_partition-0
configuring format: format-1
configuring mount: mount-1
configuring mount: mount-0
executing curtin install extract step
curtin command install
writing install sources to disk
running 'curtin extract'
curtin command extract
acquiring and extracting image from cp:///tmp/tmpby8rkhd/mount
configuring keyboard
curtin command in-target
executing curtin install curthooks step
curtin command install
configuring installed system
running 'curtin curthooks'
curtin command curthooks
configuring apt configuring apt
installing missing packages
Installing packages on target system: ['grub-pc']
configuring iscsi service
configuring raid (mdadm) service
configuring NVMe over TCP
installing kernel
setting up swap
apply networking config
writing etc/fstab
configuring multipath
updating packages on target system
configuring pollinate user-agent on target
updating initramfs configuration
configuring target system bootloader
installing grub to target devices
copying metadata from /cdrom
final system configuration
curtin command in-target
calculating extra packages to install
installing openssh-server
retrieving openssh-server \
curtin command system-install /
```

Une fois terminer Faite « reboot Now »

```
running 'curtin extract'
  curtin command extract
    acquiring and extracting image from cp:///tmp/tmpby8rkhd/mount
configuring keyboard
  curtin command in-target
executing curtin install curthooks step
curtin command install
  configuring installed system
    running 'curtin curthooks'
      curtin command curthooks
        configuring apt configuring apt
        installing missing packages
        installing packages on target system: ['grub-pc']
        configuring iscsi service
        configuring raid (mdadm) service
        configuring NVMe over TCP
        installing kernel
        setting up swap
        apply networking config
        writing etc/fstab
        configuring multipath
        updating packages on target system
        configuring pollinate user-agent on target
        updating initramfs configuration
        configuring target system bootloader
        installing grub to target devices
        copying metadata from /cdrom
final system configuration
  curtin command in-target
    calculating extra packages to install
    installing openssh-server
    retrieving openssh-server
    curtin command system-install
    unpacking openssh-server
    curtin command system-install
    configuring cloud-init
    downloading and installing security updates
    curtin command in-target
    restoring apt configuration
    curtin command in-target
subiquity/Late/run:
```

[View full log]

[Reboot Now]

Faite entrer

```
[FAILED] Failed unmounting cdrom.mount - /cdrom.
Please remove the installation medium, then press ENTER:
[FAILED] Failed unmounting cdrom.mount - /cdrom.
```

Fini

On passe a l'installation de GLPI

Taper les lignes de commande ci-dessous

Procédure GLPI installation

1. Mise à jour du système

```
sudo apt update && sudo apt upgrade -y
```

2. Installation des composants

```
sudo apt install -y apache2 mariadb-server php php-  
{cli,common,curl,gd,imap,ldap,mysql,xml,mbstring,intl,zip,bz2,apcu}  
libapache2-mod-php unzip wget
```

3. Activation des services

```
sudo systemctl enable apache2
```

```
sudo systemctl start apache2
```

```
sudo systemctl enable mariadb
```

```
sudo systemctl start mariadb
```

4. Pare-feu

```
sudo ufw allow 80
```

```
sudo ufw allow 443
```

```
sudo ufw enable
```

5. Sécurisation MariaDB

```
sudo mysql_secure_installation
```

6. Base de données

```
sudo mysql -u root -p
```

```
CREATE DATABASE glpidb CHARACTER SET utf8mb4 COLLATE  
utf8mb4_unicode_ci;
```

```
CREATE USER 'glpi'@'localhost' IDENTIFIED BY 'MotDePasseFort123!';
```

```
GRANT ALL PRIVILEGES ON glpidb.* TO 'glpi'@'localhost';
```

```
FLUSH PRIVILEGES;
```

```
EXIT;
```

Dans la commande du dessus modifier « Mot DePasseFort123 » pour
mettre le MDP de votre choix

7. Installation GLPI

```
cd /var/www/
```

```
sudo wget https://github.com/glpi-project/glpi/releases/latest/download/glpi.tgz
```

```
sudo tar -xvzf glpi.tgz
```

```
sudo mv glpi html/
```

6. Config Apache

```
sudo nano /etc/apache2/sites-available/glpi.conf
```

```
<VirtualHost *:80>
```

```
    ServerName glpi.local
```

```
    DocumentRoot /var/www/html/glpi/public
```

```
<Directory /var/www/html/glpi/public>
```

```
    Require all granted
```

```
    AllowOverride All
```

```
</Directory>
```

```
</VirtualHost>
```

8. Permissions

```
sudo chown -R www-data:www-data /var/www/html/glpi
```

```
sudo chmod -R 755 /var/www/html/glpi
```

9. Configuration Apache

```
sudo nano /etc/apache2/sites-available/glpi.conf
```

```
<VirtualHost *:80>
```

```
    ServerName glpi.local
```

```
    DocumentRoot /var/www/html/glpi/public
```

```
    <Directory /var/www/html/glpi/public>
```

```
        Require all granted
```

```
        AllowOverride All
```

```
    </Directory>
```

```
</VirtualHost>
```

10. Activation site

```
sudo a2dissite 000-default.conf
```

```
sudo a2ensite glpi.conf
```

```
sudo a2enmod rewrite
```

```
sudo systemctl restart apache2
```

11. Accès

http://IP_DU_SERVEUR/glpi donc ici sa seras


<http://192.168.17.3/glpi>

Utilisation GLPI

Se connecter avec l'adresse : 192.168.17.3 /glpi

Il faut sélectionner la langue, acceptez la licence et vérifiez les prérequis et configurer les bases de données.


Mettre son ID ET MDP



The screenshot shows the GLPI login interface. At the top center is the GLPI logo. Below it is a white box titled "Connexion à votre compte". Inside this box, there are three input fields: "Identifiant" with the value "glpi", "Mot de passe" with masked characters "...." and a toggle icon, and "Source de connexion" with a dropdown menu showing "Base interne GLPI". Below these fields is a checked checkbox labeled "Se souvenir de moi" and a yellow "Se connecter" button. At the bottom of the page, there is a small copyright notice: "GLPI Copyright (C) 2015-2025 Teclib' and contributors".

On va lier le LDAP a AD1

Configuration>Authentification>Annuaire LDAP



Remplissez les informations de connexion LDAP, y compris le serveur, le BaseDN, DN du compte, Champ de l'identifiant, champ de synchronisation. :

- Nom : SRV-AD1 •

Serveur par défaut : Oui •

Actif : Oui

- Serveur : ldap://192.168.17.1

- Port : par default (389)

- Filtre de connexion :

(&(objectClass=user)(objectCategory=person)(!(userAccountControl:1.2.840.113556.1.4.803:=2)))

BaseDN : DC=carnoux,DC=local

Utiliser bind : Oui

DN du compte : [Administrateur@carnoux.local](#)

Mot de passe du compte : Mot de passe du compte

Champ de l'identifiant : samaccountname

Champ de synchronisation : objectguid

GLPI

192.168.17.3/front/authldap.form.php?id=2

Accueil / Configuration / Authentification / Annuaire LDAP

Rechercher

Super-Admin
Entité racine (Arborescence)

Annuaire LDAP - SRV-AD1EXE - ID 2

Annuaire LDAP

- Tester
- Utilisateurs
- Groupes
- Informations avancées
- Réplicats
- Historique
- Tous

Nom: SRV-AD1EXE

Serveur par défaut: Non

Activé: Oui

Serveur: ldap://192.168.17.1

Port (par défaut 389): 389

Commentaires:

Filtre de connexion: (&(objectClass=user)(objectCategory=person)(!(userAccountControl:1.2.840.113556.1.4.803:=2)))

BaseDN: DC=carnoux,DC=local

Utiliser bind: Oui

DN du compte (pour les connexions non anonymes): CN=Administrateur,CN=Users,DC=carnoux,DC=local

Mot de passe du compte (pour les connexions non anonymes):

Effacer

Champ de l'identifiant: samaccountname

Champ de synchronisation: objectguid

Il faut tester si tout vert c'est bon

Annuaire LDAP - SRV-AD1EXE - ID 2

Actions 1/1

Annuaire LDAP

Tester

Utilisateurs

Groupes

Informations avancées

Réplicats

Historique

Tous

Test LDAP Serveur : SRV-AD1EXE

- 1 Flux TCP
Connexion à 192.168.17.1 sur le port 636 réussie
- 2 Base DN
Base DN "DC=carnoux,DC=local" configurée
- 3 LDAP URI
Vérification de l'URI LDAP réussie
- 4 Connexion Bind
Authentification réussie
- 5 Chercher (50 premiers résultats)
Recherche réussie (15 entrées trouvées)

Se déconnecter du compte super admin

Puis changer la source de connexion en « srv-AD1 »



Connexion à votre compte

Identifiant

Mot de passe

Source de connexion

Se connecter

GLPI Copyright (C) 2015-2025 Teclib' and contributors

Puis se connecter avec un User qu'on a créé sur l'AD

ici note User est « Flavinho »

Connexion à votre compte

Identifiant

Mot de passe

Source de connexion

☒ Se souvenir de moi

Se connecter

Puis tester d'envoyer un ticket

Fin

