TESTING SANITIZERS

THROUGHOUT THE DAY

SUPPLIES:



KAY® SolidSense™ Sanitizer and Quat Test Strips (for 3-Compartment Sink Sanitizer Testing)



KAY-5® Sanitizer/Cleaner and Chlorine Test Strips (for Clean Towel Bucket Sanitizer Testing and Low Temp Machine Warewash Sanitizer Testing)



KAY® Rapid Multi Surface Disinfectant Cleaner Solution and KAY® Rapid MSD Cleaner Test Strips


Other supplies needed:
Paper Towel
Container for Sanitizer Solution



ECOLAB® Dishwasher Temperature Labels (available through Ecolab Food Safety Solutions)


IMPORTANT: Sanitizer Solutions must be at the correct concentration to work effectively. Concentration levels should be tested every time a fresh Solution is made. Concentration of SolidSense Sanitizer Solution should be 200 ppm, KAY-5 Sanitizer/Cleaner Solution should be 100 ppm when freshly prepared. Rapid Multi Surface Disinfectant Cleaner Solution should be 6oz/gal and warewash sanitizer should be 100ppm.

TESTING SOLIDSENSE (QUAT) SANITIZER SOLUTION AT THE 3-COMPARTMENT SINK



1. Take a small sample of SolidSense Sanitizer Solution from 3rd sink compartment; let cool to **room temperature** (65-75°F); let foam dissipate
   NOTE: Test Strips require temperature to be approximately 75°F; **hot** Solutions will give false readings
2. Hold Quat Test Strip in Sanitizer Solution for 10 seconds; do not shake
3. Compare to color chart immediately after 10 seconds
4. Choose color on chart that most closely matches color of Quat Test Strip
   NOTE: If reading is less than 200 ppm, empty and refill sink with fresh Solution; test again
5. Check Sanitizer Solution concentration every time a new sanitizer sink is made

TESTING KAY-5® SANITIZER/CLEANER (CHLORINE) SOLUTION IN CLEAN TOWEL BUCKETS



1. Sanitizer Solution should be **lukewarm** (85-105°F)
2. Dip Chlorine Test Strip into Sanitizer Solution and quickly remove
3. Blot Chlorine Test Strip immediately with a paper towel
4. Compare Strip to color chart immediately
5. Choose color on chart that most closely matches color of Chlorine Test Strip
   NOTE: If reading is less than 50 ppm, prepare a fresh Solution and test again; Solution in towel bucket should be checked every 2 hours at a minimum

TEST STRIP GUIDE

Sanitizer Solution	PPM
SolidSense Solution	200 ppm
KAY-5 Solution	100 ppm
Rapid MSDC Solution	6 oz/gal

IMPORTANT: For all Sanitizer Solutions, when multiple Solutions are prepared and sanitizer concentration consistently reads higher or lower than required, please contact Ecolab Customer Service for assistance at (800) 529-5458.

ECOLAB®
Kay Chemical Company
8300 Capital Drive
Greensboro, NC 27409-9790, USA


CUSTOMER SERVICE 800.529.5458

42559/08 MCD US 42559/8008/1025 ©2025 Ecolab USA Inc. All rights reserved.

TESTING SANITIZERS (CONTINUED)

THROUGHOUT THE DAY

LOW TEMPERATURE WAREWASH SANITIZER TESTING




- After completion of first cycle each day, check chlorine sanitizer concentration with Chlorine Test Strips
- After cycle is complete, open door and touch a test strip to any wet surface inside the machine

- Blot Chlorine Test Strip immediately with a paper towel

- Compare Test Strip to color chart immediately
- Choose color on chart that most closely matches color of Chlorine Test Strip

NOTE: Sanitizer Solution must be at least 50 ppm

TESTING RAPID MULTI SURFACE DISINFECTANT CLEANER SOLUTION



- Take a small sample of Rapid MSDC Solution from bottle fill station
- Dip one Rapid MSD Cleaner Test Strip into Rapid MSDC Solution and quickly remove


- Blot Rapid MSD Cleaner Test Strip immediately with a paper towel

- Compare Strip to color chart immediately
- Choose color on chart that most closely matches color of the Rapid MSD Cleaner Test Strip
- If concentration correctly reads 6 oz/gal, dispense product into Rapid MSDC Solution spray bottle and begin using
- Check Rapid MSDC Solution concentration levels upon refilling a spray bottle or at least every 7 days

IMPORTANT: Testing of Rapid MSDC Solution may be required by select health departments. Check your local regulations to determine if this is needed in your area.

NOTE: If reading is greater or less than 6 oz/gal, empty and refill sample container with fresh Solution and test again; if problem persists, contact Ecolab Customer Service at 800.529.5458

HIGH TEMPERATURE WAREWASH TEMPERATURE TESTING



- Place an adhesive label onto a ware
- Run ware through the warewash machine

- After cycle is complete, check label
- It turns from white to black when it reaches the proper temperature of 160 °F as required by the 2017 FDA Food Code

NOTE: This measures ware surface temperature, not final rinse temperature

ECOLAB®
Kay Chemical Company
8300 Capital Drive
Greensboro, NC 27409-9790, USA

CUSTOMER SERVICE 800.529.5458

42559.08 MCD US 42559/8008/1025 ©2025 Ecolab USA Inc. All rights reserved.