# **Apache HTTP Server Version 2.4**

# **Apache Module mod macro**

**Description:** Provides macros within apache httpd runtime configuration files

Status: Base

**Module Identifier:** macro\_module **Source File:** mod\_macro.c

**Compatibility:** Available in httpd 2.4.5 and later

#### **Summary**

Provides macros within Apache httpd runtime configuration files, to ease the process of creating numerous similar configuration blocks. When the server starts up, the macros are expanded using the provided parameters, and the result is processed as along with the rest of the configuration file.

# Usage

Macros are defined using <Macro> blocks, which contain the portion of your configuration that needs to be repeated, complete with variables for those parts that will need to be substituted.

For example, you might use a macro to define a <VirtualHost> block, in order to define multiple similar virtual hosts:

```
<Macro VHost $name $domain>
<VirtualHost *:80>
    ServerName $domain
    ServerAlias www.$domain

DocumentRoot "/var/www/vhosts/$name"
    ErrorLog "/var/log/httpd/$name.error_log"
    CustomLog "/var/log/httpd/$name.access_log" combined
</VirtualHost>
</Macro>
```

Macro names are case-insensitive, like httpd configuration directives. However, variable names are case sensitive.

You would then invoke this macro several times to create virtual hosts:

```
Use VHost example example.com
Use VHost myhost hostname.org
Use VHost apache apache.org
UndefMacro VHost
```

At server startup time, each of these USE invocations would be expanded into a full virtualhost, as described by the <Macro> definition.

The UndefMacro directive is used so that later macros using the same variable names don't result in conflicting definitions.

A more elaborate version of this example may be seen below in the Examples section.

### Tips

Parameter names should begin with a sigil such as \$, %, or @, so that they are clearly identifiable, and also in order to help deal with interactions with other directives, such as the core Define directive. Failure to do so will result in a warning. Nevertheless, you are encouraged to have a good knowledge of your entire server configuration in order to avoid reusing the same variables in different scopes, which can cause confusion.

Parameters prefixed with either \$ or % are not escaped. Parameters prefixes with @ are escaped in quotes.

Avoid using a parameter which contains another parameter as a prefix, (For example, \$win and \$winter) as this may cause confusion at expression evaluation time. In the event of such confusion, the longest possible parameter name is used.

If you want to use a value within another string, it is useful to surround the parameter in braces, to avoid confusion:

```
<Macro DocRoot ${docroot}>
   DocumentRoot "/var/www/${docroot}/htdocs"
</Macro>
```

### **Examples**

#### **Virtual Host Definition**

A common usage of mod\_macro is for the creation of dynamically-generated virtual hosts.

#### Removal of a macro definition

It's recommended that you undefine a macro once you've used it. This avoids confusion in a complex configuration file where there may be conflicts in variable names.

#### <Macro> Directive

```
Description:Define a configuration file macroSyntax:<Macro name [par1 .. parN]> ... </Macro>Context:server config, virtual host, directoryStatus:BaseModule:mod_macro
```

The <Macro> directive controls the definition of a macro within the server runtime configuration files. The first argument is the name of the macro. Other arguments are parameters to the macro. It is good practice to prefix parameter names with any of '\$%@', and not macro names with such characters.

```
<Macro LocalAccessPolicy>
    Require ip 10.2.16.0/24
</Macro>

<Macro RestrictedAccessPolicy $ipnumbers>
    Require ip $ipnumbers
</Macro>
```

# **UndefMacro Directive**

Description: Undefine a macro
 Syntax: UndefMacro name
 Context: server config, virtual host, directory
 Status: Base
 Module: mod\_macro

The UndefMacro directive undefines a macro which has been defined before hand.

```
UndefMacro LocalAccessPolicy
UndefMacro RestrictedAccessPolicy
```

# **Use Directive**

Description:Use a macroSyntax:Use name [value1 ... valueN]Context:server config, virtual host, directoryStatus:BaseModule:mod\_macro

The USE directive controls the use of a macro. The specified macro is expanded. It must be given the same number of arguments as in the macro definition. The provided values are associated to their corresponding initial parameters and are substituted before processing.

```
Use LocalAccessPolicy
...
Use RestrictedAccessPolicy "192.54.172.0/24 192.54.148.0/24"
```

is equivalent, with the macros defined above, to:

```
Require ip 10.2.16.0/24
...
Require ip 192.54.172.0/24 192.54.148.0/24
```

#### **Comments**

# **Notice:**

This is not a Q&A section. Comments placed here should be pointed towards suggestions on improving the documentation or server, and may be removed by our moderators if they are either implemented or considered invalid/off-topic. Questions on how to manage the Apache HTTP Server should be directed at either our IRC channel, #httpd, on Libera.chat, or sent to our mailing lists.

Copyright 2023 The Apache Software Foundation. Licensed under the Apache License, Version 2.0.