# **Solana Memecoin Trading Bot**

A customizable trading bot for Solana memecoins with social media scanning, token analysis, and automated trading.

# **Key Features**

- Twitter scanning for memecoin discovery
- Token analysis with safety scoring
- Configurable trading parameters
- Dashboard for monitoring performance
- Simulation mode for risk-free testing

# **Quick Start**

#### 1. Set Up Environment

```
# Create and activate a virtual environment
python -m venv venv
source venv/bin/activate # On Windows: venv\Scripts\activate
# Install dependencies
pip install tweepy aiohttp solders solana-py python-dotenv pandas vaderSentiment streamlit plot
```

# 2. Configure API Keys

Create a (.env) file in the project directory:

```
# API Keys

TWITTER_BEARER_TOKEN=your_twitter_bearer_token

SOLANA_RPC_ENDPOINT=https://mainnet.helius-rpc.com/?api-key=your_api_key

WALLET_PRIVATE_KEY=your_wallet_private_key

DEXSCREENER_BASE_URL=https://api.dexscreener.com

JUPITER_QUOTE_API=https://quote-api.jup.ag/v6/quote

JUPITER_SWAP_API=https://quote-api.jup.ag/v6/swap
```

### 3. Run the Database Fix Script (First Time Only)

```
python fix_database.py
```

#### 4. Run the Bot

bash

python main.py

# 5. Run the Dashboard (Optional)

bash

streamlit run dashboard.py

# **Adjusting Trading Parameters**

#### **Option 1: Using the Dashboard**

The dashboard provides an intuitive interface to adjust all trading parameters in real-time:

- 1. Launch the dashboard: (streamlit run dashboard.py)
- 2. Navigate to the Bot Controls section in the sidebar
- 3. Adjust parameters as needed
- 4. Click "Update Trading Parameters" to save changes

# **Option 2: Editing bot\_control.json**

You can manually edit (data/bot\_control.json) to change trading parameters:

```
json
    "running": true,
    "simulation_mode": true,
    "max_investment_per_token": 1.0,
    "take profit target": 15.0,
    "stop_loss_percentage": 0.25,
    "slippage_tolerance": 0.30,
    "MIN_SAFETY_SCORE": 0.0,
    "MIN_VOLUME": 0.0,
    "MIN_LIQUIDITY": 0.0,
    "MIN_MCAP": 0.0,
    "MIN_HOLDERS": 0,
    "MIN_PRICE_CHANGE_1H": 0.0,
    "MIN_PRICE_CHANGE_6H": 0.0,
    "MIN PRICE CHANGE 24H": 0.0
}
```

### **Key Parameters Explained**

### **Core Trading Parameters**

- Simulation Mode: When enabled, trades are simulated without real execution
- Max Investment per Token: Maximum SOL to invest in a single token (default: 1.0 SOL)
- Take Profit Target: Multiplier for take profit (default: 15.0 = 1500% profit)
- **Stop Loss Percentage**: Percentage for stop loss trigger (default: 0.25 = 25%)
- Slippage Tolerance: Maximum allowed slippage percentage (default: 0.30 = 30%)

### **Token Screening Parameters**

- MIN\_SAFETY\_SCORE: Minimum safety score (0-100) for token to be tradable
- MIN VOLUME: Minimum 24-hour trading volume in USD
- MIN\_LIQUIDITY: Minimum liquidity in USD
- MIN MCAP: Minimum market capitalization in USD
- MIN HOLDERS: Minimum number of token holders

### **Price Change Parameters**

- MIN\_PRICE\_CHANGE\_1H: Minimum price change over 1 hour
- MIN\_PRICE\_CHANGE\_6H: Minimum price change over 6 hours

• MIN\_PRICE\_CHANGE\_24H: Minimum price change over 24 hours

# **Starting with Very Lenient Parameters**

For testing, we've set all minimum criteria to 0 to catch all possible tokens. As you refine your strategy, you can gradually increase these values to be more selective.

# **Troubleshooting**

#### **Common Issues**

#### **No Tokens Meeting Criteria**

If you don't see any tokens qualifying for trading, lower the screening parameters:

- Set MIN\_SAFETY\_SCORE to 0
- Set MIN\_VOLUME, MIN\_LIQUIDITY, MIN\_MCAP to 0
- Set MIN\_HOLDERS to 0
- Set all MIN\_PRICE\_CHANGE values to 0

#### **Database Errors**

If you encounter database issues:

```
bash

python fix_database.py --reset
```

#### **API Rate Limiting**

The bot includes automatic rate limiting mechanisms, but if you encounter API rate limit errors, increase the scan interval in config.py.

# **Important Notes**

- Always start in simulation mode
- Monitor the logs for any errors
- Use the dashboard to visualize performance
- The bot is set to a 15x profit target by default

Happy trading! 🚀