Claiming your tokens at mvxvest.io

A short guide for the beneficiaries of a vesting




Someone locked tokens for you in a **vesting**. They unlock over time. You collect what has unlocked **whenever you like**.

Your wallet holds the vesting's **claim key**: an NFT called *Vesting #… claim key*, like the one on the left. Whoever holds it can claim.

Your part takes about a minute. It is the same every time.


1 Open mvxvest.io and connect your wallet

- Go to **mvxvest.io** and press **Connect**. Check the address in your browser: only mvxvest.io.
- Choose how you sign: **xPortal** (scan the code with your phone), the MultiversX **browser extension**, a **Ledger** or the **web wallet**.
- Connect the wallet that holds the claim key. Connecting only shows the site your address; it cannot move anything.



2 Open My vestings

- Press **My vestings** at the top. You see every vesting whose claim key is in your wallet.
- Each card shows what has vested so far, what you already claimed and what you can **claim now**.




3 Claim

- Press **Claim** on one card. **Claim all** collects from every vesting, with one transaction per token.
- The page first checks with the network and shows the most the network fee can be. Then press **Sign in your wallet** and approve in your wallet. A Ledger asks you to confirm each transaction on the device.
- A claim names your own address as the receiver: the key goes to the vesting contract through your own account and the transaction's data names it. xPortal shows your own address and the key, not where the key goes. A copy of the site elsewhere can look the same, so open it only at **mvxvest.io**, from a bookmark or by typing it. A wallet or device that shows the transaction's data shows the contract there in hexadecimal: `0000000000000000000500f882d8136db7846cdb650b16134bb5424da58ddfe614`. Another address in that place means it is not the real site.
- A Ledger shows only the start of the data: ESDTNFTTransfer@, the key's collection, @, the key's number, @01@ and then the contract (right after MultiESDTNFTTransfer@ when one transaction claims several keys). The key's number never starts with 00. What the screen shows of the contract must match the start of the form above. On a Nano S Plus or a Nano X one key's data ends inside the zeros every contract starts with; there the site's address is the check that counts. On any other Ledger a claim shows at least `0000000000000000000500f882d8136db7846c` there; if it does not, do not sign.
- Claiming costs only that small network fee, paid in EGLD. Keep a little EGLD in your wallet: around 0.05 is plenty.

4 Done

- The page tells you what reached your wallet, token by token. The tokens are in your wallet now.
- The claim key comes back to you for the next time. Once everything is claimed it is burned: that vesting is finished.



Good to know

- You can claim as often as you like. Waiting loses nothing.
- Some vestings grow every second; others unlock on set dates. Each vesting's page shows the next release.
- If the creator can cancel your vesting, what has vested by then stays yours.
- Sending the claim key to another wallet gives that wallet the right to claim. Only do it on purpose.
- A token's issuer can freeze it or pause it. If a token is frozen for your wallet, the page warns you and leaves it out of Claim all: a claim of it could send your tokens back to the contract. A key with more to pay stays in your wallet; the key of a last claim is burned. The tokens are safe there and the owners' multisig can send them back by a vote. Ask through an issue at github.com/foxsyai/mvxvest/issues.
- Nobody from mvxvest will ever ask for your secret words or your keys.

---

mvxvest is open source: github.com/foxsyai/mvxvest. It never holds your keys: every transaction is signed in your own wallet. The full guide, for creators too: mvxvest.io/guide.