We use optional cookies to improve your experience on our websites, such as through social media connections, and to display personalized advertising based on your online activity. If you reject optional cookies, only cookies necessary to provide you the services will be used. You may change your selection by clicking "Manage Cookies" at the bottom of the page. Privacy Statement Third-Party Cookies

Accept

Reject

Manage cookies

Microsoft Ignite

Nov 19-22, 2024

Register now >



Learn

Product documentation ∨ Development languages ∨

Sign in

Microsoft 365

Solutions and architecture V Apps and services V Training V Resources V

Free Account

Version

Windows 11 and Windows Server 2022 **PowerShell**

Q Search

Set-InetiPsecivialniviodeCryptoSet

Set-NetIPsecMainModeRule

Set-NetIPsecPhase1AuthSet

Set-NetIPsecPhase2AuthSet

Set-NetIPsecQuickModeCryptoSet

Set-NetIPsecRule

Show-NetFirewallRule

Show-NetIPsecRule

Sync-NetIPsecRule

Update-

NetFirewallDynamicKeywordAddress

Update-NetIPsecRule

- > NetSwitchTeam
- > NetTCPIP
- > NetworkConnectivityStatus
- > NetworkController
- > NetworkControllerDiagnostics
- > NetworkLoadBalancingClusters
- > NetworkSwitchManager
- > NFS
- > NPS
- > PcsvDevice
- > PersistentMemory
- > pki
- > PlatformIdentifier
- > PnpDevice
- > PrintManagement
- > ProcessMitigations
- > Provisioning
- > RDMgmt
- > RemoteAccess

Learn / Windows / PowerShell / NetSecurity /







Set-NetFirewallProfile

Reference

Feedback

Module: NetSecurity

In this article

Syntax

Description

Examples

Parameters

Show 3 more

Configures settings that apply to the per-profile configurations of the Windows Firewall with Advanced Security.

Syntax

PowerShell Copy Set-NetFirewallProfile [-Name] <String[]> [-PolicyStore <String>] [-GPOSession <String>] [-Enabled <GpoBoolean>] [-DefaultInboundAction <Action>] [-DefaultOutboundAction <Action>] [-AllowInboundRules <GpoBoolean>] [-AllowLocalFirewallRules <GpoBoolean>] [-AllowLocalIPsecRules <GpoBoolean>] [-AllowUserApps <GpoBoolean>] [-AllowUserPorts <GpoBoolean>] [-AllowUnicastResponseToMulticast <GpoBoolean>] [-NotifyOnListen <GpoBoolean>] [-EnableStealthModeForIPsec <GpoBoolean>] [-LogFileName <String>] [-LogMaxSizeKilobytes <UInt64>] [-LogAllowed <GpoBoolean>] [-LogBlocked <GpoBoolean>] [-LogIgnored <GpoBoolean>] [-DisabledInterfaceAliases <String[]>] [-CimSession <CimSession[]>] [-ThrottleLimit <Int32>] [-AsJob] [-PassThru] [-WhatIf]

■ Download PDF

```
[-Confirm]
[<CommonParameters>]
```

```
PowerShell
                                                                          Copy
Set-NetFirewallProfile
   [-All]
   [-PolicyStore <String>]
   [-GPOSession <String>]
   [-Enabled <GpoBoolean>]
   [-DefaultInboundAction <Action>]
   [-DefaultOutboundAction <Action>]
   [-AllowInboundRules <GpoBoolean>]
   [-AllowLocalFirewallRules <GpoBoolean>]
   [-AllowLocalIPsecRules <GpoBoolean>]
   [-AllowUserApps <GpoBoolean>]
   [-AllowUserPorts <GpoBoolean>]
   [-AllowUnicastResponseToMulticast <GpoBoolean>]
   [-NotifyOnListen <GpoBoolean>]
   [-EnableStealthModeForIPsec <GpoBoolean>]
   [-LogFileName <String>]
   [-LogMaxSizeKilobytes <UInt64>]
   [-LogAllowed <GpoBoolean>]
   [-LogBlocked <GpoBoolean>]
   [-LogIgnored <GpoBoolean>]
   [-DisabledInterfaceAliases <String[]>]
   [-CimSession <CimSession[]>]
   [-ThrottleLimit <Int32>]
   [-AsJob]
   [-PassThru]
   [-WhatIf]
   [-Confirm]
   [<CommonParameters>]
```

```
PowerShell
                                                                          Copy
Set-NetFirewallProfile
   -InputObject <CimInstance[]>
   [-Enabled <GpoBoolean>]
   [-DefaultInboundAction <Action>]
   [-DefaultOutboundAction <Action>]
   [-AllowInboundRules <GpoBoolean>]
   [-AllowLocalFirewallRules <GpoBoolean>]
   [-AllowLocalIPsecRules <GpoBoolean>]
   [-AllowUserApps <GpoBoolean>]
   [-AllowUserPorts <GpoBoolean>]
   [-AllowUnicastResponseToMulticast <GpoBoolean>]
   [-NotifyOnListen <GpoBoolean>]
   [-EnableStealthModeForIPsec <GpoBoolean>]
   [-LogFileName <String>]
   [-LogMaxSizeKilobytes <UInt64>]
   [-LogAllowed <GpoBoolean>]
   [-LogBlocked <GpoBoolean>]
   [-LogIgnored <GpoBoolean>]
   [-DisabledInterfaceAliases <String[]>]
   [-CimSession <CimSession[]>]
   [-ThrottleLimit <Int32>]
   [-AsJob]
   [-PassThru]
   [-WhatIf]
   [-Confirm]
   [<CommonParameters>]
```

Description

The **Set-NetFirewallProfile** cmdlet configures options for the profiles, including domain, public, and private, that are global, or associated with the input rules. This cmdlet displays information that is presented on the Windows Firewall with Advanced Security Properties page, with the tabs for domain, private, and public profiles. This cmdlet configures the states, default actions, and logging properties on a per-profile basis.

Examples

Example 1



This example enables the Windows Firewall on the local computer.

Example 2



This example sets the default inbound and outbound actions, specifies protected network connections, allows notifications to be displayed to the user when a program is blocked from receiving inbound connections. This cmdlet allows unicast response to multi-cast or broadcast network traffic, and specifies logging settings for troubleshooting.

Example 3

```
PowerShell

PS C:\>Set-NetFirewallProfile -Name Domain -DefaultInboundAction Block
```

This example modifies the default inbound action of the domain profile.

Example 4

```
PowerShell

PS C:\>$nfProfile = Get-NetFirewallProfile -Name Private -PolicyStore corp.contc
PS C:\>Set-NetFirewallProfile -AllowUnicastResponseToMulticast True -InputObject
This cmdlet can be run using only the pipeline.
PS C:\>Get-NetFirewallProfile -Name Private -PolicyStore corp.contoso.com\gpo_na
```

This example modifies the private profile associated with a GPO.

Example 5

```
PowerShell

PS C:\>$nfProfile = Get-NetFirewallRule -DisplayName "Unicast Rule" | Get-NetFirewallProfile -AllowUnicastResponseToMulticast True -InputObject

This cmdlet can be run using only the pipeline.

PS C:\>Get-NetFirewallRule -DisplayName "Unicast Rule" | Get-NetFirewallProfile
```

This example modifies the profiles associated with a firewall rule.

Parameters

-A11

Indicates that all of the firewall profiles within the specified policy store are modified.

Expand table

Туре:	SwitchParameter
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-AllowInboundRules

Specifies that the firewall blocks inbound traffic. If this parameter is set to True, then the administrator will be able to create firewall rules which allow unsolicited inbound traffic to be accepted. If this parameter is set to False, then firewall rules will be ignored. The acceptable values for this parameter are: False, True, or NotConfigured.

- True: Inbound firewall rules are allowed. All traffic that does not match a rule will be processed according to the *DefaultInboundAction* parameter value.
- False: All inbound firewall rules are ignored. All inbound traffic will use the
 DefaultInboundAction parameter value. If this parameter is set to False and the
 DefaultInboundAction parameter is set to Block, then the Windows Firewall is placed
 into Shields-Up mode on this profile.
- NotConfigured: Valid only when configuring a Group Policy Object (GPO). This
 parameter removes the setting from the GPO, which results in the policy not changing
 the value on the computer when the policy is applied.

The default setting when managing a computer is True. When managing a GPO, the default setting is NotConfigured.

Expand table

Туре:	GpoBoolean
Accepted values:	False, True, NotConfigured
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-AllowLocalFirewallRules

Specifies that the local firewall rules should be merged into the effective policy along with Group Policy settings. The acceptable values for this parameter are: False, True, or NotConfigured.

- True: The firewall rules defined by the local administrator are merged with firewall rules from GPOs and are applied to the computer.
- False: The firewall rules defined by the local administrator are ignored, and only firewall rules from GPOs are applied to the computer.
- NotConfigured: Valid only when configuring a Group Policy Object (GPO). This
 parameter removes the setting from the GPO, which results in the policy not changing

the value on the computer when the policy is applied.

The default setting when managing a computer is True. When managing a GPO, the default setting is NotConfigured.

Α.	Francis al	م امامه
J	Expand	table

Туре:	GpoBoolean
Accepted values:	False, True, NotConfigured
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-AllowLocalIPsecRules

Specifies that the local IPsec rules should be merged into the effective policy along with Group Policy settings. The acceptable values for this parameter are: False, True, or NotConfigured.

- True: The IPsec rules defined by the local administrator are merged with IPsec rules from GPOs and are applied to the computer.
- False: The IPsec rules defined by the local administrator are ignored, and only IPsec rules from GPOs are applied to the computer.
- NotConfigured: Valid only when configuring a Group Policy Object (GPO). This
 parameter removes the setting from the GPO, which results in the policy not changing
 the value on the computer when the policy is applied.

The default setting when managing a computer is True. When managing a GPO, the default setting is NotConfigured.

Expand table

Туре:	GpoBoolean
Accepted values:	False, True, NotConfigured
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-AllowUnicastResponseToMulticast

Allows unicast responses to multi-cast traffic. The acceptable values for this parameter are: False, True, or NotConfigured.

- True: The computer can receive unicast responses to outgoing multi-cast or broadcast messages.
- False: The computer discards unicast responses to outgoing multi-cast or broadcast messages.
- NotConfigured: Valid only when configuring a Group Policy Object (GPO). This parameter removes the setting from the GPO, which results in the policy not changing the value on the computer when the policy is applied.

The default setting when managing a computer is True. When managing a GPO, the default setting is NotConfigured.

Expand table

Туре:	GpoBoolean
Accepted values:	False, True, NotConfigured
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-AllowUserApps

Determines how the Windows XP policy is applied to the newer Windows Firewall. Defines how to use the policy merge field for older operating systems. Specifies that traffic from local user applications is allowed through the firewall. The acceptable values for this parameter are: False, True, or NotConfigured.

- True: The traffic from local user applications is allowed.
- False: The traffic from local user applications is blocked.
- NotConfigured: Valid only when Windows PowerShell is configuring a GPO by using this cmdlet. This parameter removes the setting from the GPO, resulting in the policy not changing the value of the computer when the policy is applied.

Expand table

Torran	Coopposition
Type:	GpoBoolean
Accepted values:	False, True, NotConfigured
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-AllowUserPorts

Determines how the Windows XP policy is applied to the newer Windows Firewall. Defines how to use the policy merge field for older operating systems. Specifies that traffic is allowed through local user ports. The acceptable values for this parameter are: False, True, or NotConfigured.

- True: The traffic through local user ports is allowed.
- False: The traffic through local user ports is blocked.
- NotConfigured: Valid only when Windows PowerShell is configuring a GPO by using this cmdlet. This parameter removes the setting from the GPO, resulting in the policy not changing the value of the computer when the policy is applied.

Туре:	GpoBoolean
Accepted values:	False, True, NotConfigured

Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-AsJob

Runs the cmdlet as a background job. Use this parameter to run commands that take a long time to complete.

Expand table

Туре:	SwitchParameter
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-CimSession

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a New-CimSession \checkmark or Get-CimSession \checkmark cmdlet. The default is the current session on the local computer.

Expand table

Туре:	CimSession[]
Aliases:	Session
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-Confirm

Prompts you for confirmation before running the cmdlet.

Туре:	SwitchParameter
1	
Aliases:	cf
Position:	Named
Default value:	False
Required:	False
Accept pipeline input:	False

Accept wildcard characters:	False
-----------------------------	-------

-DefaultInboundAction

Specifies how to filter inbound traffic. The acceptable values for this parameter are: NotConfigured, Allow, or Block.

- Block: Blocks inbound network traffic that does not match an inbound rule.
- Allow: Allows all inbound network traffic, whether or not it matches an inbound rule.
- NotConfigured: Valid only when configuring a Group Policy Object (GPO). This
 parameter removes the setting from the GPO, which results in the policy not changing
 the value on the computer when the policy is applied.

The default setting when managing a computer is Block. When managing a GPO, the default setting is NotConfigured.

r	٦.	_			
Ċ.	ر	EX	oand	i ta	ıble

Туре:	Action
Accepted values:	NotConfigured, Allow, Block
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-DefaultOutboundAction

Specifies how to filter outbound traffic. The acceptable values for this parameter are: NotConfigured, Allow, or Block.

- Block: Blocks outbound network traffic that does not match an outbound rule.
- Allow: Allows all outbound network traffic, whether or not it matches an outbound rule.
- NotConfigured: Valid only when configuring a Group Policy Object (GPO). This
 parameter removes the setting from the GPO, which results in the policy not changing
 the value on the computer when the policy is applied.

The default setting when managing a computer is Allow. When managing a GPO, the default setting is NotConfigured.

Expand table

Туре:	Action
Accepted values:	NotConfigured, Allow, Block
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-DisabledInterfaceAliases

Specifies a list of interfaces on which firewall settings are excluded.

Accept wildcard characters:

	C Expand table
Туре:	String[]
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False

-Enabled

Allows unicast responses to multi-cast traffic. The acceptable values for this parameter are: False, True, or NotConfigured.

- True: Enables Windows Firewall with Advanced Security when the specified profile is active.
- False: Disables Windows Firewall with Advanced Security when the specified profile is active.
- NotConfigured: Valid only when configuring a Group Policy Object (GPO). This
 parameter removes the setting from the GPO, which results in the policy not changing
 the value on the computer when the policy is applied.

The default setting when managing a computer is True. When managing a GPO, the default setting is NotConfigured.

Expand table

False

Туре:	GpoBoolean
Accepted values:	False, True, NotConfigured
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-EnableStealthModeForIPsec

Enables stealth mode for IPsec traffic. Stealth mode is a mechanism in Windows Firewall that helps prevent malicious users from discovering information about network computers and the services that are run. Stealth mode blocks outgoing ICMP unreachable and TCP reset messages for a port when no application is listening on that port. The acceptable values for this parameter are: False, True, or NotConfigured.

Туре:	GpoBoolean
Accepted values:	False, True, NotConfigured
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False

Accept wildcard characters:	False

-GPOSession

Specifies the network GPO from which to retrieve the rules to be modified. This parameter is used in the same way as the *PolicyStore* parameter. When modifying GPOs in Windows PowerShell®, each change to a GPO requires the entire GPO to be loaded, modified, and saved back. On a busy Domain Controller (DC), this can be a slow and resource-heavy operation. A GPO Session loads a domain GPO onto the local computer and makes all changes in a batch, before saving it back. This reduces the load on the DC and speeds up the Windows PowerShell cmdlets. To load a GPO Session, use the Open-NetGPO cmdlet. To save a GPO Session, use the Save-NetGPO cmdlet.

Expand table

Туре:	String
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-InputObject

Specifies the input object that is used in a pipeline command.

Expand table

Type:	CimInstance[]
Position:	Named
Default value:	None
Required:	True
Accept pipeline input:	True
Accept wildcard characters:	False

-LogAllowed

Specifies how to log the allowed packets in the location specified by the *LogFileName* parameter. The acceptable values for this parameter are: False, True, or NotConfigured.

- True: Windows writes an entry to the log whenever an incoming or outgoing connection is allowed by the policy.
- False: No logging for allowed connections.
- NotConfigured: Valid only when configuring a Group Policy Object (GPO). This parameter removes the setting from the GPO, which results in the policy not changing the value on the computer when the policy is applied.

The default setting when managing a computer is False. When managing a GPO, the default setting is NotConfigured.

Туре:		GpoBoolean
Accepted	values:	False, True, NotConfigured

Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-LogBlocked

Specifies how to log the dropped packets in the location specified by the *LogFileName* parameter. The acceptable values for this parameter are: False, True, or NotConfigured.

- True: Windows writes an entry to the log whenever an incoming or outgoing connection is prevented by policy.
- False: No logging for dropped connections.
- NotConfigured: Valid only when configuring a Group Policy Object (GPO). This
 parameter removes the setting from the GPO, which results in the policy not changing
 the value on the computer when the policy is applied.

The default setting when managing a computer is False. When managing a GPO, the default setting is NotConfigured.

Expand table

Туре:	GpoBoolean
Accepted values:	False, True, NotConfigured
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-LogFileName

Specifies the path and filename of the file to which Windows Server 2012 writes log entries. The default setting for managing a computer is

%windir%\system32\logfiles\firewall\pfirewall.log. When managing a GPO, the default setting is NotConfigured. To grant write permissions for the log folder to the Windows Firewall service.

- Locate the folder that was specified for the logging file, right-click the file, and then click Properties.
- Select the Security tab, and then click Edit.
- Click Add, in Enter the object names to select, type NT SERVICE\mpssvc, and then click OK.
- In the Permissions dialog box, verify that MpsSvc has Write access, and then click OK.

Туре:	String
Position:	Named
Default value:	None
Required:	False

Accept pipeline input:	False
Accept wildcard characters:	False

-LogIgnored

Specifies how to log the ignored packets in the location specified by the *LogFileName* parameter. The acceptable values for this parameter are: False, True, or NotConfigured.

- True: Windows writes an entry to the log whenever an incoming or outgoing connection is ignored by policy.
- False: No logging for ignored connections.
- NotConfigured: Valid only when configuring a Group Policy Object (GPO). This
 parameter removes the setting from the GPO, which results in the policy not changing
 the value on the computer when the policy is applied.

The default setting when managing a computer is False. When managing a GPO, the default setting is NotConfigured.

רח	Evnand	+able
L J	Expand	lable

Туре:	GpoBoolean
Accepted values:	False, True, NotConfigured
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-LogMaxSizeKilobytes

Specifies the maximum file size of the log, in kilobytes. The acceptable values for this parameter are: 1 through 32767 This parameter specifies in kilobytes the maximum file size of the log in the location specified by the *LogFileName* parameter.

NotConfigured: Valid only when configuring a Group Policy Object (GPO). This
parameter removes the setting from the GPO, which results in the policy not changing
the value on the computer when the policy is applied. The default setting when
managing a computer is 4096. When managing a GPO, the default setting is
NotConfigured. This parameter values is case sensitive and NotConfigured can only
be specified using dot-notation.

Expand table

Туре:	UInt64
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-Name

Specifies the network firewall profile objects by profile type to modify. Specifies the profile type. The acceptable values for this parameter are: Domain, Public, or Private. This

parameter accepts multiple values, separated by commas.

Expand table

Type:	String[]
Aliases:	Profile
Position:	0
Default value:	None
Required:	True
Accept pipeline input:	False
Accept wildcard characters:	False

-NotifyOnListen

Allows the notification of listening for inbound connections by a service. The acceptable values for this parameter are: False, True, or NotConfigured.

- True: Windows notifies the user whenever a program or service starts listening for inbound connections.
- False: Windows does not notify the user whenever a program or service starts listening for inbound connections.
- NotConfigured: Valid only when configuring a Group Policy Object (GPO). This
 parameter removes the setting from the GPO, which results in the policy not changing
 the value on the computer when the policy is applied. If managing a computer
 running firstref_vista and firstref_client_7, then the default value is True. If managing a
 computer running firstref_longhorn and firstref_server_7, then the default value is
 False. If managing a computer running Windows Server® 2012, then the default
 value is True. When managing a GPO, the default setting for all operating systems is
 NotConfigured.

Expand table

Туре:	GpoBoolean
Accepted values:	False, True, NotConfigured
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-PassThru

Returns an object representing the item with which you are working. By default, this cmdlet does not generate any output.

Туре:	SwitchParameter
Position:	Named
Default value:	None
Required:	False

Accept pipeline input:	False
Accept wildcard characters:	False

-PolicyStore

Specifies the policy store from which to retrieve the rules to be modified. A policy store is a container for firewall and IPsec policy. The acceptable values for this parameter are:

PersistentStore: Sometimes called static rules, this store contains the persistent policy
for the local computer. This policy is not from GPOs, and has been created manually
or programmatically (during application installation) on the computer. Rules created
in this store are attached to the ActiveStore and activated on the computer
immediately.

ActiveStore: This store contains the currently active policy, which is the sum of all

policy stores that apply to the computer. This is the resultant set of policy (RSOP) for the local computer (the sum of all GPOs that apply to the computer), and the local stores (the PersistentStore, the static Windows service hardening (WSH), and the configurable WSH). ---- GPOs are also policy stores. Computer GPOs can be specified as follows. ----- -PolicyStore hostname. ---- Active Directory GPOs can be specified as follows. ----- -PolicyStore

domain.fqdn.com\GPO_Friendly_Namedomain.fqdn.comGPO_Friendly_Name. -----Such as the following. ------ -PolicyStore localhost ------ -PolicyStore

corp.contoso.com\FirewallPolicy ---- Active Directory GPOs can be created using

 RSOP: This read-only store contains the sum of all GPOs applied to the local computer.

the New-GPO cmdlet or the Group Policy Management Console.

- SystemDefaults: This read-only store contains the default state of firewall rules that ship with Windows Server 2012.
- StaticServiceStore: This read-only store contains all the service restrictions that ship with Windows Server 2012. Optional and product-dependent features are considered part of Windows Server 2012 for the purposes of WFAS.
- ConfigurableServiceStore: This read-write store contains all the service restrictions
 that are added for third-party services. In addition, network isolation rules that are
 created for Windows Store application containers will appear in this policy store. The
 default value is PersistentStore. The Set-NetFirewallRule cmdlet cannot be used to add
 an object to a policy store. An object can only be added to a policy store at creation
 time with the Copy-NetFirewallRule cmdlet or with the New-NetFirewallRule cmdlet.

רח	F	4-1-1-
	Expand	table

Туре:	String
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-ThrottleLimit

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of 0 is entered, then Windows PowerShell® calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are running on the computer. The throttle limit applies only to the current cmdlet, not to the session or to the computer.

Expand table

Туре:	Int32
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-WhatIf

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Expand table

Туре:	SwitchParameter
Aliases:	wi
Position:	Named
Default value:	False
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

Inputs

CimInstance[]

The Microsoft.Management.Infrastructure.CimInstance object is a wrapper class that displays Windows Management Instrumentation (WMI) objects. The path after the pound sign (#) provides the namespace and class name for the underlying WMI object.

Outputs

CimInstance[]

The Microsoft.Management.Infrastructure.CimInstance object is a wrapper class that displays Windows Management Instrumentation (WMI) objects. The path after the pound sign (#) provides the namespace and class name for the underlying WMI object.

Related Links

- Copy-NetlPsecRule
- Get-NetFirewallProfile
- New-NetIPsecRule
- Open-NetGPO
- Save-NetGPO
- Set-NetFirewallRule
- Set-NetlPsecRule

Feedback

Provide product feedback ☑

Manage cookies Previous Versions Blog ☑ Contribute Privacy ☑ Terms of Use Trademarks ☑ © Microsoft 2024