Bitbucket Support

Documentation

Knowledge base Resources

V

Q

Log in





Bitbucket Data Center 9.3 (Latest) Documentation

- Get started with Bitbucket Data Center
- Use Bitbucket Data Center

Administer Bitbucket Data Center

Users and groups

Advanced repository management

> External user directories

Global permissions

Setting up your mail server

- Integrate with Atlassian applications
- Connect Bitbucket to an external database

Migrating Bitbucket
Data Center to another
server

Migrate Bitbucket Server from Windows to Linux

> Run Bitbucket in AWS

Specify the Bitbucket base URL

Configuring the application navigator

Managing apps

View and configure the audit log

Monitor security threats

Update your license key

Configuration properties

Change Bitbucket's context path

Data recovery and backups

Disable HTTP(S) access to Git repositories

- > Mirrors
- Bitbucket Mesh

Atlassian Support / Bit... / Doc... / Administer B...

Cloud

Data Center 9.3 🕶

Enable SSH access to Git repositories

Administrators can enable SSH access to Git repositories in Bitbucket Data Center. This allows users to:

- add their own SSH keys to Bitbucket
- use those SSH keys to secure Git operations between their computer and the Bitbucket instance.

Each user must add their own SSH key pairs to their account to be able to use SSH to access repositories.

Bitbucket supports the following SSH key types:

- ED25519
- RSA2
- ECDSA
- DSA (we recommend you use other key types)
- ED25519-SK
- ECDSA-SK



Performance

Using SSH has performance implications. When users connect to Bitbucket using SSH the encryption of data adds to overall CPU usage. See Scaling Bitbucket Server for more information.



Security

To implement SSH authentication support, Bitbucket bundles a version of the Apache Mina SSHD server. The Bitbucket SSH server is not integrated with the SSH server on the host Bitbucket is running on, and it doesn't consider the users on the host when authenticating Bitbucket users.

To prevent security issues, the embedded SSH server has been locked down to allow execution of a small set of commands for Git hosting. The only commands that are supported are git upload-pack, git receive-pack, git archive-pack and whoami (a custom whoami implemented in Bitbucket, not the whoami command that exists on Linux). It is not possible to open an SSH shell using the embedded server to execute arbitrary commands on the server.

Enabling SSH access

To enable SSH access:

- 1. Go to O > Server settings.
- 2. Select **SSH enabled**.
- 3. Enter values for **SSH port** and **SSH base URL**, according to the information in the sections below.
- 4. Select **Save**.

Ce site utilise des cookies pour améliorer votre expérience de navigation, effectuer des analyses et des recherches, et cibler la publicité. Pour modifier vos préférences, cliquez sur Gérer les préférences. Sinon, cliquez sur Accepter tous les cookies pour indiquer que vous consentez à leur utilisation sur votre appareil. Cliquez sur Rejeter tous les cookies signifie que vous n'acceptez pas que nous utilisions des cookies qui ne sont pas strictement nécessaires sur votre appareil. Avis relatif aux cookies et au suivi d'Atlassian

Gérer les préférences

Rejeter tous les cookies

Accepter tous les cookies



Setting up SSH port forwarding

Signed system commits





Bitbucket Data Center 9.3 (Latest)
Documentation

- Get started with Bitbucket Data Center
- Use Bitbucket Data Center

Administer Bitbucket Data Center

Users and groups

Advanced repository management

External user directoriesGlobal permissions

Setting up your mail server

- Integrate with Atlassian applications
- Connect Bitbucket to an external database

Migrating Bitbucket Data Center to another server

Migrate Bitbucket Server from Windows to Linux

Run Bitbucket in AWS

Specify the Bitbucket base URL

Configuring the application navigator

Managing apps

View and configure the audit log

Monitor security threats

Update your license key

Configuration properties

Change Bitbucket's context path

Data recovery and backups

Disable HTTP(S) access to Git repositories

- > Mirrors
- Bitbucket Mesh



For Data Center installations, a load balancer setup is required for SSH. For instructions on how to install and configure your load balancer, refer to Install Bitbucket Data Center.

SSH base URL

The **SSH base URL** is the base URL with which users can access the SSH push/pull/clone functionality of Bitbucket.

This is the base URL that Bitbucket will use when displaying SSH URLs to users. If you do not set this, it will default to the host that is set in **Bitbucket base URL**, with the port that SSH is listening on. See Specify the Bitbucket base URL.




For example, if the **SSH base URL** is not set and the **Bitbucket base URL** is https://bitbucket.atlassian.com and the SSH port is 7999, the SSH URL for the repository Jira in the project Atlassian will be ssh://git@bitbucket.atlassian.com:7999/ATLASSIAN/jira.git

If you set up port forwarding, you will need to set the **SSH base URL** to the machine and port that is being forwarded to Bitbucket. However, you do not need to specify the port portion of the URL if the default SSH port (port 22) is being forwarded to Bitbucket.



If the **SSH base URL** and **SSH port** configurations are modified in the global Server settings page, the configurations specified in the properties file will no longer be used.



Port forwarding	SSH base URL	Bitbucket base URL
8	Not set	https://bitbucket.atlassian.com
⊘ Port	https://bitbucket.atlassian.com	https://bitbucket.atlassian.com
22 -> 7999		

When running Bitbucket behind a proxy

If you run Bitbucket behind a http proxy such as Apache (e.g. as per our instructions), and if Apache runs on a different host. SSH will not be available on that host. Instead. you will need to set the SSH

Ce site utilise des cookies pour améliorer votre expérience de navigation, effectuer des analyses et des recherches, et cibler la publicité. Pour modifier vos préférences, cliquez sur Gérer les préférences. Sinon, cliquez sur Accepter tous les cookies pour indiquer que vous consentez à leur utilisation sur votre appareil. Cliquez sur Rejeter tous les cookies signifie que vous n'acceptez pas que nous utilisions des cookies qui ne sont pas strictement nécessaires sur votre appareil. Avis relatif aux cookies et au suivi d'Atlassian

Setting up SSH port forwarding

Signed system commits





Bitbucket Data Center 9.3 (Latest)

Documentation

- > Get started with Bitbucket Data Center
- Use Bitbucket Data Center

Center

Users and groups

Advanced repository management

External user directories

Global permissions

Setting up your mail server

- Integrate with Atlassian applications
- Connect Bitbucket to an external database

Migrating Bitbucket Data Center to another server

Migrate Bitbucket Server from Windows to Linux

> Run Bitbucket in AWS

Specify the Bitbucket base URL

Configuring the application navigator

Managing apps

View and configure the audit log

Monitor security threats

Update your license key

Configuration properties

Change Bitbucket's context path

Data recovery and backups


> Disable HTTP(S) access to Git repositories

- Mirrors
- Bitbucket Mesh

If you set up port forwarding, you will need to set the SSH base URL to the proxy machine and port that is being forwarded to Bitbucket However, you do not need to specify the port portion of the URL if the default SSH port (port 22) is being forwarded to Bitbucket.



For example, if you set up port forwarding from your http proxy host, bitbucket.atlassian.com, port 22, to bitbucket.backend.atlassian.com port 7999, set the SSH base URL to ssh://bitbucket.atlassian.com. Then, the SSH URL for the repository Jira in the project Atlassian will be ssh://git@bitbucket.atlassian.com/ATLASSIAN/jira.git



bitbucket.atlassian.com

bitbucket.backend.atlassian.com

Port forwarding	SSH base URL	SSH port	Bitbucket base UF
8	ssh://bitbucket.backend.atlassian.com:7999	7999	https://bitbuc
Port 22->7999	ssh://bitbucket.atlassian.com	7999	https://bitbuc
⊘ Port 44->7999	ssh://bitbucket.atlassian.com:44	7999	https://bitbuc

Last modified on Oct 29, 2024

Was this helpful? Provide feedback about this article Yes No

In this section

Setting up SSH port forwarding

Related content

Setting up SSH port forwarding

Specify the Bitbucket base URL

SSH user keys for personal use

Creating SSH keys

Install Bitbucket Data Center on Linux

Administer Bitbucket in AWS

Install Bitbucket Data Center on Linux from an

Ce site utilise des cookies pour améliorer votre expérience de navigation, effectuer des analyses et des recherches, et cibler la publicité. Pour modifier vos préférences, cliquez sur Gérer les préférences. Sinon, cliquez sur Accepter tous les cookies pour indiquer que vous consentez à leur utilisation sur votre appareil. Cliquez sur Rejeter tous les cookies signifie que vous n'acceptez pas que nous utilisions des cookies qui ne sont pas strictement nécessaires sur votre appareil. Avis relatif aux cookies et au suivi d'Atlassian

Setting up SSH port forwarding

Signed system commits





Bitbucket Data Center 9.3 (Latest)

Documentation

- Get started with Bitbucket Data Center
- > Use Bitbucket Data Center

Administer Bitbucket Data Center

Users and groups

Advanced repository management

> External user directories

Global permissions

Setting up your mail server

- Integrate with Atlassian applications
- Connect Bitbucket to an external database

Migrating Bitbucket Data Center to another server

Migrate Bitbucket Server from Windows to Linux

> Run Bitbucket in AWS

Specify the Bitbucket base URL

Configuring the application navigator

Managing apps

View and configure the audit log

Monitor security threats

Update your license key

Configuration properties

Change Bitbucket's context path

Data recovery and backups

Disable HTTP(S) access to Git repositories

- > Mirrors
- Bitbucket Mesh

Powered by Confluence and Scroll Viewport.

Your Privacy Choices Privacy Policy Terms of Use Security © 2024 Atlassian

Ce site utilise des cookies pour améliorer votre expérience de navigation, effectuer des analyses et des recherches, et cibler la publicité. Pour modifier vos préférences, cliquez sur Gérer les préférences. Sinon, cliquez sur Accepter tous les cookies pour indiquer que vous consentez à leur utilisation sur votre appareil. Cliquez sur Rejeter tous les cookies signifie que vous n'acceptez pas que nous utilisions des cookies qui ne sont pas strictement nécessaires sur votre appareil. Avis relatif aux cookies et au suivi d'Atlassian