$\oplus$ 

**Open Specifications** 

Specifications ∨ Dev Center Events 🗗 Test Support Programs Patents Blog ∨

🔽 Filter by title

3.1.4 Message Processing **Events and Sequencing** Rules

- > 3.1.4.1 Printer Management Methods
- > 3.1.4.2 Printer-Driver Management Methods
- > 3.1.4.3 Printer-Port Management Methods
- > 3.1.4.4 Print-Processor Management Methods
- > 3.1.4.5 Port Monitor Management Methods
- > 3.1.4.6 Form Management Methods
- > 3.1.4.7 Job Management Methods
- > 3.1.4.8 Job Printing Methods
- > 3.1.4.9 Printing-Related **Notification Methods**
- > 3.1.4.10 Job Named **Property Management** Methods
- > 3.1.4.11 Branch Office Print Remote Logging Methods
- 3.1.5 Timer Events
- 3.1.6 Other Local Events
- > 3.2 IRemoteWinspool Client Details
- > 4 Protocol Examples
  - 5 Security Considerations
  - 6 Appendix A: Full IDL
  - 7 Appendix B: Product Behavior
  - 8 Change Tracking
  - 9 Index
- Download PDF

Learn /

## 3.1.4 Message Processing Events and **Sequencing Rules**

Feedback Article • 06/24/2021

An implementation of the Print System Asynchronous Remote Protocol MUST indicate the following to the remote procedure call (RPC) runtime ([MS-RPCE] section 3).

- Perform a strict NDR data consistency check at target level 6.0.
- Reject a NULL unique or full pointer with nonzero conformant value.
- Using the **strict\_context\_handle** attribute ([MS-RPCE] section 2.2.4.15), reject the use of context handles that are created by the methods of a different RPC interface.

The methods that are defined by this protocol are grouped into functional categories, and their syntax and behavior are specified in sections, as shown in the following table. Most methods described in these sections have functional equivalents in the Print System Remote Protocol ([MS-RPRN] section 3.1.4).

Expand table

Functional category	Description	Section
Printer management	Methods used for discovering and obtaining access to supported printers.	3.1.4.1
Printer driver management	Methods for discovering and installing printer drivers.	3.1.4.2
Printer port management	Methods for discovering and communicating with printer ports.	3.1.4.3
Print-processor management	Methods for discovering and manipulating print-processor objects.	3.1.4.4
Port monitor management	Methods for discovering and installation of port monitor modules.	3.1.4.5
Form management	Methods for discovering and configuring printer forms.	3.1.4.6
Job management	Methods for discovering, defining, and scheduling print jobs.	3.1.4.7
Job printing	Methods for adding documents, pages, and data to print jobs.	3.1.4.8
Printing-related notifications	Methods for obtaining notifications of printing events.	3.1.4.9
Job named property management	Methods for creating, updating, deleting, and enumerating <b>Job Named Properties</b> (section 3.1.1).<9>	3.1.4.10
Branch office print remote logging	Methods for processing Branch Office Print Remote Log Entries (section 3.1.1).<10>	3.1.4.11

The following table lists all the methods of the Print System Asynchronous Remote Protocol in ascending order of their opnums.

Methods in RPC opnum order:

## **Expand table**

Method	Description
RpcAsyncOpenPrinter	RpcAsyncOpenPrinter retrieves a handle to a specified printer, port, print job or print server. A client uses this method to obtain a print handle to an existing printer on a remote computer.
	The counterpart of this method in the Print System Remote Protocol is <b>RpcOpenPrinterEx</b> . All parameters not defined below are specified in [MS-RPRN] section 3.1.4.2.14.
	Opnum: 0
RpcAsyncAddPrinter	RpcAsyncAddPrinter installs a printer on the print server.
	The counterpart of this method in the Print System Remote Protocol is <b>RpcAddPrinterEx</b> . All parameters not defined below are specified in [MS-RPRN] section 3.1.4.2.15.
	Opnum: 1
RpcAsyncSetJob	RpcAsyncSetJob pauses, resumes, cancels, or restarts a print job on a specified printer. This method also can set print job parameters, including the job priority and document name.
	Opnum: 2
RpcAsyncGetJob	RpcAsyncGetJob retrieves information about a specified print job on a specified printer.
	Opnum: 3
RpcAsyncEnumJobs	<b>RpcAsyncEnumJobs</b> retrieves information about a specified set of print jobs on a specified printer.
	Opnum: 4
RpcAsyncAddJob	RpcAsyncAddJob returns ERROR_INVALID_PARAMETER.  Opnum: 5
RpcAsyncScheduleJob	RpcAsyncScheduleJob returns ERROR_SPL_NO_ADDJOB.
	Opnum: 6
RpcAsyncDeletePrinter	RpcAsyncDeletePrinter deletes the specified printer object.
	The client MUST call <b>RpcAsyncClosePrinter</b> (section 3.1.4.1.10) with the same <b>PRINTER_HANDLE</b> after calling this method.
	Opnum: 7
RpcAsyncSetPrinter	RpcAsyncSetPrinter sets the state of a specified printer.
	Opnum: 8
RpcAsyncGetPrinter	<b>RpcAsyncGetPrinter</b> retrieves information about a specified printer.
	Opnum: 9
RpcAsyncStartDocPrinter	<b>RpcAsyncStartDocPrinter</b> notifies a specified printer that a document is being spooled for printing.
	Opnum: 10
RpcAsyncStartPagePrinter	<b>RpcAsyncStartPagePrinter</b> notifies a specified printer that a page is about to be printed.
	Opnum: 11

RpcAsyncWritePrinter  RpcAsyncWritePrinter adds data to the file report the spool file for a specified printer, if the spool is turned on; or it sends data to the device direct printer is configured for direct printing.  Opnum: 12	ling option
	ctly, if the
RpcAsyncEndPagePrinter  RpcAsyncEndPagePrinter notifies a specified printer application is at the end of a page in a printer notifies a specified printer application is at the end of a page in a printer notifies a specified printer notifies a speci	
Opnum: 13	
RpcAsyncEndDocPrinter RpcAsyncEndDocPrinter signals the completion current print job on a specified printer.	n of the
Opnum: 14	
RpcAsyncAbortPrinter RpcAsyncAbortPrinter aborts the current document specified printer.	iment on a
Opnum: 15	
RpcAsyncGetPrinterData RpcAsyncGetPrinterData retrieves configuration a specified printer or print server.	on data from
Opnum: 16	
RpcAsyncGetPrinterDataEx retrieves configurate the specified printer or print server. This method RpcAsyncGetPrinterData (section 3.1.4.1.6) and retrieve values stored under a specified key by RpcAsyncSetPrinterDataEx (section 3.1.4.1.9).	od extends d can
Opnum: 17	
RpcAsyncSetPrinterData RpcAsyncSetPrinterData sets the configuration printer or print server.	າ data for a
Opnum: 18	
RpcAsyncSetPrinterDataEx RpcAsyncSetPrinterDataEx sets the configuration a printer or print server. This method is similar RpcAsyncSetPrinterData (section 3.1.4.1.8) but the caller to specify the registry key under which the data.	to t also allows
Opnum: 19	
RpcAsyncClosePrinter RpcAsyncClosePrinter closes a handle to a print server object, job object, or port object, which i calling RpcAsyncOpenPrinter (section 3.1.4.1.1 RpcAsyncAddPrinter (section 3.1.4.1.2).	is opened by
Opnum: 20	
RpcAsyncAddForm adds a form name to the liss supported forms.	st of
Opnum: 21	
RpcAsyncDeleteForm RpcAsyncDeleteForm removes a form name from of supported forms.	om the list
Opnum: 22	
RpcAsyncGetForm RpcAsyncGetForm retrieves information about form.	a specified
Opnum: 23	
RpcAsyncSetForm RpcAsyncSetForm sets the form information for specified printer.	or the

RpcAsyncEnumForms	<b>RpcAsyncEnumForms</b> enumerates the forms that the specified printer supports.
	Opnum: 25
RpcAsyncGetPrinterDriver	<b>RpcAsyncGetPrinterDriver</b> retrieves data about a specified printer driver on a specified printer.
	Opnum: 26
RpcAsyncEnumPrinterData	<b>RpcAsyncEnumPrinterData</b> enumerates configuration data for a specified printer.
	Opnum: 27
RpcAsyncEnumPrinterDataEx	RpcAsyncEnumPrinterDataEx enumerates all value names and data for a specified printer and key. This method extends RpcAsyncEnumPrinterData (section 3.1.4.1.11) by retrieving several values in a single call.
	Opnum: 28
RpcAsyncEnumPrinterKey	<b>RpcAsyncEnumPrinterKey</b> enumerates the subkeys of a specified key for a specified printer.
	Opnum: 29
RpcAsyncDeletePrinterData	RpcAsyncDeletePrinterData deletes a specified value from the configuration of a specified printer.
	Opnum: 30
RpcAsyncDeletePrinterDataEx	RpcAsyncDeletePrinterDataEx deletes a specified value from the configuration of a specified printer. This method is similar to RpcAsyncDeletePrinterData (section 3.1.4.1.14) but accesses the configuration data using a set of named and typed values that are stored in a hierarchy of registry keys.
	Opnum: 31
RpcAsyncDeletePrinterKey	RpcAsyncDeletePrinterKey deletes a specified key and all its subkeys from the configuration of a specified printer.
	Opnum: 32
RpcAsyncXcvData	RpcAsyncXcvData provides the means by which a port monitor client component can communicate with its server-side counterpart, the actual port monitor that is hosted by the server.
	Opnum: 33
RpcAsyncSendRecvBidiData	RpcAsyncSendRecvBidiData sends and receives bidirectional data. This method is used to communicate with print monitors that support such data.
	Opnum: 34
RpcAsyncCreatePrinterIC	RpcAsyncCreatePrinterIC creates an information context on a specified printer.
	Opnum: 35
RpcAsyncPlayGdiScriptOnPrinterIC	RpcAsyncPlayGdiScriptOnPrinterIC queries fonts for printer connections.
	Opnum: 36
RpcAsyncDeletePrinterIC	RpcAsyncDeletePrinterIC deletes a printer information context.
	Opnum: 37
RpcAsyncEnumPrinters	<b>RpcAsyncEnumPrinters</b> enumerates available local printers, printers on a specified print server, printers in a specified

	domain, or print providers.
	Opnum: 38
RpcAsyncAddPrinterDriver	RpcAsyncAddPrinterDriver installs a specified local or a remote printer driver on a specified print server, and it links the configuration, data, and driver files.
	Opnum: 39
RpcAsyncEnumPrinterDrivers	<b>RpcAsyncEnumPrinterDrivers</b> enumerates the printer drivers installed on a specified print server.
	Opnum: 40
RpcAsyncGetPrinterDriverDirectory	RpcAsyncGetPrinterDriverDirectory retrieves the path of the printer-driver directory on a specified print server.
	Opnum: 41
RpcAsyncDeletePrinterDriver	<b>RpcAsyncDeletePrinterDriver</b> removes the specified printer driver from the list of supported drivers for a specified print server.
	Opnum: 42
RpcAsyncDeletePrinterDriverEx	RpcAsyncDeletePrinterDriverEx removes the specified printer driver from the list of supported drivers on a specified print server, and deletes the files associated with the driver. This method is similar to RpcAsyncDeletePrinterDriver (section 3.1.4.2.5) but can also delete specific versions of the driver.
	Opnum: 43
RpcAsyncAddPrintProcessor	RpcAsyncAddPrintProcessor installs a specified print processor on the specified server and adds its name to an internal list of supported print processors.
	Opnum: 44
RpcAsyncEnumPrintProcessors	<b>RpcAsyncEnumPrintProcessors</b> enumerates the print processors installed on a specified server.
	Opnum: 45
RpcAsyncGetPrintProcessorDirectory	<b>RpcAsyncGetPrintProcessorDirectory</b> retrieves the path for the print processor on the specified server.
	Opnum: 46
RpcAsyncEnumPorts	<b>RpcAsyncEnumPorts</b> enumerates the ports that are available for printing on a specified server.
	Opnum: 47
RpcAsyncEnumMonitors	<b>RpcAsyncEnumMonitors</b> retrieves information about the port monitors installed on a specified server.
	Opnum: 48
RpcAsyncAddPort	<b>RpcAsyncAddPort</b> adds a specified port name to the list of supported ports on a specified server.
	Opnum: 49
RpcAsyncSetPort	<b>RpcAsyncSetPort</b> sets the status associated with a specified port on a specified print server.
	Opnum: 50
RpcAsyncAddMonitor	<b>RpcAsyncAddMonitor</b> installs a specified local port monitor, and links the configuration, data, and monitor files on a specified print server.
	Opnum: 51

RpcAsyncDeleteMonitor	<b>RpcAsyncDeleteMonitor</b> removes a specified port monitor from a specified print server.
	Opnum: 52
RpcAsyncDeletePrintProcessor	<b>RpcAsyncDeletePrintProcessor</b> removes a specified print processor from a specified server.
	Opnum: 53
RpcAsyncEnumPrintProcessorDatatypes	RpcAsyncEnumPrintProcessorDatatypes enumerates the data types that a specified print processor supports.
	Opnum: 54
RpcAsyncAddPerMachineConnection	RpcAsyncAddPerMachineConnection persistently saves the configuration information for a connection, including the print server name and the name of the print providers for a specified connection.
	Opnum: 55
RpcAsyncDeletePerMachineConnection	RpcAsyncDeletePerMachineConnection deletes the stored connection configuration information that corresponds to the <i>pPrinterName</i> parameter value.
	Opnum: 56
RpcAsyncEnumPerMachineConnections	RpcAsyncEnumPerMachineConnections enumerates each of the per-machine connections into a specified buffer.
	Opnum: 57
RpcSyncRegisterForRemoteNotifications	RpcSyncRegisterForRemoteNotifications opens a notification handle by using a printer handle or print server handle, to listen for remote printer change notifications.
	Opnum: 58
RpcSyncUnRegisterForRemoteNotifications	RpcSyncUnRegisterForRemoteNotifications closes a notification handle that is opened by calling RpcSyncRegisterForRemoteNotifications (section 3.1.4.9.1).
	Opnum: 59
RpcSyncRefreshRemoteNotifications	RpcSyncRefreshRemoteNotifications gets notification information for all requested members. This is called by a client if the "RemoteNotifyData Flags" property in the RpcPrintPropertiesCollection (section 2.2.4) instance, which was returned as part of the notification from an RpcAsyncGetRemoteNotifications (section 3.1.4.9.4) call, has the PRINTER_NOTIFY_INFO_DISCARDED bit set ([MS-RPRN] section 2.2.3.2).
	Opnum: 60
RpcAsyncGetRemoteNotifications	RpcAsyncGetRemoteNotifications is used to poll the print server for specified change notifications. A call to this method is suspended until the server has a new change notification for the client. Subsequently, the client calls this method again to poll for additional notifications from the server.
	Opnum: 61
RpcAsyncInstallPrinterDriverFromPackage	RpcAsyncInstallPrinterDriverFromPackage installs a printer driver from a driver package.
	Opnum: 62
RpcAsyncUploadPrinterDriverPackage	RpcAsyncUploadPrinterDriverPackage uploads a driver package so it can be installed with the RpcAsyncInstallPrinterDriverFromPackage method (section 3.1.4.2.7).

	Opnum: 63
RpcAsyncGetCorePrinterDrivers	RpcAsyncGetCorePrinterDrivers retrieves the globally unique identifier (GUID), the version, the date of the specified core printer drivers, and the path to their packages.
	Opnum: 64
RpcAsyncCorePrinterDriverInstalled	RpcAsyncCorePrinterDriverInstalled determines if a specific core printer driver is installed.
	Opnum: 65
RpcAsyncGetPrinterDriverPackagePath	RpcAsyncGetPrinterDriverPackagePath gets the path to the specified printer driver package.
	Opnum: 66
RpcAsyncDeletePrinterDriverPackage	<b>RpcAsyncDeletePrinterDriverPackage</b> deletes a specified printer driver package.
	Opnum: 67
RpcAsyncReadPrinter	<b>RpcAsyncReadPrinter</b> retrieves data from the specified job object.
	Opnum: 68
RpcAsyncResetPrinter	RpcAsyncResetPrinter resets the data type and device mode values to use for printing documents that are submitted by the RpcAsyncStartDocPrinter method (section 3.1.4.8.1).
	Opnum: 69
RpcAsyncGetJobNamedPropertyValue	<b>RpcAsyncGetJobNamedPropertyValue</b> retrieves the value of the specified <b>Job Named Property</b> (section 3.1.1) for the specified print job.
	Opnum: 70
RpcAsyncSetJobNamedProperty	RpcAsyncSetJobNamedProperty creates a new Job Named Property or changes the value of an existent Job Named Property for the specified print job.
	Opnum: 71
RpcAsyncDeleteJobNamedProperty	RpcAsyncDeleteJobNamedProperty deletes a Job Named Property for the specified print job.
	Opnum: 72
RpcAsyncEnumJobNamedProperties	RpcAsyncEnumJobNamedProperties enumerates the Job Named Properties for the specified print job.
	Opnum: 73
RpcAsyncLogJobInfoForBranchOffice	RpcAsyncLogJobInfoForBranchOffice processes one or more Branch Office Print Remote Log Entries (section 3.1.1) by writing them to the Microsoft-Windows-PrintService/Admin and Microsoft-Windows-PrintService/Operations event channels.
	Opnum: 74

All methods defined in this protocol are request/response RPC methods. Each method returns either an HRESULT value ([MS-ERREF] section 2.1) or a Win32 code ([MS-ERREF] section 2.2).

A non-negative HRESULT return value indicates successful completion, and a negative value indicates failure. A Win32 return value of zero indicates successful completion, and a nonzero value indicates failure, with the following exceptions.

The ERROR\_MORE\_DATA and ERROR\_INSUFFICIENT\_BUFFER Win32 codes defined in the table have specific meanings in this protocol. When a method has an output parameter that returns a required buffer size, the method can return one of these errors.

**Expand table** 

Name/Value	Meaning
ERROR_INSUFFICIENT_BUFFER	The buffer size specified in a method call is too small.
0x0000007A	
ERROR_MORE_DATA	More data is available.
0x000000EA	

The caller SHOULD NOT treat these return values as errors. The caller SHOULD use the buffer size returned by the method to resize the buffers, and it SHOULD call the method again using the resized buffers. These cases are noted in the method definitions in this section and in their corresponding definitions in [MS-RPRN] section 3.1.4.

## **Additional resources**

**Events** 

Nov 20, 12 AM - Nov 22, 12 AM

Join online sessions at Microsoft Ignite created to expand your skills and help you tackle today's complex issues.

Register now

Senglish (United States)

✓ Your Privacy Choices

☆ Theme ∨

Manage cookies

**Previous Versions** 

Blog ☑ Contribute

ıte Privacy ♂

Terms of Use Trademarks ♂

© Microsoft 2024