Strategy Studio: SpeedRouteExecutionHandler (Execution Handler)

SpeedRouteExecutionHandler is Strategy Studio's FIX4.2 interface to SpeedRoute's exchange gateway.

This execution handler may be selected by including the following line in the server's main configuration file:

EXECUTION_HANDLER_MODE=SpeedRouteExecutionHandler

Session Level Settings

Many of the session-level settings are specified in the file execution_handler-conf/speed_route.config. Notable settings include:

- StartTime=HH:MM:SS
- > EndTime=HH:MM:SS
 - Required. Sets the window of time that the execution handler will attempt a connection.
 Connection will begin at StartTime, and end at EndTime. Times are in UTC.
- SocketConnectHost=host
 - Required. Specifies the IP of the SpeedRoute server for this session. This must be an IP address, and not a domain name.
- SocketConnectPort=port number
 - Required. Specifies the IP port of the SpeedRoute server for this session.
- Reconnectinterval=seconds
 - Sets the wait period before a disconnected session attempts a reconnect.
- TargetCompID=targetCompID
 - Required. Required. This will be provided by SpeedRoute.
- SenderCompID=senderCompID
 - Required. This corresponds to a SpeedRoute account and will be provided by SpeedRoute.
- SenderSubID=senderSubID
 - Required. This corresponds to a SpeedRoute account and will be provided by SpeedRoute.
- StrategyStudioAccount=accountName
 - Required. Sets the Strategy Studio account that will be associated with this session. This
 value must be unique for each session.
- > LocateBroker=MPID
 - Required if selling short. This is the MPID of the broker to be used for locates of short-sold stocks.