T···Systems···

Message Implementation Guideline

HBPO EDIFACT DELFOR

based on

DELFOR
Delivery schedule message

UN D.96A S3

Version: 96
Variant: A
Issue date: 11.05.2010

Structure / Table of Contents

Counter	No	Tag	St	MaxOcc	Level	Content
0000	1	**UNA**	C	1	0	SERVICE STRING ADVICE
0000	2	**UNB**	M	1	0	INTERCHANGE HEADER
0010	3	**UNH**	M	1	0	MESSAGE HEADER
0020	4	**BGM**	M	1	0	Beginning of message
0030	5	**DTM**	M	10	1	Date/time/period
0070		**SG2**	C	20	1	NAD
0080	6	**NAD**	M	1	1	Name and address
0070		**SG2**	C	20	1	NAD
0080	7	**NAD**	M	1	1	Name and address
0130	8	**UNS**	M	1	0	SECTION CONTROL
0140		**SG4**	C	500	1	NAD-LOC-SG8
0150	9	**NAD**	M	1	1	Name and address
0160	10	**LOC**	C	10	2	Place/location identification
0270		**SG8**	C	9999	2	LIN-PIA-FTX-SG10-SG10-SG10-SG10-SG10-SG12-SG12-SG12
0280	11	**LIN**	M	1	2	Line item
0290	12	**PIA**	C	10	3	Additional product id
0370	13	**FTX**	C	5	3	Free text
0410		**SG10**	C	10	3	RFF-DTM
0420	14	**RFF**	M	1	3	Reference
0430	15	**DTM**	C	1	4	Date/time/period
0410		**SG10**	C	10	3	RFF-DTM
0420	16	**RFF**	M	1	3	Reference
0430	17	**DTM**	C	1	4	Date/time/period
0410		**SG10**	C	10	3	RFF
0420	18	**RFF**	M	1	3	Reference
0410		**SG10**	C	10	3	RFF-DTM
0420	19	**RFF**	M	1	3	Reference
0430	20	**DTM**	C	1	4	Date/time/period
0410		**SG10**	C	10	3	RFF
0420	21	**RFF**	M	1	3	Reference
0470		**SG12**	C	200	3	QTY
0480	22	**QTY**	M	1	3	Quantity
0470		**SG12**	C	200	3	QTY
0480	23	**QTY**	M	1	3	Quantity
0470		**SG12**	C	200	3	QTY-SCC-DTM
0480	24	**QTY**	M	1	3	Quantity
0490	25	**SCC**	C	1	4	Scheduling conditions
0500	26	**DTM**	C	2	4	Date/time/period

Counter = Counter of segment/group within the standard
No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

T··Systems····

Counter	No	Tag	St	MaxOcc	Level	Content
1220	27	**UNS**	M	1	0	SECTION CONTROL
1250	28	**UNT**	M	1	0	MESSAGE TRAILER
0000	29	**UNZ**	M	1	0	INTERCHANGE TRAILER

Counter = Counter of segment/group within the standard
No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

HBPO EDIFACT DELFOR; 96; A   DELFOR / UN D.96A S3   Issue date: 11.05.2010   Print date: 17.05.2010
Generated by GEFEG.FX   Page: 3 /   37

T · · Systems · · ·

Branching Diagram of Used Segments/Groups

Legend:

Tag
St   MaxOcc
No
Counter

Tag = Segment/Group Tag
St = Status (M=Mandatory, C=Conditional, R=Required, O=Optional, A=Advised, D=Dependent)
MaxOcc = Maximum occurrence of the segment/group
No = Consecutive segment number
Counter = Counter of segment/group within the standard

T··Systems····

```
          ( 1 )                                                    ( 3 )

Level   0              ┌─────────────┐
                       │     UNS     │
                       ├───┬─────────┤
                       │ M │    1    │
                       ├───┴─────────┤
                       │      8      │
                       ├─────────────┤
                       │    0130     │
                       └─────────────┘

          ┌─────────────┐          ┌─────────────┐
          │     SG2     │          │     SG4     │
          ├───┬─────────┤          ├───┬─────────┤
          │ C │   20    │          │ C │   500   │
          ├───┴─────────┤          ├───┴─────────┤
          │    0070     │          │    0140     │
          └─────────────┘          └─────────────┘
Level   1 ┌─────────────┐          ┌─────────────┐
          │     NAD     │          │     NAD     │
          ├───┬─────────┤          ├───┬─────────┤
          │ M │    1    │          │ M │    1    │
          ├───┴─────────┤          ├───┴─────────┤
          │      7      │          │      9      │
          ├─────────────┤          ├─────────────┤
          │    0080     │          │    0150     │
          └─────────────┘          └─────────────┘
                                            ┌─────────────┐
                                            │     SG8     │
                                            ├───┬─────────┤
                                            │ C │  9999   │
                                            ├───┴─────────┤
                                            │    0270     │
                                            └─────────────┘
Level   2                       ┌─────────────┐  ┌─────────────┐
                                │     LOC     │  │     LIN     │
                                ├───┬─────────┤  ├───┬─────────┤
                                │ C │   10    │  │ M │    1    │
                                ├───┴─────────┤  ├───┴─────────┤
                                │     10      │  │     11      │
                                ├─────────────┤  ├─────────────┤
                                │    0160     │  │    0280     │
                                └─────────────┘  └─────────────┘
                                                             ( 2 )

Level   3                                  ┌─────────────┐  ┌─────────────┐
                                           │     PIA     │  │     FTX     │
                                           ├───┬─────────┤  ├───┬─────────┤
                                           │ C │   10    │  │ C │    5    │
                                           ├───┴─────────┤  ├───┴─────────┤
                                           │     12      │  │     13      │
                                           ├─────────────┤  ├─────────────┤
                                           │    0290     │  │    0370     │
                                           └─────────────┘  └─────────────┘
```

Tag	
St	MaxOcc
No	
Counter	

Tag = Segment/Group Tag
St = Status (M=Mandatory, C=Conditional, R=Required, O=Optional, A=Advised, D=Dependent)
MaxOcc = Maximum occurrence of the segment/group
No = Consecutive segment number
Counter = Counter of segment/group within the standard

T··Systems····

	SG10	SG10	SG10	SG10	SG10	
2	C | 10	C | 10	C | 10	C | 10	C | 10	4
	0410	0410	0410	0410	0410	

Level 3

RFF	RFF	RFF	RFF	RFF
M | 1	M | 1	M | 1	M | 1	M | 1
14	16	18	19	21
0420	0420	0420	0420	0420

Level 4

DTM	DTM		DTM
C | 1	C | 1		C | 1
15	17		20
0430	0430		0430

Tag	
St MaxOcc	
No	
Counter	

Tag = Segment/Group Tag
St = Status (M=Mandatory, C=Conditional, R=Required, O=Optional, A=Advised, D=Dependent)
MaxOcc = Maximum occurrence of the segment/group
No = Consecutive segment number
Counter = Counter of segment/group within the standard

HBPO EDIFACT DELFOR; 96; A   DELFOR / UN D.96A S3   Issue date: 11.05.2010   Print date: 17.05.2010
Generated by GEFEG.FX   Page: 6 /   37

Level 3

Level 4

Tag		Tag = Segment/Group Tag
St	MaxOcc	St = Status (M=Mandatory, C=Conditional, R=Required, O=Optional, A=Advised, D=Dependent)
No		MaxOcc = Maximum occurrence of the segment/group
Counter		No = Consecutive segment number
		Counter = Counter of segment/group within the standard

HBPO EDIFACT DELFOR; 96; A   DELFOR / UN D.96A S3   Issue date: 11.05.2010   Print date: 17.05.2010
Generated by GEFEG.FX   Page: 7 /   37

T··Systems····

Level 0

	UNS		UNT		UNZ	
M	1	M	1	M	1	
	27		28		29	
	1220		1250		0000	

Tag	
St	MaxOcc
No	
Counter	

Tag = Segment/Group Tag
St = Status (M=Mandatory, C=Conditional, R=Required, O=Optional, A=Advised, D=Dependent)
MaxOcc = Maximum occurrence of the segment/group
No = Consecutive segment number
Counter = Counter of segment/group within the standard

Segments

Counter	No	Tag	St	MaxOcc	Level	Name
0000	1	**UNA**	C	1	0	**SERVICE STRING ADVICE**

Tag	Name	Standard		Implementation		
		St Format		St Format		Usage / Remark
UNA						
UNA1	Component data element separator	M an1		M an1		default (A): colon
UNA2	Data element separator	M an1		M an1		default (A): plus sign
UNA3	Decimal notation	M an1		M an1		default (A): comma or full stop
UNA4	Release indicator	M an1		M an1		default (A): question mark; if not used, insert space character
UNA5	Reserved for future use	M an1		M an1		default (A): insert space character
UNA6	Segment terminator	M an1		M an1		default (A): apostrophe

Remark:

Example:

```
UNA:+.? '
```

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

T··Systems····

Counter	No	Tag	St	MaxOcc	Level	Name
0000	2	**UNB**	M	1	0	**INTERCHANGE HEADER**

		Standard		**Implementation**	
Tag	Name	St Format	St Format	Usage / Remark	
UNB					
S001	SYNTAX IDENTIFIER	M	M		
0001	Syntax identifier	M a4	M a4	**UNOC UN/ECE level C**	
0002	Syntax version number	M n1	M n1	**3 Syntax version number 3**	
S002	INTERCHANGE SENDER	M	M		
0004	Sender identification	M an..35	M an..35	Possible Odette codes are: O0013010120HBPO CA1 O0013010120HBPO DE1 O0013010120HBPO ES1 O0013010120HBPO ES2 O0013010120HBPO ES3 O0013010120HBPO HQ O0013010120HBPO MX1 O0013010120HBPO MX2 O0013010120HBPO MX3 O0013010120HBPO MX4 O0013010120HBPO SK1 O0013010120HBPO UK1 O0013010120HBPO US1 O0013010120HBPO US2 Note: The space in the Odettecode is always 4 Blanks!	
S003	INTERCHANGE RECIPIENT	M	M		
0010	Recipient identification	M an..35	M an..35		
S004	DATE/TIME OF PREPARATION	M	M		
0017	Date of preparation	M n6	M n6	Form: YYMMDD	
0019	Time of preparation	M n4	M n4	Form: HHMM	
0020	Interchange control reference	M an..14	M an..14	Unique reference assigned by the sender to an interchange	
0026	Application reference	C an..14	C an..14	Fix: "DELFOR"	
0035	Test indicator	C n1	C n1	1 indicates, that the message is a test **1 Interchange is a test**	

Remark:

Example:
```
UNB+UNOC:3+O0013010120HBPO+FRISCHER        01+010127:0717+1166477++DELFOR++++1'
```

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

Counter	No	Tag	St	MaxOcc	Level	Name
0010	3	**UNH**	M	1	0	**MESSAGE HEADER**

		Standard		**Implementation**	
Tag	Name	St Format		St Format	Usage / Remark
UNH					
0062	Message reference number	M an..14		M an..14	Unique message reference assigned by the sender
S009	MESSAGE IDENTIFIER	M		M	
0065	Message type identifier	M an..6		M an..6	**DELFOR Delivery schedule message**
0052	Message type version number	M an..3		M an..3	**D Draft directory**
0054	Message type release number	M an..3		M an..3	**96A Version 96A**
0051	Controlling agency	M an..2		M an..2	**UN UN/ECE/TRADE/WP.4, United Nations Standard Messages (UNSM)**

Remark:

Example:
UNH+00016+DELFOR:D:96A:UN'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

Counter	No	Tag	St	MaxOcc	Level	Name
0020	4	**BGM**	M	1	0	**Beginning of message**

		Standard		Implementation	
Tag	Name	St Format	St Format	Usage / Remark	
BGM					
C002	Document/message name	C	C		
1001	Document/message name, coded	C an..3	C an..3	**241 Delivery schedule**	
1000	Document/message name	C an..35	C an..35	**LIEFERA Delivery schedule BRUF**	
1004	Document/message number	C an..35	C an..35	Reference number assigned to the document/message by the issuer.	

Remark:

Example:
```
BGM+241:::LIEFERABRUF+00016'
```

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

HBPO EDIFACT DELFOR; 96; A   DELFOR / UN D.96A S3   Issue date: 11.05.2010   Print date: 17.05.2010
Generated by GEFEG.FX   Page: 12 /   37

Counter	No	Tag	St	MaxOcc	Level	Name
0030	5	**DTM**	M	10	1	**Date/time/period**

			Standard		**Implementation**	
Tag	Name		St Format		St Format	Usage / Remark
DTM						
C507	Date/time/period		M		M	
2005	Date/time/period qualifier		M an..3		M an..3	**137 Document/message date/time**
2380	Date/time/period		C an..35		C an..35	
2379	Date/time/period format qualifier		C an..3		C an..3	**102 CCYYMMDD**

Remark:

Example:
DTM+137:20010127:102'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

HBPO EDIFACT DELFOR; 96; A   DELFOR / UN D.96A S3   Issue date: 11.05.2010   Print date: 17.05.2010
Generated by GEFEG.FX   Page: 13 /   37

Counter	No	Tag	St	MaxOcc	Level	Name
0070		**SG2**	C	20	1	**NAD**
0080	6	**NAD**	M	1	1	**Name and address**

Tag	Name	St Format	St Format	Usage / Remark
		Standard	**Implementation**	
NAD				
3035	Party qualifier	M an..3	M an..3	**SU Supplier** Code giving specific meaning to a party
C082	Party identification details	C	C	
3039	Party id. identification	M an..35	M an..35	
3055	Code list responsible agency, coded	C an..3	C an..3	**92 Assigned by buyer or buyer's agent**

Remark:

Example:

NAD+SU+99000677::92'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

Counter	No	Tag	St	MaxOcc	Level	Name
0070		**SG2**	C	20	1	**NAD**
0080	7	**NAD**	M	1	1	**Name and address**

Tag	Name				Usage / Remark
		Standard		**Implementation**	
		St Format		St Format	
NAD					
3035	Party qualifier	M an..3		M an..3	**BY Buyer** Code giving specific meaning to a party
C082	Party identification details	C		C	
3039	Party id. identification	M an..35		M an..35	
3055	Code list responsible agency, coded	C an..3		C an..3	**91 Assigned by seller or seller's agent**

Remark:

Example:
NAD+BY+00000063::91'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

Counter	No	Tag	St	MaxOcc	Level	Name
0130	8	**UNS**	M	1	0	**SECTION CONTROL**

Tag	Name	Standard		Implementation	
		St Format	St Format	Usage / Remark	
UNS					
0081	Section identification	M a1	M a1	**D Header/detail section separation** A charcter identifying the next section in a message

Remark:

Example:
UNS+D '

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

T · · Systems · · ·

Counter	No	Tag	St	MaxOcc	Level	Name
0140		**SG4**	C	500	1	**NAD-LOC-SG8**
0150	9	**NAD**	M	1	1	**Name and address**

			Standard		Implementation	
Tag	Name		St Format		St Format	Usage / Remark
NAD						
3035	Party qualifier		M an..3		M an..3	**ST Ship to** Code giving specific meaning to a party
C082	Party identification details		C		C	
3039	Party id. identification		M an..35		M an..35	
3055	Code list responsible agency, coded		C an..3		C an..3	**92 Assigned by buyer or buyer's agent**
C080	Party name		C		C	
3036	Party name		M an..35		M an..35	
C059	Street		C		C	
3042	Street and number/p.o. box		M an..35		M an..35	
3164	City name		C an..35		C an..35	Name of a city (a town, a village) for addressing purposes
3251	Postcode identification		C an..9		C an..9	Code defining postal zones or addresses; Note: Use code defined by appropriate national authority
3207	Country, coded		C an..3		C an..3	Identification of the name of a country or other geographical entity as specified in ISO 3166 Note: Use ISO 3166 two alpha country codes

Remark:

Example:
NAD+ST+004::92++HBPO GmbH+ERMELINGHOFSTRASSE 19+HAMM++59075+DE'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

Counter	No	Tag	St	MaxOcc	Level	Name
0140		**SG4**	C	500	1	**NAD-LOC-SG8**
0160	10	**LOC**	C	10	2	**Place/location identification**

Tag	Name	St Format	St Format	Usage / Remark
		Standard	**Implementation**	
LOC				
3227	Place/location qualifier	M an..3	M an..3	**11 Place/port of discharge** Code identifying the function of a location
C517	Location identification	C	C	
3225	Place/location identification	C an..25	C an..25	

Remark:

Example:
LOC+11+4400'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

HBPO EDIFACT DELFOR; 96; A   DELFOR / UN D.96A S3   Issue date: 11.05.2010   Print date: 17.05.2010
Generated by GEFEG.FX   Page: 18 /   37

Counter	No	Tag	St	MaxOcc	Level	Name
0270		**SG8**	C	9999	2	**LIN-PIA-FTX-SG10-SG12**
0280	11	**LIN**	M	1	2	**Line item**

Tag	Name	Standard		Implementation		
		St	Format	St	Format	Usage / Remark
LIN						
C212	Item number identification	C		C		
7140	Item number	C	an..35	C	an..35	
7143	Item number type, coded	C	an..3	C	an..3	**BP Buyer's part number**

Remark:

Example:
```
LIN+++721 415-01:BP'
```

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

HBPO EDIFACT DELFOR; 96; A   DELFOR / UN D.96A S3   Issue date: 11.05.2010   Print date: 17.05.2010
Generated by GEFEG.FX   Page: 19 /   37

Counter	No	Tag	St	MaxOcc	Level	Name
0270		**SG8**	C	9999	2	**LIN-PIA-FTX-SG10-SG12**
0290	12	**PIA**	C	10	3	**Additional product id**

			Standard		Implementation	
Tag	Name		St Format		St Format	Usage / Remark
PIA						
4347	Product id. function qualifier		M an..3		M an..3	**1 Additional identification** Indication of the function of the product code
C212	Item number identification		M		M	
7140	Item number		C an..35		C an..35	
7143	Item number type, coded		C an..3		C an..3	**SA Supplier's article number**
C212	Item number identification		C		C	
7140	Item number		C an..35		C an..35	
7143	Item number type, coded		C an..3		C an..3	**DR Drawing revision number**

Remark:

Example:
```
PIA+1+ABC4711:SA+0815:DR'
```

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

$\mathbf{T} \cdot \cdot \text{Systems} \cdot \cdot \cdot \cdot$

Counter	No	Tag	St	MaxOcc	Level	Name
0270		**SG8**	C	9999	2	**LIN-PIA-FTX-SG10-SG12**
0370	13	**FTX**	C	5	3	**Free text**

			Standard		**Implementation**	
Tag	Name		St Format		St Format	Usage / Remark
FTX						
4451	Text subject qualifier		M an..3		M an..3	**LIN Line item** Code specifying subject of a free text
C108	Text literal		C		C	
4440	Free text		M an..70		M an..70	
4440	Free text		C an..70		C an..70	
4440	Free text		C an..70		C an..70	
4440	Free text		C an..70		C an..70	
4440	Free text		C an..70		C an..70	

Remark:

Example:
```
FTX+LIN+++X:X:X:X:X'
```

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

HBPO EDIFACT DELFOR; 96; A   DELFOR / UN D.96A S3   Issue date: 11.05.2010   Print date: 17.05.2010
Generated by GEFEG.FX   Page: 21 /   37

Counter	No	Tag	St	MaxOcc	Level	Name
0410		**SG10**	C	10	3	**RFF-DTM**
0420	14	**RFF**	M	1	3	**Reference**

			Standard		Implementation	
Tag	Name		St Format	St Format	Usage / Remark	
RFF						
C506	Reference		M	M		
1153	Reference qualifier		M an..3	M an..3	**AAN Delivery schedule number**	
1154	Reference number		C an..35	C an..35		

Remark:

Example:
RFF+AAN:000000016'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

Counter	No	Tag	St	MaxOcc	Level	Name
0410		**SG10**	C	10	3	**RFF-DTM**
0430	15	**DTM**	C	1	4	**Date/time/period**

			Standard		**Implementation**	
Tag	Name		St	Format	St Format	Usage / Remark
DTM						
C507	Date/time/period		M		M	
2005	Date/time/period qualifier		M	an..3	M an..3	**171 Reference date/time**
2380	Date/time/period		C	an..35	C an..35	
2379	Date/time/period format qualifier		C	an..3	C an..3	**102 CCYYMMDD**

Remark:

Example:
DTM+171:20060317:102'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

T··Systems····

Counter	No	Tag	St	MaxOcc	Level	Name
0410		**SG10**	C	10	3	**RFF-DTM**
0420	16	**RFF**	M	1	3	**Reference**

		Standard		Implementation	
Tag	Name	St Format	St Format	Usage / Remark	
RFF					
C506	Reference	M	M		
1153	Reference qualifier	M an..3	M an..3	**AIF Previous delivery instruction number**	
1154	Reference number	C an..35	C an..35		

Remark:

Example:
RFF+AIF:000000015'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

Counter	No	Tag	St	MaxOcc	Level	Name
0410		**SG10**	C	10	3	**RFF-DTM**
0430	17	**DTM**	C	1	4	**Date/time/period**

			Standard		**Implementation**	
Tag	Name		St Format	St Format	Usage / Remark	
DTM						
C507	Date/time/period		M	M		
2005	Date/time/period qualifier		M an..3	M an..3	**171 Reference date/time**	
2380	Date/time/period		C an..35	C an..35		
2379	Date/time/period format qualifier		C an..3	C an..3	**102 CCYYMMDD**	

Remark:

Example:
DTM+171:20060302:102'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

Counter	No	Tag	St	MaxOcc	Level	Name
0410		**SG10**	C	10	3	**RFF**
0420	18	**RFF**	M	1	3	**Reference**

			Standard		Implementation	
Tag	Name		St Format	St Format	Usage / Remark	
RFF						
C506	Reference		M	M		
1153	Reference qualifier		M an..3	M an..3	**ON Order number (purchase)**	
1154	Reference number		C an..35	C an..35		

Remark:

Example:
RFF+ON:5500004949'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

Counter	No	Tag	St	MaxOcc	Level	Name
0410		**SG10**	C	10	3	**RFF-DTM**
0420	19	**RFF**	M	1	3	**Reference**

			Standard		Implementation	
Tag	Name		St Format	St Format	Usage / Remark	
RFF						
C506	Reference		M	M		
1153	Reference qualifier		M an..3	M an..3	**AAK Despatch advice number**	
1154	Reference number		C an..35	C an..35		

Remark:

Example:
RFF+AAK:01/03984'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

HBPO EDIFACT DELFOR; 96; A   DELFOR / UN D.96A S3   Issue date: 11.05.2010   Print date: 17.05.2010
Generated by GEFEG.FX   Page: 27 /   37

Counter	No	Tag	St	MaxOcc	Level	Name
0410		**SG10**	C	10	3	**RFF-DTM**
0430	20	**DTM**	C	1	4	**Date/time/period**

			Standard		Implementation	
Tag	Name		St Format	St Format	Usage / Remark	
DTM						
C507	Date/time/period		M	M		
2005	Date/time/period qualifier		M an..3	M an..3	**50 Goods receipt date/time**	
2380	Date/time/period		C an..35	C an..35		
2379	Date/time/period format qualifier		C an..3	C an..3	**102 CCYYMMDD**	

Remark:

Example:
DTM+50:20050402:102'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

Counter	No	Tag	St	MaxOcc	Level	Name
0410		**SG10**	C	10	3	**RFF**
0420	21	**RFF**	M	1	3	**Reference**

			Standard		Implementation	
Tag	Name		St Format	St Format	Usage / Remark	
RFF						
C506	Reference		M	M		
1153	Reference qualifier		M an..3	M an..3	**CST Team assignment number**	
1154	Reference number		C an..35	C an..35		

Remark:

Example:
RFF+CST:0071'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

T···Systems····

Counter	No	Tag	St	MaxOcc	Level	Name
0470		**SG12**	C	200	3	**QTY**
0480	22	**QTY**	M	1	3	**Quantity**

			Standard		**Implementation**	
Tag	Name		St Format	St Format	Usage / Remark	
QTY						
C186	Quantity details		M	M		
6063	Quantity qualifier		M an..3	M an..3	**70 Cumulative quantity received**	
6060	Quantity		M n..15	M n..15		
6411	Measure unit qualifier		C an..3	C an..3	**PCE Piece**	

Remark:

Example:
QTY+70:25000:PCE'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

HBPO EDIFACT DELFOR; 96; A   DELFOR / UN D.96A S3   Issue date: 11.05.2010   Print date: 17.05.2010
Generated by GEFEG.FX   Page: 30 /   37

T··Systems····

Counter	No	Tag	St	MaxOcc	Level	Name
0470		**SG12**	C	200	3	**QTY**
0480	23	**QTY**	M	1	3	**Quantity**

Tag	Name	Standard St Format	Implementation St Format	Usage / Remark
QTY				
C186	Quantity details	M	M	
6063	Quantity qualifier	M an..3	M an..3	**48 Received quantity**
6060	Quantity	M n..15	M n..15	
6411	Measure unit qualifier	C an..3	C an..3	**PCE Piece**

Remark:

Example:
QTY+48:0:PCE'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

HBPO EDIFACT DELFOR; 96; A   DELFOR / UN D.96A S3   Issue date: 11.05.2010   Print date: 17.05.2010
Generated by GEFEG.FX   Page: 31 /   37

T··Systems···

Counter	No	Tag	St	MaxOcc	Level	Name
0470		**SG12**	C	200	3	**QTY-SCC-DTM**
0480	24	**QTY**	M	1	3	**Quantity**

			Standard		**Implementation**	
Tag	Name		St Format	St Format	Usage / Remark	
QTY						
C186	Quantity details		M	M		
6063	Quantity qualifier		M an..3	M an..3	**113 Quantity to be delivered**	
6060	Quantity		M n..15	M n..15		
6411	Measure unit qualifier		C an..3	C an..3	**PCE Piece**	

Remark:

Example:
QTY+113:0:PCE'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

HBPO EDIFACT DELFOR; 96; A   DELFOR / UN D.96A S3   Issue date: 11.05.2010   Print date: 17.05.2010
Generated by GEFEG.FX   Page: 32 /   37

Counter	No	Tag	St	MaxOcc	Level	Name
0470		**SG12**	C	200	3	**QTY-SCC-DTM**
0490	25	**SCC**	C	1	4	**Scheduling conditions**

			Standard		**Implementation**	
Tag	Name		St Format		St Format	Usage / Remark
SCC						
4017	Delivery plan status indicator, coded		M an..3		M an..3	**1 Firm** **4 Planning/forecast** Planning/forecast quantities have to be delivered like firm orders if there is no update with the next DELFOR. Code indicating the level of commitment of schedule information.

Remark:

Example:
SCC+1'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

HBPO EDIFACT DELFOR; 96; A   DELFOR / UN D.96A S3   Issue date: 11.05.2010   Print date: 17.05.2010
Generated by GEFEG.FX   Page: 33 /   37

Counter	No	Tag	St	MaxOcc	Level	Name
0470		**SG12**	C	200	3	**QTY-SCC-DTM**
0500	26	**DTM**	C	2	4	**Date/time/period**

Tag	Name	St Format	St Format	Usage / Remark
		Standard	**Implementation**	
DTM				
C507	Date/time/period	M	M	
2005	Date/time/period qualifier	M an..3	M an..3	**2 Delivery date/time, requested**
				10 Shipment date/time, requested
2380	Date/time/period	C an..35	C an..35	
2379	Date/time/period format qualifier	C an..3	C an..3	**102 CCYYMMDD**

Remark:

Example:
```
DTM+2:20010131:102'
```

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

HBPO EDIFACT DELFOR; 96; A   DELFOR / UN D.96A S3   Issue date: 11.05.2010   Print date: 17.05.2010
Generated by GEFEG.FX   Page: 34 /   37

Counter	No	Tag	St	MaxOcc	Level	Name
1220	27	**UNS**	M	1	0	**SECTION CONTROL**

			Standard		Implementation	
Tag	Name		St Format	St Format	Usage / Remark	
UNS						
0081	Section identification		M a1	M a1	**S Detail/summary section separation**	
					A charcter identifying the next section in a message	

Remark:

Example:
UNS+S'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

Counter	No	Tag	St	MaxOcc	Level	Name
1250	28	**UNT**	M	1	0	**MESSAGE TRAILER**

		Standard		Implementation	
Tag	Name	St Format	St Format	Usage / Remark	
UNT					
0074	Number of segments in a message	M n..6	M n..6	Control count of number of segments in a message	
0062	Message reference number	M an..14	M an..14	Unique message reference assigned by the sender	

Remark:

Example:
`UNT+26+00016'`

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used

Counter	No	Tag	St	MaxOcc	Level	Name
0000	29	**UNZ**	M	1	0	**INTERCHANGE TRAILER**

		Standard		Implementation	
Tag	Name	St Format	St Format	Usage / Remark	
UNZ					
0036	Interchange control count	M n..6	M n..6	Count either of the number of messages or, if used, of the number of functional groups in an interchange.	
0020	Interchange control reference	M an..14	M an..14	Unique reference assigned by the sender to an interchange.	

Remark:

Example:
```
UNZ+1+1166477'
```

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used