
AMWAY MALAYSIA · PDP CONTENT

PDP Builder
How to use

Build the product pages shown in the **Product Overview** tab on amway.my. Add sections, fill in text and pictures, check Desktop, Tablet and Mobile, then export a ready-to-upload **{SKU}_en.html** with its images, in English, Bahasa Melayu and 中文.

Guide updated 21 Oct 2026



1 The screen at a glance

2 Make your first page

3 Simple and All options

4 The sections

5 Elements and text

6 Columns, cards and layout

7 Pictures and file names

8 Desktop, tablet, mobile and full screen

9 Languages (EN · BM · 中文)

10 Import an existing page

11 Page settings, saving and autosave

12 Export and upload

13 Keyboard shortcuts and tips

Vibe Coded by Claude & CC. All Rights Reserved ® 2026.

1 The screen at a glance

AREA	WHAT IT DOES
Top bar	SKU, preview size (Desktop / Tablet / Mobile), Open / Import, Undo / Redo, light or dark theme, Save project and **Export**.
Add a section (left)	Click a section to add it below the one selected, or drag it into the preview or the page list.
Page (left)	Your sections in order. Drag to reorder, or use the arrows, duplicate and delete buttons on each row.
Preview (middle)	The page as visitors see it. Click anything in it to edit it. **Grid** shows alignment lines and **Full screen** shows only the page.
Section / Page settings (right)	Settings for what you clicked, or for the whole page.
? (bottom left)	Keyboard shortcuts and a link to this guide. Below it is the date the builder was last updated.

> **Pop-up messages** (such as "Section added" or "Saved") appear at the top of the screen, under the top bar.

2 Make your first page

1. Type the product **SKU** in the top bar, for example `343136`. Every file name is built from it.
2. Add sections from **Add a section**. A typical page is Hero banner → Intro text → Columns or Feature rows → Cards → Brand strip → More Information → Bottom banner.
3. Click a section in the preview and fill in its text and pictures on the right.
4. Check the page on Tablet and Mobile, or press `F` for full screen.
5. Open **Page settings** to fill in the page title, description and keywords, and turn on BM / 中文 if needed.
6. Press **Export**, fix anything the checks list, and save the .zip.

> **Tip:** **Empty column** gives you a blank Columns section to build anything from scratch. **Custom HTML** lets you paste your own code.

3 Simple and All options

Each section's settings open in **Simple** mode, which shows only the main options:


- text and pictures
- Section size, including **Full width**
- Column background
- layout choices, such as Per row, Number of logos and Style

Switch to **All options** to see everything else:

- spacing and padding
- section backgrounds
- corners
- picture fit
- **Show on** (hide on a device)
- tablet and mobile text alignment
- gaps
- Send to top / bottom buttons

The builder remembers your choice.

> **Nothing is lost:** settings made in All options still apply when you switch back to Simple. They are only hidden.



Cards section in All options.

4 The sections

SECTION	USE IT FOR
Empty column	A blank Columns section to build your own layout.
Hero banner	The top banner: logo, title and text on a picture, with separate desktop, tablet and mobile pictures.
Intro text	A centred headline and paragraph. It also covers what "Text" and "Brand profile" did before.
Columns	Side-by-side boxes that wrap onto new lines. Each one holds any elements.
Cards	Boxes with a picture on top or on the left, then text and a button.
YouTube video	A full-width YouTube video.
Feature rows	Text and a picture side by side, alternating left and right.
Image + text	A picture with a title, subtitle and text beside it, such as "what's inside".
Brand strip	1 to 6 logos side by side, with a tagline.
Full-width image	One picture across the page, with tablet and mobile versions.
Divider	A line between sections.
More Information	How to use, consumer, precautions, storage and ingredients. White background by default.
Bottom banner	A closing banner.
Custom HTML	Your own code, or sections from an imported page.

Older projects with Text or Brand profile sections still open and edit as before.

5 Elements and text

Columns, cards, banners and strips are made of **elements**: Headline, Title, Paragraph, Icon, Icon row, Image, Video, Image + text, Logo, Button and Divider. Add them with the **Add** buttons under the list.

Click to edit

Click any element in the preview, and the right panel jumps to that element. Click the empty part of a column or card to open the column or card.

Order


Use the up and down arrows to move an element one place, or **Send to top** and **Send to bottom** (All options) to move it to the first or last place. Duplicate and delete sit next to them.

Text

- Select words and press **B**, **I**, **• List**, **1. List** or **Link**. A link turns the selected words into a clickable link, and web links open in a new tab.
- Set **Align**, **Weight**, **Italic**, **Size** and **Colour** for each element. "Default" keeps the template style.
- **Tablet align** and **Mobile align** (All options) let text be centred on desktop and left-aligned on mobile, for example.

Image + text

- **Layout:** picture left, picture right, or stacked.
- **Stack on:** Never, Mobile, or Tablet & mobile. For example, side by side on desktop and stacked on tablet and mobile.
- **Picture width** in % or px (up to 60%), the **gap** between picture and text, the vertical position, text alignment and picture fit.
- Separate styles for the **title, subtitle and text**. The text can have lists and links.



An Image + text element with a list.


Size, spacing and Show on

- **Width** is a % of the column. **Height** is a minimum, so text is never cut off.
- **Spacing** sets the space above and below, plus padding, in px. It has Desktop, Tablet and Mobile tabs.
- **Show on** hides an element, column, card or section on any device.

Buttons, dividers and videos

- **Buttons:** text, link, an optional icon, style (solid, gradient, outline or underline), corners and width.
- **Dividers:** width, thickness, colour or gradient, and round or square ends.
- **Videos:** a YouTube link, or an mp4 file saved to `assets/video/`.

6 Columns, cards and layout



A Columns section: alignment for all columns, the column list, Content position and each column's elements.

Columns

- Add as many columns as you like, and they wrap onto the next line. **Per line** sets how many fit on one line.
- Each column has a width %, a minimum height, a **Column background**, corners, padding and a **Content position** (a 3×3 grid).
- Column background can be a colour, a gradient or a picture. A picture can fill the column, fit, fill the width, fill the height or stretch. Its position can be the centre or any corner.
- For the whole section:
  - **Line up columns at**: top, middle or bottom
  - **Align content in every column**
  - **Place columns across the line**: stretch, left, centre or right

Cards

- **Style:** picture on top, or picture on the left with an adjustable width and a **Content position**.
- **Per row:** 1 to 6 on desktop. Tablet shows up to 2 per row and mobile shows 1.
- **Card style** sets the background, corners and padding for all cards at once.


Full width

Columns, Cards and Feature rows have **Full width** under Section size. It goes edge to edge with no side padding and no gap between columns. It also starts with **no space on the top and bottom**. To add space, type a number in **Top & bottom space** (px). Clear the box to use the template's normal space.

Brand strip

Choose **Number of logos** (1–6). The logos sit side by side in one row, and on mobile they wrap to two per row. Upload each logo in Elements.

Lowering the number removes the last logos in the list.



Brand strip with 3 logos.

7 Pictures and file names

Every picture is named automatically from the SKU, in page order, the same way as the live pages:

KIND	FILE NAME
Hero / bottom banner	`{SKU}_PDP_banner1.jpg`, `{SKU}_PDP_tb_banner1.jpg`, `{SKU}_PDP_mb_banner1.jpg`
Images, cards, Image + text	`{SKU}_PDP_img1.jpg`, `img2` ...
Tablet / mobile pictures NEW	`{SKU}_PDP_tb_img1.jpg`, `{SKU}_PDP_mb_img1.jpg`
Icons	`{SKU}_PDP_icon1.png` ...
Logos	`{SKU}_PDP_logo.png`; in a brand strip `{SKU}_PDP_whitelogo.png`, `whitelogo2` ...
Backgrounds	`{SKU}_PDP_bg1.jpg` ...
Videos	`assets/video/{SKU}_PDP_video1.mp4`
Language versions	the same name plus `_bm` or `_zh`, for example `{SKU}_PDP_banner1_bm.jpg`

Three ways to fill a picture

- **Upload** a file, or drop it on the box. It goes into the zip with the automatic name, or a name you type.
- **Use a file already on the server:** type its name, or paste the full link. To get the link, right-click the picture on the live page and choose *Copy image address*. Only the file name is kept, and the zip skips the file.
- If an upload has the **same name as a file on the server**, the page points to the server file. New uploads never take the name of a server file.

A different picture on tablet and mobile NEW

Image, Logo, Image + text and Card pictures have a **Tablet & mobile picture** panel under the main upload, for example for a taller crop on phones.

- If Tablet is empty, the tablet uses the desktop picture.
- If Mobile is empty, the phone uses the tablet picture, or the desktop picture when there is no tablet picture.

Hero banners and full-width images have always had their own three pictures. Icons and backgrounds use one picture on every device.

Picture fit

In All options, Image, Logo and Image + text pictures can **fill the column height**. Choose Fill (crops the edges), Fit (shows the whole picture) or Stretch, and pick which part stays in view.

Formats

PNG, JPG, SVG, WebP, GIF and AVIF all work. HEIC photos from an iPhone don't, so convert them to JPG first. Use PNG or SVG for icons and logos, and JPG for photos and banners.


8 Desktop, tablet, mobile and full screen

The page is shown inside the **Product Overview** tab, which is narrower than the browser window. The previews use the tab's width, so they show what visitors see:

PREVIEW	WIDTH	LAYOUT USED	BROWSER WINDOW ON AMWAY.MY
Desktop 1	1313px	page wider than 1200px	wider than 1287px
Tablet 2	834px	769 – 1200px	829 – 1287px
Mobile 3	390px	768px and narrower	828px and narrower

Full screen preview NEW

Press **Full screen** in the preview bar, or F. Only the page shows, on black, without outlines or grid lines. Switch between Desktop, Tablet and Mobile at the top. Leave with **✕ Exit**, Esc or F.




Full screen preview, Mobile.

Per-device settings

- **Show on** hides a section, column, card or element on any device.
- **Spacing** has Desktop, Tablet and Mobile tabs. Tablet values also apply to mobile, unless mobile has its own. A dot marks the tabs you've changed.
- **Tablet align** and **Mobile align** for text.
- **Stack on** for Image + text.
- **Page width** (Page settings) sets a minimum and maximum width per device.

9 Languages (EN · BM · 中文)

1. **Page settings → Languages:** tick Bahasa Melayu and / or 中文.
2. Press **Translate texts…**. Each English text is on the left. Type the translation on the right. An empty box stays in English.
3. For pictures with words on them, upload a language version in the same window, or type a server file name. Tablet and mobile pictures are listed too. Leave a box empty to use the English picture.
4. Pick the language in the preview's language menu to check the page.



Translate window: texts and pictures grouped by section.

Export gives `{SKU}_en.html`, `{SKU}_bm.html` and `{SKU}_zh.html`, all with the same layout. When you translate, keep the `**bold**`, `*italic*` and `-` list marks.

> **Missing translation warning** NEW: Export lists every text still in English on the BM and 中文 pages, section by section, including the page title, description and keywords. It also adds a note for each section listing the pictures that still use the English version. That's fine for pictures without words.

10 Import an existing page

Open / Import accepts a saved project or a live PDP page (`{SKU}_en.html`).

- **Pages made with this builder** reopen fully editable, with every section, translation and file name.
- **LIVARA-style pages** (like 343136) come in as editable sections: hero, intro, feature rows, brand, More Information and banners.
- **Other templates** ask how to come in. **Keep exactly** keeps every section as Custom HTML, unchanged. **Make editable** converts banners, repeated items, columns and More Information into builder sections. `Ctrl` + `Z` goes back to the exact version.
- **Every imported page keeps its own styles**, in Page settings → Page CSS.
- Any Custom HTML section can be changed with **Convert to editable section**.

Edit Custom HTML in place


- **Text:** click it in the preview and type. The bar above it has **B**, *I*, Link and Done. `Esc` cancels.
- **Pictures and videos:** click one to open it on the right. **Replace** uploads a new file under the same name. To add it as a new file instead, change the file name first.
- **Adding or removing parts:** use the section's **HTML code** box, or Convert to editable section.

> **Tip:** import replaces the page you are working on. Undo brings it back, but save first if you need it.

11 Page settings, saving and autosave

- **Page title, meta description and keywords** are used in the browser tab and by search engines.
- **Server images in preview** and the image folder address (default `https://www.amway.my/pdpcontent/MYBN/assets/img/`).
- **Languages**, **Page width** per device, and **Page CSS** for imported pages.
- **Save project** (`Ctrl` + `S`) downloads `{SKU}_project.html` with everything inside, uploads included.
- **Autosave** keeps your work in this browser. If a tab closes by accident, reopen the builder and choose **Restore**. Autosave only works in the same browser on the same device, so use Save project to move work to another computer.
- **Undo / Redo** keeps the last 100 steps.

12 Export and upload



The Export window: checks, image optimisation and the list of files.

1. Press **Export** (`Ctrl` + `E`). **Checks** list errors to fix, warnings and tips, such as sample text, missing pictures or links, untranslated text and large files. **Go to** jumps to the section.
2. The **server check** marks each server picture ✅ Found or ⛔ Not on server. It only works when the builder is opened from GitHub.
3. Optional: **Optimise images** resizes and compresses uploads.
4. **Save .zip** downloads every language page plus `assets/img/` with your new uploads. **Save HTML only** saves just the pages.
5. Upload the files to `pdpcontent/MYBN/`, keeping the `assets/img/` folder. The page uses the `assets/css/artistry.css` and `assets/js` files already on the server.

> **First time using a new feature?** Upload a test page and check it on a computer, an iPhone and an Android phone before it goes live. Also check that the Product Overview tab fits the page's height.

13 Keyboard shortcuts and tips

KEYS	ACTION
`⌘/Ctrl` `S`	Save project
`⌘/Ctrl` `O`	Open / import a file
`⌘/Ctrl` `E`	Export
`⌘/Ctrl` `Z`	Undo
`⌘/Ctrl` `⇧` `Z` or `⌘/Ctrl` `Y`	Redo
`⌘/Ctrl` `D`	Duplicate the selected element, or the section
`Delete` / `Backspace`	Delete the selected element, or the section
`↑` `↓`	Select the previous / next section
`1` `2` `3`	Preview Desktop / Tablet / Mobile
`G`	Grid lines on / off
`F`	Full screen preview on / off
`?`	Show the shortcut list
`Esc`	Close a window or leave full screen

Single-key shortcuts do nothing while you are typing in a box. An element is "selected" after you click it in the preview.

Good to know

- The preview reloads for about a second after each change, so a click during that second may be missed.
- Spacing in px stays fixed. Template spacing is in vw, so it grows with the screen.
- Open the builder from GitHub to see live server pictures and run the server check. Inside claude.ai, outside pictures are blocked and placeholders show instead.
- If something looks out of date after an update, hard-refresh the builder (`⌘/Ctrl` `⇧` `R`).

Vibe Coded by Claude & CC. All Rights Reserved ® 2026.