Jessica要努力了。。

博客园 首页 新随笔 联系 订阅 管理

昵称: Jessica程序猿园龄: 5年10个月粉丝: 544关注: 27+加关注

<		202	20年	4月		>
日	_	=	Ξ	四	五	六
29	30	31	1	2	3	4
5	6	7	8	9	10	11
12	13	14	15	16	17	18
19	20	21	22	23	24	25
26	27	28	29	30	1	2
3	4	5	6	7	8	9

搜索	
	找找看
	谷歌搜索

常用链接
我的随笔
我的评论
我的参与
最新评论
我的标签

我的标签
随笔分类 (988)
C++(79)
C++ template(5)
C++ 容器(28)
C++构造函数(6)
C++面向对象编程(7)
C++训练(71)
C++重载与类型转换(9)
careercup(87)
dubbo(2)
Effective C++(3)
ext2文件系统系列(6)
flashcache(2)

KVM虚拟机IO处理过程(二) ----QEMU/KVM I/O 处理过程

接着KVM虚拟机IO处理过程中Guest Vm IO处理过程

(http://blog.csdn.net/dashulu/article/details/16820281),本篇文章主要描述IO从guest vm跳转到kvm和qemu后的处理过程.

随笔 - 974 文章 - 0 评论 - 134

首先回顾一下kvm的启动过程

(http://blog.csdn.net/dashulu/article/details/17074675).qemu通过调用kvm提供的一系列接口来启动kvm. qemu的入口为vl.c中的main函数,main函数通过调用kvm_init 和 machine->init来初始化kvm. 其中, machine->init会创建vcpu, 用一个线程去模拟vcpu, 该线程执行的函数为qemu_kvm_cpu_thread_fn, 并且该线程最终kvm_cpu_exec,该函数调用kvm_vcpu_ioctl切换到kvm中,下次从kvm中返回时,会接着执行kvm_vcpu_ioctl之后的代码,判断exit_reason,然后进行相应处理.

```
int kvm_cpu_exec(CPUState *cpu)
 2.
 3.
          struct kvm run *run = cpu->kvm run;
 4.
          int ret, run_ret;
 5.
          DPRINTF("kvm_cpu_exec()\n");
 6.
 7.
 8.
          if (kvm_arch_process_async_events(cpu)) {
 9.
              cpu->exit request = 0;
10.
              return EXCP HLT;
11.
12
13.
14.
              if (cpu->kvm_vcpu_dirty) {
15.
                  kvm_arch_put_registers(cpu, KVM_PUT_RUNTIME_STATE);
16.
                   cpu->kvm vcpu dirty = false;
17.
18.
19.
              kvm_arch_pre_run(cpu, run);
20.
              if (cpu->exit_request) {
21.
                  DPRINTF("interrupt exit requested\n");
22.
23.
                    ^{\star} KVM requires us to reenter the kernel after IO exits to complete
                    \mbox{\scriptsize \star} instruction emulation. This self-signal will ensure that we
24.
25.
                    * leave ASAP again.
26.
27.
                   qemu_cpu_kick_self();
28.
29.
              qemu_mutex_unlock_iothread();
3.0
31.
              run ret = kvm vcpu ioctl(cpu, KVM RUN, 0);
32.
33.
              qemu_mutex_lock_iothread();
              kvm_arch_post_run(cpu, run);
34.
35.
36.
              if (run_ret < 0) {
37.
                  if (run_ret == -EINTR || run_ret == -EAGAIN) {
38.
                      DPRINTF("io window exit\n");
39.
                       ret = EXCP_INTERRUPT;
40.
                      break;
41.
42.
                   fprintf(stderr, "error: kvm run failed %s\n",
43.
                          strerror(-run ret));
                   abort();
44.
45.
46
47.
              trace kvm run exit(cpu->cpu index, run->exit reason);
```

```
gdb调试(2)
git(3)
hbase(1)
iscsi(4)
JAVA(16)
JVM虚拟机(1)
Leetcode(169)
linux内存管理(11)
linux内核(23)
Linux内核分析及编程(9)
Linux内核设计与实现(1)
maven
nainx(2)
python(1)
shell 编程(20)
Spring(2)
SQL(5)
STL源码剖析(11)
UNIX 网络编程(25)
unix环境高级编程(24)
Vim(2)
web(10)
阿里中间件(5)
操作系统
测试(13)
程序员的自我修养(7)
大数据处理(3)
动态内存和智能指针(4)
泛型编程(2)
分布式(1)
概率题(2)
论文中的算法(11)
面试(82)
```

```
48.
              switch (run->exit_reason) {
49
              case KVM EXIT IO:
                 DPRINTF("handle_io\n");
50.
51.
                  kvm handle io(run->io.port,
52.
                                (uint8_t *)run + run->io.data_offset,
53.
                                run->io.direction,
54.
                                run->io.size,
55.
                                run->io.count);
56.
                  ret = 0;
57.
                 break;
58.
              case KVM_EXIT_MMIO:
59.
                  DPRINTF("handle_mmio\n");
60.
                  cpu_physical_memory_rw(run->mmio.phys_addr,
61.
                                          run->mmio.data,
62.
                                          run->mmio.len,
                                          run->mmio.is write);
63.
                 ret = 0;
64.
65.
                  break:
              case KVM_EXIT_IRQ_WINDOW_OPEN:
66.
67.
                  DPRINTF("irq_window_open\n");
68.
                  ret = EXCP_INTERRUPT;
69.
                 break:
70.
              case KVM_EXIT_SHUTDOWN:
71.
                 DPRINTF("shutdown\n");
72.
                 qemu_system_reset_request();
73.
                  ret = EXCP INTERRUPT;
74.
                  break;
75.
              case KVM EXIT UNKNOWN:
76.
                  fprintf(stderr, "KVM: unknown exit, hardware reason %" PRIx64 "\n",
77.
                          (uint64_t)run->hw.hardware_exit_reason);
78.
                  ret = -1;
79.
                  break;
80.
              case KVM_EXIT_INTERNAL_ERROR:
                  ret = kvm_handle_internal_error(cpu, run);
81.
82.
83.
              default:
                  DPRINTF("kvm_arch_handle_exit\n");
84.
85.
                  ret = kvm arch handle exit(cpu, run);
86.
                  break:
87.
88.
          } while (ret == 0);
89.
90.
          if (ret < 0) {
91.
              cpu dump state(cpu, stderr, fprintf, CPU DUMP CODE);
92.
              vm stop(RUN STATE INTERNAL ERROR);
93.
94.
95.
          cpu->exit_request = 0;
96.
          return ret;
97.
```

kvm_vcpu_ioctl执行时,调用的kvm函数是virt/kvm/kvm-main.c中的kvm_vcpu_ioctl.c函数.当传入参数为KVM_RUN时,最终会调用到vcpu_enter_guest函数,vcpu_enter_guest函数中调用了kvm_x86_ops->run(vcpu),在intel处理器架构中该函数对应的实现为vmx_vcpu_run,vmx_vcpu_run设置好寄存器状态之后调用VM_LAUNCH或者VM_RESUME进入guest vm,一旦发生vm exit则从此处继续执行下去.

```
[cpp] view plain copy  定在CODE上查看代码片  定派生到我的代码片
      static void __noclone vmx_vcpu_run(struct kvm_vcpu *vcpu)
 1.
 2.
 3.
          struct vcpu_vmx *vmx = to_vmx(vcpu);
         unsigned long debugctlmsr;
 4.
 5.
 6.
         /*...此处省略n行代码...*/
 7.
         vmx->__launched = vmx->loaded_vmcs->launched;
 8.
 9.
             /* Store host registers */
             "push %%" _ASM_DX "; push %%" _ASM_BP ";"
10.
              "push %%" _ASM_CX " \n\t" /* placeholder for guest rcx */
             "push %%" _ASM_CX " \n\t"
12.
              "cmp %%" _ASM_SP ", %c[host_rsp](%0) \n\t"
13.
14.
             "je 1f \n\t"
```

软件安装(31)
设计模式(12)
深度探索C++对象模型(17)
深入理解Linux内核(1)
数据结构与算法(60)
搜索引擎(2)
算法 每日一练(7)
算法导论(27)
文件系统(20)
虚拟化(11)
杂项(23)
随笔档案 (974)
2020年1月(1)
2019年2月(2)
2019年1月(1)
2018年8月(1)
2018年7月(1)
2018年6月(6)
2018年5月(7)
2018年4月(2)
2018年2月(3)
2017年12月(3)
2017年11月(1)
2017年9月(2)
2017年5月(2)
2017年4月(2)
2017年3月(3)
2017年2月(3)
2016年5月(4)
2016年4月(12)
2016年3月(3)
2016年2月(2)
2016年1月(6)

15. 16

17.

18. 19.

20. 21.

22.

23.

24. 25.

26.

27.

28. 29.

30.

31.

32

33.

34. 35.

36.

37. 38.

39. 40.

41.

42. 43.

44. 45.

46.

47. 48.

49. 50.

51.

52. 53.

54.

55.

56. 57.

58. 59.

60. 61.

62.

63. 64.

65. 66.

67.

68. 69.

70.

71.

72.

73.

74. 75.

76.

77.

78.

79.

80.

81. 82.

83.

84.

85. 86.

87.

88.

89.

```
"mov %%" _ASM_SP ", %c[host_rsp](%0) \n\t"
         _ex(ASM_VMX_VMWRITE_RSP_RDX) "\n\t"
        "1: \n\t"
        /* Reload cr2 if changed */
        "mov %c[cr2](%0), %%" _ASM_AX " \n\t"
        "mov %%cr2, %%" _ASM_DX " \n\t"
        "cmp %%" _ASM_AX ", %%" _ASM_DX " \n\t"
        "je 2f \n\t"
        "mov %%" ASM AX", %%cr2 \n\t"
        "2: \n\t"
        /* Check if vmlaunch of vmresume is needed */
        "cmpl $0, %c[launched](%0) \n\t"
        /* Load guest registers. Don't clobber flags. */
        "mov %c[rax](%0), %%" _ASM_AX " \n\t"
"mov %c[rbx](%0), %%" _ASM_BX " \n\t"
        "mov %c[rdx](%0), %%" _ASM_DX " \n\t"
        "mov %c[rsi](%0), %%" _ASM_SI " \n\t"
        "mov %c[rdi](%0), %%" _ASM_DI " \n\t"
        "mov %c[rbp](%0), %%" _ASM_BP " \n\t"
#ifdef CONFIG X86 64
        "mov %c[r8](%0), %%r8 \n\t"
        "mov %c[r9](%0), %%r9 \n\t"
        "mov %c[r10](%0), %%r10 \n\t"
        "mov %c[r11](%0), %%r11 \n\t"
        "mov %c[r12](%0), %%r12 \n\t"
        "mov %c[r13](%0), %%r13 \n\t"
        "mov %c[r14](%0), %%r14 \n\t"
        "mov %c[r15](%0), %%r15 \n\t"
#endif
        "mov %c[rcx](%0), %%" _ASM_CX " \n\t" /* kills %0 (ecx) */
        /* Enter guest mode */
        "jne 1f \n\t"
        __ex(ASM_VMX_VMLAUNCH) "\n\t"
        "jmp 2f \n\t"
        "1: " __ex(ASM_VMX_VMRESUME) "\n\t"
        "2: "
        /\!\!\!\!\!\!^{\star} Save guest registers, load host registers, keep flags ^{\star}/\!\!\!\!
        "mov %0, %c[wordsize](%%" ASM SP ") \n\t"
        "pop %0 \n\t"
        "mov %%" _ASM_AX ", %c[rax](%0) \n\t"
        "mov %%" ASM BX ", %c[rbx](%0) \n\t"
        __ASM_SIZE(pop) " %c[rcx](%0) \n\t"
        "mov %%" _ASM_DX ", %c[rdx](%0) \n\t"
        "mov %%" _ASM_SI ", %c[rsi](%0) \n\t"
        "mov %%" _ASM_DI ", %c[rdi](%0) \n\t"
"mov %%" _ASM_BP ", %c[rbp](%0) \n\t"
#ifdef CONFIG X86 64
        "mov %%r8, %c[r8](%0) \n\t"
        "mov %%r9, %c[r9](%0) \n\t"
        "mov %%r10, %c[r10](%0) \n\t"
        "mov %%r11, %c[r11](%0) \n\t"
        "mov %%r12, %c[r12](%0) \n\t"
        "mov %%r13, %c[r13](%0) \n\t"
        "mov %%r14, %c[r14](%0) \n\t"
        "mov %%r15, %c[r15](%0) \n\t"
#endif
        "mov %%cr2, %%" ASM AX " \n\t"
        "mov %%" ASM AX ", %c[cr2](%0) \n\t"
        "pop %%" ASM BP "; pop %%" ASM DX " \n\t"
        "setbe %c[fail](%0) \n\t"
        ".pushsection .rodata \n\t"
        ".global vmx return \n\t"
        "vmx_return: " _ASM_PTR " 2b \n\t"
        ".popsection"
          : : "c"(vmx), "d"((unsigned long)HOST_RSP),
        [launched]"i"(offsetof(struct vcpu_vmx, __launched)),
        [fail]"i"(offsetof(struct vcpu_vmx, fail)),
        [host_rsp]"i"(offsetof(struct vcpu_vmx, host_rsp)),
        [rax]"i"(offsetof(struct vcpu_vmx, vcpu.arch.regs[VCPU_REGS_RAX])),
        [rbx]"i"(offsetof(struct vcpu_vmx, vcpu.arch.regs[VCPU_REGS_RBX])),
        [rcx]"i"(offsetof(struct vcpu_vmx, vcpu.arch.regs[VCPU_REGS_RCX])),
        [rdx]"i"(offsetof(struct vcpu_vmx, vcpu.arch.regs[VCPU_REGS_RDX])),
        [rsi]"i"(offsetof(struct vcpu_vmx, vcpu.arch.regs[VCPU_REGS_RSI])),
```

```
90.
                                                    [rdi]"i"(offsetof(struct vcpu_vmx, vcpu.arch.regs[VCPU_REGS_RDI])),
2015年11月(3)
                                      91
                                      92.
                                            #ifdef CONFIG X86 64
2015年10月(7)
                                      93.
                                      94.
                                      95.
2015年9月(15)
                                      96.
                                      97.
2015年8月(10)
                                      98.
                                      99.
2015年7月(11)
                                     100.
                                            #endif
                                     102.
2015年6月(2)
                                     103.
                                     104.
2015年5月(38)
                                            #ifdef CONFIG X86 64
                                     105.
                                     106.
2015年4月(60)
                                     107.
                                     108.
                                            #else
2015年3月(71)
                                     109.
                                            #endif
2015年2月(3)
                                                      ) :
                                     112.
                                     113.
2015年1月(3)
                                     114.
                                                if (debugctlmsr)
                                     115.
2014年12月(119)
                                     116.
                                     117.
                                            #ifndef CONFIG X86 64
2014年11月(180)
                                     118.
                                     119.
2014年10月(69)
                                     121.
                                     122.
2014年9月(18)
                                     123.
                                     124.
2014年8月(109)
                                                 */
                                     125.
                                     126.
2014年7月(67)
                                     128.
                                     129.
2014年6月(85)
                                     130.
                                     131.
2014年5月(37)
                                     132.
                                     133.
                                     134.
文章分类(0)
                                     135.
                                     136.
metaq
                                     137.
                                     138.
nettv
                                     139.
                                     140.
                                     141.
UMI
                                     142.
                                     143.
                                     144.
linux
                                     145.
                                     146.
阮一峰的网络日志
```

```
淘宝内核组
```

```
阿里核心系统团队博客
算法牛人
v JULY v
分布式文件系统测试
acm之家
Linux开发专注者
```

```
[{\tt rbp}] \verb|"i" (offsetof ({\tt struct \ vcpu\_vmx}, \ {\tt vcpu.arch.regs[VCPU\_REGS\_RBP])) \ ,
              [r8]"i"(offsetof(struct vcpu_vmx, vcpu.arch.regs[VCPU_REGS_R8])),
               [r9]"i"(offsetof(struct vcpu_vmx, vcpu.arch.regs[VCPU_REGS_R9])),
               [r10]"i"(offsetof(struct vcpu_vmx, vcpu.arch.regs[VCPU_REGS_R10])),
               [r11]"i"(offsetof(struct vcpu_vmx, vcpu.arch.regs[VCPU_REGS_R11])),
               [r12]"i"(offsetof(struct vcpu_vmx, vcpu.arch.regs[VCPU_REGS_R12])),
               [r13]"i"(offsetof(struct vcpu_vmx, vcpu.arch.regs[VCPU_REGS_R13])),
               [r14]"i"(offsetof(struct vcpu_vmx, vcpu.arch.regs[VCPU_REGS_R14])),
               [r15]"i"(offsetof(struct vcpu_vmx, vcpu.arch.regs[VCPU_REGS_R15])),
               [cr2]"i"(offsetof(struct vcpu_vmx, vcpu.arch.cr2)),
               [wordsize]"i"(sizeof(ulong))
                 : "cc", "memory"
               , "rax", "rbx", "rdi", "rsi"
               , "r8", "r9", "r10", "r11", "r12", "r13", "r14", "r15"
               , "eax", "ebx", "edi", "esi"
           /* MSR IA32 DEBUGCTLMSR is zeroed on vmexit. Restore it if needed */
               update debugctlmsr(debugctlmsr);
            \,^{\star} The sysexit path does not restore ds/es, so we must set them to
            ^{\star} a reasonable value ourselves.
            * We can't defer this to vmx\_load\_host\_state() since that function
            ^{\star} may be executed in interrupt context, which saves and restore segments
            \star around it, nullifying its effect.
           loadsegment(ds, __USER_DS);
           loadsegment(es, __USER_DS);
           vcpu->arch.regs_avail = ~((1 << VCPU_REGS_RIP) | (1 << VCPU_REGS RSP)
                         | (1 << VCPU EXREG RFLAGS)
                         | (1 << VCPU_EXREG_CPL)
                         | (1 << VCPU_EXREG_PDPTR)
                         | (1 << VCPU EXREG SEGMENTS)
                         | (1 << VCPU EXREG CR3));
           vcpu->arch.regs_dirty = 0;
           vmx->idt_vectoring_info = vmcs_read32(IDT_VECTORING_INFO_FIELD);
           if (is guest mode(vcpu)) {
               struct vmcs12 *vmcs12 = get_vmcs12(vcpu);
               vmcs12->idt_vectoring_info_field = vmx->idt_vectoring_info;
               if (vmx->idt_vectoring_info & VECTORING_INFO_VALID_MASK) {
                   vmcs12->idt vectoring error code =
                       vmcs_read32(IDT_VECTORING_ERROR_CODE);
                   vmcs12->vm_exit_instruction_len =
147.
                       vmcs read32(VM EXIT INSTRUCTION LEN);
148.
149
150.
           vmx->loaded vmcs->launched = 1;
151.
153.
           vmx->exit reason = vmcs read32(VM EXIT REASON);
           trace kvm exit(vmx->exit reason, vcpu, KVM ISA VMX);
154.
155.
156.
           vmx complete atomic exit(vmx);
157.
           vmx_recover_nmi_blocking(vmx);
158.
           vmx_complete_interrupts(vmx);
159.
```

酷壳

C++11 中值得关注的几大变化 (详解)

iTech's Blog

Not Only Algorithm,不仅仅是算法,关注数学、算法、数据结构、程序员笔试面试以及一切涉及计算机编程之美的内容。

最新评论

1. Re:编写一个程序,从标准输入中读取若干string对象并查找连续重复出现的单词。所谓连续重复出现的意思是:一个单词后面紧跟着这个单词本身。要求记录连续重复出现的最大次数以及对应的单词

输入how cow,两个不同的单词,统计会出现问题。结果应该是没有连续出现的单词。

--想撸串的红杉树

2. Re:linux内核内存管理(zone_dma zone_normal zone_highmem)

你好,我想咨询您一个问题,32 位系统中,用户进程可以访问物理 内存的大小为3G,那么这3G有具 体的空间范围吗?是物理内存的0-3G还是什么,因为我看0-896M是 被内核线性映射,所以肯定表示0-3G,所...

--CV学习者

3. Re:spring中bean配置和bean注入

tql

--那么小晨呐

4. Re:如何使用jstack分析线程状态

thanks

--andyFly2016

5. Re:迪杰斯特拉算法介绍

不过有图挺好的,但我看到那里 看不懂了。

--何所倚

阅读排行榜

1. spring中bean配置和bean注入(13 8538)

介绍完初始化的流程,可以介绍IO在kvm和qemu中的处理流程了. 当Guest Vm进行IO操作需要访问设备时,就会触发vm exit 返回到vmx_vcpu_run, vmx保存好vmcs并且记录下 VM_ExIT_REASON后返回到调用该函数的vcpu_enter_guest, 在vcpu_enter_guest函数末尾调用了r = kvm_x86_ops->handle_exit(vcpu), 该函数对应于vmx_handle_exit函数(intel cpu架构对应关系可以查看vmx.c文件中static struct kvm_x86_ops vmx_x86_ops), vmx_handle_exit调用kvm_vmx_exit_handlers[exit_reason](vcpu),该语句根据exit_reason调用不同的函数,该数据结构定义如下:

```
static int (*const kvm_vmx_exit_handlers[])(struct kvm_vcpu *vcpu) = {
          [EXIT_REASON_EXCEPTION_NMI] = handle_exception,
 2.
          [EXIT_REASON_EXTERNAL_INTERRUPT]
 3.
                                                = handle_external_interrupt,
          [EXIT_REASON_TRIPLE_FAULT]
                                                = handle_triple_fault,
          [EXIT REASON NMI WINDOW]
                                           = handle_nmi_window,
 5.
         [EXIT REASON IO INSTRUCTION]
                                               = handle io,
 6.
        [EXIT REASON CR ACCESS]
                                                = handle cr,
        [EXIT_REASON_DR_ACCESS]
8.
                                                = handle dr,
         [EXIT REASON CPUID]
9.
                                                = handle cpuid,
          [EXIT REASON MSR READ]
                                                = handle rdmsr,
         [EXIT_REASON_MSR_READ]
[EXIT_REASON_MSR_WRITE]
                                               = handle_wrmsr,
11.
         [EXIT_REASON_PENDING_INTERRUPT] = handle_interrupt_window,
12.
         [EXIT REASON HLT]
13.
                                                = handle halt,
14.
         [EXIT_REASON_INVD]
                                      = handle_invd,
          [EXIT_REASON_INVLPG]
15.
                                          = handle_invlpg,
16.
          [EXIT REASON RDPMC]
                                                 = handle rdpmc,
17.
          [EXIT REASON VMCALL]
                                                = handle vmcall,
         [EXIT REASON VMCLEAR]
18.
                                                = handle vmclear,
19.
         [EXIT_REASON_VMLAUNCH]
                                                = handle_vmlaunch,
20.
        [EXIT_REASON_VMPTRLD]
                                                = handle_vmptrld,
         [EXIT_REASON_VMPTRST]
                                                = handle_vmptrst,
21.
22.
         [EXIT REASON VMREAD]
                                                = handle vmread,
23.
          [EXIT REASON VMRESUME]
                                                = handle vmresume,
         [EXIT_REASON_VMWRITE]
                                                = handle_vmwrite,
24.
25.
         [EXIT REASON VMOFF]
                                                = handle vmoff,
        [EXIT REASON VMON]
26.
                                                = handle vmon,
         [EXIT_REASON_TPR_BELOW_THRESHOLD] = handle_tpr_below_threshold,
27.
          [EXIT_REASON_APIC_ACCESS]
28.
                                                = handle_apic_access,
29.
          [EXIT REASON WBINVD]
                                                = handle wbinvd,
         [EXIT_REASON_WBINVD] = handle_wbinvd,

[EXIT_REASON_XSETBV] = handle_xsetbv,

[EXIT_REASON_TASK_SWITCH] = handle_task_switch,
30.
31.
        [EXIT REASON MCE DURING VMENTRY]
32.
                                               = handle machine check,
        [EXIT_REASON_EPT_VIOLATION] = handle_ept_violation,
[EXIT_REASON_EPT_MISCONFIG] = handle_ept_miscon
33.
                                             = handle_ept_misconfig,
34.
          [EXIT_REASON_PAUSE_INSTRUCTION] = handle_pause,
[EXIT_REASON_MWAIT_INSTRUCTION] = handle_invalid_op,
35.
36.
          [EXIT_REASON_MONITOR_INSTRUCTION] = handle_invalid_op,
37.
38. };
```

如果是因为IO原因导致的vm exit,则调用的处理函数为handle_io,handle_io的处理可以查看(http://blog.csdn.net/fanwenyi/article/details/12748613),该过程结束之后需要qemu去处理IO,这时候会返回到qemu,在kvm_cpu_exec中继续执行下去,看上面kvm_cpu_exec的代码,如果是因为IO原因返回到qemu,会调用kvm handle io函数.

```
switch (run->exit reason) {
            case KVM_EXIT_IO:
                DPRINTF("handle io\n");
3.
4.
                kvm_handle_io(run->io.port,
                               (uint8_t *)run + run->io.data_offset,
6.
                               run->io.direction,
7.
                              run->io.size,
8.
                              run->io.count);
9.
                ret = 0:
                break;
```

kvm_handle_io调用cpu_outb, cpu_outw等指令处理IO操作.

假设虚拟机是用raw格式的磁盘,则IO在qemu中处理时经过的函数栈如下所示:

- 2. 如何使用jstack分析线程状态(899 73)
- 3. maven快照版本和发布版本(2924 3)
- 4. C++ stringstream介绍,使用方法与例子(28518)
- 5. Linux用户空间与内核空间(理解高端内存)(27348)

评论排行榜

- 1. KVM虚拟机IO处理过程(一) ----G uest VM I/O 处理过程(9)
- careercup-递归和动态规划 9.10
 (7)
 - 3. 如何使用jstack分析线程状态(6)
 - 4. spring中bean配置和bean注入(6)
 - 5. 蜻蜓fm面试(6)

推荐排行榜

- 1. 如何使用jstack分析线程状态(20)
- 2. spring中bean配置和bean注入(1 9)
 - 3. 数据库索引原理及优化(12)
 - 4. maven快照版本和发布版本(8)
- 5. linux下的僵尸进程处理SIGCHLD 信号(8)

```
#0 bdrv_aio_writev (bs=0x55555629e9b0, sector_num=870456,
      qiov=0x555556715ab0, nb sectors=1,
      cb=0x55555570161b <ide sector write cb>, opaque=0x55555567157b8)
 3.
      #1 0x0000555555701960 in ide_sector_write (s=0x5555567157b8)
 5.
     at hw/ide/core.c:798
 6.
      #2 0x00005555557047ae in ide_data_writew (opaque=0x555556715740, addr=496,
 8.
      val=8995) at hw/ide/core.c:1907
 9.
      #3 0x00005555558d9e4c in portio write (opaque=0x5555565c0670, addr=0,
10.
      data=8995, size=2) at /home/dashu/kvm/gemu/gemu-dev-zwu/ioport.c:174
11.
      #4 0x00005555558e13d5 in memory_region_write_accessor (mr=0x5555565c0670,
      addr=0, value=0x7fffb4dbd528, size=2, shift=0, mask=65535)
12.
13.
      at /home/dashu/kvm/qemu/qemu-dev-zwu/memory.c:440
      \#5\ 0 \times 000005555558e151d in access with adjusted size (addr=0,
14.
15.
      value=0x7fffb4dbd528, size=2, access_size_min=1, access_size_max=4,
      access=0x5555558e1341 <memory_region_write_accessor>, mr=0x5555565c0670)
16.
17.
      at /home/dashu/kvm/qemu/qemu-dev-zwu/memory.c:477
18.
      \#6\ 0x00005555558e3dfb in memory_region_dispatch_write (mr=0x5555565c0670,
19.
      addr=0, data=8995, size=2)
20.
      at /home/dashu/kvm/qemu/qemu-dev-zwu/memory.c:984
21.
      \#7 0x00005555558e7384 in io_mem_write (mr=0x5555565c0670, addr=0, val=8995,
22.
      size=2) at /home/dashu/kvm/gemu/gemu-dev-zwu/memory.c:1748
23.
      #8 0x000055555586a18e in address_space_rw (as=0x555556216d80, addr=496,
      buf=0x7fffb4dbd670 "##", len=2, is_write=true)
24.
25.
      at /home/dashu/kvm/gemu/gemu-dev-zwu/exec.c:1968
26.
      #9 0x000055555586a474 in address_space_write (as=0x555556216d80, addr=496,
27.
      buf=0x7fffb4dbd670 "##", len=2)
      at /home/dashu/kvm/qemu/qemu-dev-zwu/exec.c:2030
28.
29.
      #10 0x00005555558d98c9 in cpu outw (addr=496, val=8995)
30.
      at /home/dashu/kvm/qemu/qemu-dev-zwu/ioport.c:61
```

bdrv_aio_writev最终调用bdrv_co_aio_rw_vector函数,该函数调用co = qemu_coroutine_create(bdrv_co_do_rw) 创建一个协程去执行bdrv_co_do_rw函数,bdrv_co_wo_rw函数的函数栈如下:

[cpp] view plain copy 是在CODE上查看代码片 是派生到我的代码片

```
\#1 0x000055555563653c in paio submit (bs=0x5555562a13d0, fd=10, sector num=2,
      qiov=0x555556715ab0, nb sectors=1,
      cb=0x5555556028b1 <bdrv_co_io_em_complete>, opaque=0x555556964e30, type=1)
 3.
      at block/raw-posix.c:825
 4.
      #2 0x0000555555636659 in raw aio submit (bs=0x5555562a13d0, sector num=2,
      qiov=0x555556715ab0, nb sectors=1,
      \verb|cb=0x5555556028b1 < bdrv_co_io_em_complete>|, opaque=0x555556964e30|, type=1|| \\
      at block/raw-posix.c:853
 8.
      #3 0x00005555556366c9 in raw_aio_readv (bs=0x5555562a13d0, sector_num=2,
      qiov=0x555556715ab0, nb sectors=1,
11.
      cb=0x5555556028b1 <bdrv_co_io_em_complete>, opaque=0x555556964e30)
      at block/raw-posix.c:861
13.
      #4 0x00005555556029b8 in bdrv_co_io_em (bs=0x5555562a13d0, sector_num=2,
     nb sectors=1, iov=0x555556715ab0, is write=false) at block.c:4038
14.
      #5 0x0000555555602a49 in bdrv_co_readv_em (bs=0x5555562a13d0, sector_num=2,
15.
16.
      nb sectors=1, iov=0x555556715ab0) at block.c:4055
      #6 0x00005555555fed61 in bdrv co do readv (bs=0x5555562a13d0, sector num=2,
17.
      nb_sectors=1, qiov=0x555556715ab0, flags=0) at block.c:2547
19.
      #7 0x00005555555fee03 in bdrv_co_readv (bs=0x5555562a13d0, sector_num=2,
      nb sectors=1, qiov=0x555556715ab0) at block.c:2573
      #8 0x0000555555637d8c in raw co readv (bs=0x55555629e9b0, sector num=2,
22.
      nb sectors=1, qiov=0x555556715ab0) at block/raw.c:47
      #9 0x00005555555fed61 in bdrv_co_do_readv (bs=0x55555629e9b0, sector_num=2,
23.
      nb sectors=1, qiov=0x555556715ab0, flags=0) at block.c:2547
      #10 0x00005555556023af in bdrv_co_do_rw
```

最终在paio_summit中会往线程池中提交一个请求thread_pool_submit_aio(pool, aio_worker, acb, cb, opaque),由调度器去执行aio_worker函数,aio_worker是真正做IO操作的函数,它通过pwrite和pread去读取磁盘.

当qemu完成IO操作后,会在kvm_cpu_exec函数的循环中,调用kvm_vcpu_ioctl重新进入kvm.以上阐述了IO操作在kvm和qemu中处理的整个过程.



刷新评论 刷新页面 返回顶部

注册用户登录后才能发表评论,请 <u>登录</u> 或 <u>注册</u>, <u>访问</u> 网站首页。

【推荐】超50万行VC++源码:大型组态工控、电力仿真CAD与GIS源码库 【推荐】腾讯云产品限时秒杀,爆款1核2G云服务器99元/年!

相关博文:

- ·gemu到kvm的处理,再到vm的运行
- ·kvm和qemu交互处理io流程
- ·KVM初始化过程
- ·KVM的初始化过程
- · QEMU-KVM 介绍2 概述
- » 更多推荐...

最新 IT 新闻:

- ·再下一城 寒武纪科创板IPO进入"已问询"状态
- ·小鹏汽车成立贸易公司,注册资本1000万元
- ·微软开始推送Windows 10 V2004: 修复大量错误、Bug
- ·美团外卖回应佣金话题:每单平台利润不到2毛钱 将长期帮助商户
- ·三星和谷歌合作打造下一代Pixel智能手机 最早可能今年推出
- » 更多新闻...