

# SSH jump host

From Gentoo Wiki

An alternative to SSH tunneling (/wiki/SSH\_tunneling) to access internal machines through gateway is using jump hosts (http://glandium.org/blo g/?p=308)

The idea is to use ProxyCommand to automatically execute ssh command on remote host to jump to the next host and forward all traffic through.

### Contents

- 1 Prerequisites
- 2 Dynamic jumphost list
  - 2.1 Multiple jumps
- 3 Static jumphost list
  - 3.1 Setup
  - 3.2 Usage
    - 3.2.1 Multiple jumps
- 4 Tips
- 5 External resources

## **Prerequisites**

- SSH access to the gateway machine and the internal one.
- Gateway machine has Netcat installed.

# Dynamic jumphost list

You can use the -J option to jump through a host:

user \$ ssh -J host1 host2

If usernames or ports on machines differ, specify them:

user \$ ssh -J user1@host1:port1 user2@host2:port2

#### Multiple jumps

The same syntax can be used to make jumps over multiple machines:

user \$ ssh -J user1@host1:port1,user2@host2:port2 user3@host3

# Static jumphost list

Static jumphost list means, that you know the jumphost or jumphosts you need, to reach a host. Therefore you can create a static jumphost 'routing' in ~/. ssh/config file. The advantage in comparison to the dynamic jumphost option is, that you don't have to provide the .ssh config on jumphosts between your machine and all the other jumphosts between you and the final host you want to jump to.

### Setup

#### FILE \ ~/.ssh/config ProxyJump Example

```
### First jumphost. Directly reachable
Host betajump
  HostName jumphost1.example.org
### Host to jump to via jumphost1.example.org
Host behindbeta
  HostName behindbeta.example.org
  ProxyJump betajump
```

### Usage

user \$ ssh behindalpha

If usernames on machines differ, specify them by modifing the correspondent Proxylump line:

ProxyJump otheruser@behindalpha

It works with scp command, too:

user \$ scp filename behindalphabeta:~/

Note

The colon and path at the end is needed so that scp recognizes it as remote.

### Multiple jumps

The same syntax can be used to make jumps over multiple machines:

#### FILE ~/.ssh/config Add this text

```
### First jumphost. Directly reachable
Host alphajump
  HostName jumphost1.example.org

### Second jumphost. Only reachable via jumphost1.example.org
Host betajump
  HostName jumphost2.example.org
  ProxyJump alphajump

### Host only reachable via alphajump and betajump
Host behindalphabeta
  HostName behindalphabeta.example.org
  ProxyJump betajump
```

user \$ ssh behindalphabeta

### Tips

To ease the connecting even further:

- Set these commands as shell aliases (https://en.wikipedia.org/wiki/Alias\_(command))
- To avoid typing passwords use OpenSSH keys (/wiki/SSH#Passwordless\_authentication)

### External resources

- SSH through jump hosts (http://glandium.org/blog/?p=308)
- net-misc/connect (https://packages.gentoo.org/packages/net-misc/connect) SSH Proxy Command -- connect.c (https://bitbucket.org/got oh/connect/wiki/Home)

Retrieved from "https://wiki.gentoo.org/index.php?title=SSH\_jump\_host&oldid=770785 (https://wiki.gentoo.org/index.php?title=SSH\_jump\_host&oldid=770785)"

- This page was last edited on 10 January 2019, at 18:02.
- Privacy policy (/wiki/Gentoo\_Wiki:Privacy\_policy)
- About Gentoo Wiki (/wiki/Gentoo\_Wiki:About)
- Disclaimers (/wiki/Gentoo\_Wiki:General\_disclaimer)

#### © 2001–2020 Gentoo Foundation, Inc.

Gentoo is a trademark of the Gentoo Foundation, Inc. The contents of this document, unless otherwise expressly stated, are licensed under the CC-BY-SA-3.0 (https://creativecommons.org/licenses/by-sa/3.0/) license. The Gentoo Name and Logo Usage Guidelines (https://www.gentoo.org/inside-gentoo/foundation/name-logo-guidelines.html) apply.