

# markpublish.yaml

Top level: `document`, `theme`, `parts`, optionally `templates_dir`. All paths are relative to the directory of this file. Build with `markpublish build [CONFIG_FILE] [OPTIONS]`.

## Structure

There are exactly two structural tiers. Anything deeper is carried by the Markdown file itself.

```
markpublish.yaml
├── document:      metadata and global switches
├── theme:         name of the theme
└── parts:        list of sections
    ├── part:     name of the section
    └── chapters: list of chapters
        └── file:  one Markdown file
            ├── # H1 chapter heading
            ├── ## H2 structure
            └── ### H3 inside the file
```

## document

Metadata and global layout toggles. Only `title` is required.

| Key                          | Default            | Meaning                                       |
|------------------------------|--------------------|-----------------------------------------------|
| <code>title</code>           | <i>required</i>    | Document title (cover page, header, filename) |
| <code>subtitle</code>        | –                  | Subtitle on the cover page                    |
| <code>summary</code>         | –                  | Summary / abstract on the cover page          |
| <code>author</code>          | –                  | Author name                                   |
| <code>date</code>            | <code>auto</code>  | Date (auto or today for the build date)       |
| <code>version</code>         | –                  | Version on the cover page and in the footer   |
| <code>status</code>          | –                  | Document status (e.g. Draft, Approved)        |
| <code>copyright</code>       | –                  | Copyright notice on the cover page            |
| <code>language</code>        | system language    | ISO code for static labels (de, en)           |
| <code>cover</code>           | <code>false</code> | Generate a cover page                         |
| <code>header / footer</code> | <code>true</code>  | Running headers and footers                   |

| Key             | Default              | Meaning                                                  |
|-----------------|----------------------|----------------------------------------------------------|
| document_toc    | full                 | Main table of contents: none, full or a depth            |
| part_toc        | full                 | Default for part divider pages: none, full or a depth    |
| chapter_toc     | full                 | Default for chapter divider pages: none, full or a depth |
| autonum_pattern | see <i>Numbering</i> | How numbers are built; slot 1 is the part here           |
| autonum_reset   | false                | Levels below start again at one when entered             |
| part_label      | from i18n            | Word before a part number (Part); "" drops it            |
| chapter_label   | from i18n            | Word before a chapter number (Chapter); "" drops it      |
| pagenum_reset   | false                | Restart page numbering per part or chapter               |

Custom fields under `document:` (`department: "R&D"`) reach the theme through the meta dictionary (`meta.at("department").value`). Static labels belong in `i18n.yaml`, not here.

## parts

A part brackets chapters and passes settings down to them. Without `break_before` it does not show itself.

| Key                | Default         | Meaning                                                   |
|--------------------|-----------------|-----------------------------------------------------------|
| part               | <i>required</i> | Name of the section                                       |
| chapters           | <i>required</i> | List of chapters in this section                          |
| toc_title          | part            | Title in the main table of contents                       |
| divider_title      | part            | Title on the divider page                                 |
| subtitle / summary | –               | Subtitle and summary on the divider page                  |
| break_before       | none            | divider, page OR none                                     |
| document_toc       | inherited       | Contribution to the main TOC; none hides the part         |
| part_toc           | inherited       | Local TOC on its own divider page                         |
| chapter_toc        | inherited       | Default for the divider pages of its chapters             |
| autonum_pattern    | inherited       | Numbers of its chapters; slot 1 is the chapter here       |
| autonum_reset      | inherited       | Chapters of this part start again at one                  |
| label              | from i18n       | Word before its own number                                |
| chapter_label      | inherited       | Word before the number of each of its chapters (Appendix) |
| pagenum_reset      | inherited       | Restart page numbering at the start of the part           |

## chapters

A chapter is one Markdown file. Its name comes from that file's # heading.

| Key                             | Default           | Meaning                                                                                     |
|---------------------------------|-------------------|---------------------------------------------------------------------------------------------|
| <code>file</code>               | <i>required</i>   | Path to the Markdown file                                                                   |
| <code>show_title</code>         | <code>true</code> | Show the file's H1 on the content page                                                      |
| <code>toc_title</code>          | file H1           | Title in the table of contents and running header                                           |
| <code>divider_title</code>      | file H1           | Title on the divider page                                                                   |
| <code>subtitle / summary</code> | –                 | Subtitle and summary on the divider page                                                    |
| <code>break_before</code>       | page              | divider, page OR none                                                                       |
| <code>document_toc</code>       | inherited         | Contribution to the main TOC ( <code>none</code> , <code>full</code> , <code>depth</code> ) |
| <code>chapter_toc</code>        | inherited         | Local TOC on its own divider page                                                           |
| <code>autonum_pattern</code>    | inherited         | Numbers <i>inside</i> the chapter; slot 1 is the H2 here                                    |
| <code>autonum_reset</code>      | inherited         | Headings of this chapter start again at one                                                 |
| <code>label</code>              | inherited         | Word before its own number (Appendix A: ...)                                                |
| <code>pagenum_reset</code>      | inherited         | Restart page numbering at the start of the chapter                                          |

## Inheritance

Everything marked *inherited* flows from the outside in; the innermost setting wins.

| document                     | parts[]                      | chapters[]                   |
|------------------------------|------------------------------|------------------------------|
| <code>autonum_pattern</code> | <code>autonum_pattern</code> | <code>autonum_pattern</code> |
| <code>autonum_reset</code>   | <code>autonum_reset</code>   | <code>autonum_reset</code>   |
| <code>document_toc</code>    | <code>document_toc</code>    | <code>document_toc</code>    |
| <code>part_toc</code>        | <code>part_toc</code>        | –                            |
| <code>chapter_toc</code>     | <code>chapter_toc</code>     | <code>chapter_toc</code>     |
| <code>pagenum_reset</code>   | <code>pagenum_reset</code>   | <code>pagenum_reset</code>   |
| <code>part_label</code>      | <code>label</code>           | –                            |
| <code>chapter_label</code>   | <code>chapter_label</code>   | <code>label</code>           |

## Numbering

A pattern describes the levels *below* the place it stands — so slot 1 shifts with that place.

| Level | under document | on a part | on a chapter |
|-------|----------------|-----------|--------------|
|-------|----------------|-----------|--------------|

|              |        |        |        |
|--------------|--------|--------|--------|
| Part         | slot 1 | -      | -      |
| Chapter (H1) | slot 2 | slot 1 | -      |
| H2           | slot 3 | slot 2 | slot 1 |
| H3           | slot 4 | slot 3 | slot 2 |
| ⋮            | ⋮      | ⋮      | ⋮      |
| H6           | slot 7 | slot 6 | slot 5 |

**Symbols:**  $1 \rightarrow 1, 2, 3 \cdot 01 \rightarrow 01, 02 \cdot a / A \rightarrow a, b / A, B \cdot i / I \rightarrow i, ii / I, II \cdot$   $\_$  level without a number  $\cdot +$  repeats the slot before it for every deeper level. Slots are separated by  $|$ ; everything else in a slot is a literal, reserved characters go in single quotes ('Article '1').

|             |                        |                                   |
|-------------|------------------------|-----------------------------------|
| on document | "_ 1 .1 +"             | part unnumbered · chapter 1 · 1.1 |
| on document | "I 1 .1 +"             | Part I · chapters 1, 2, 3 through |
| on a part   | "A .1 +"               | chapter A · A.1 · A.1.1           |
| on a part   | "'Article '1 ' ('1')'" | Article 1 · Article 1 (2)         |

Without a setting, `"_|1|.1|+"` applies: parts unnumbered, chapters 1, 1.1, 1.1.1.

The part number does **not** enter the chapter numbers; a part with `document_toc: "none"` gets none and consumes none. A notated `label` steps in front of the heading's number (Appendix A: Schema) without reaching the subheadings (A.1).

# Templates and Themes

Everything visible is controlled by a theme: typography, page layout, and static text. The built-in default theme `default` is provided for PDF.

## Where Themes Are Located

The first match wins — a theme is always loaded from exactly one source location and never merged across multiple locations. Which theme is used is determined by the `--theme` command-line option or the `theme:` setting in `markpublish.yaml` (default: `default`).

| Rank       | Location                                                                                                                                                      |
|------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1. User    | <code>~/.markpublish/templates/&lt;theme&gt;/</code> or user-specific AppData directory                                                                       |
| 2. Project | <code>--templates-dir</code> on CLI, <code>templates_dir:</code> in YAML, <code>MARKPUBLISH_TEMPLATES_DIR</code> , or <code>./templates/&lt;theme&gt;/</code> |
| 3. Package | Built-in standard theme <code>default</code>                                                                                                                  |

`markpublish templates` lists all templates available on the system along with their resolution rank and origin.

## Customizing a Theme

```
markpublish export-template default ./templates
```

This command copies the built-in theme files into your project directory, where resolution rank 2 automatically discovers and uses them on the next build. For PDF output, a theme directory contains:

- `template.typ`: Main Typst layout template defining page geometry, headers, footers, and styles
- `i18n.yaml`: Shared label definitions and localized strings across the theme
- `pdf/i18n.yaml`: Format-specific label definitions and string overrides for PDF
- `fonts/`: Optional custom font files (`.ttf`, `.otf`) loaded by Typst
- `assets/`: Image assets, logos, and vector icons

## Static Labels (i18n)

Labels resolve through a four-stage cascade; a lower level overrides only the keys it explicitly defines:

| Level            | File                                                |
|------------------|-----------------------------------------------------|
| 1. Application   | markpublish/i18n.yaml (application default strings) |
| 2. Theme         | <templates>/<theme>/i18n.yaml                       |
| 3. Target format | <templates>/<theme>/pdf/i18n.yaml                   |
| 4. Project       | ./i18n.yaml next to markpublish.yaml                |

Each file is organized by language code (de:, en:); the key "\*" applies to all languages. Level 4 belongs to the project: it allows overriding labels and localizing custom metadata fields (department: "Department"). Use markpublish labels --overridden OR markpublish labels --theme <theme> to inspect the cascade before building.

## Key CLI Commands

| Command                     | Key Options                                          | Description                             |
|-----------------------------|------------------------------------------------------|-----------------------------------------|
| markpublish build           | --theme, --target, -o, --<br>templates-dir           | Compile document to PDF                 |
| markpublish init            | [TARGET], --title, --lang                            | Set up a minimal starter project        |
| markpublish cheatsheet      | --lang, --theme, -o, --<br>templates-dir             | Generate this quick reference as PDF    |
| markpublish manual          | --lang, --theme, -o, --<br>templates-dir             | Generate the complete user manual       |
| markpublish templates       | --target, --templates-dir                            | List templates and lookup rank          |
| markpublish export-template | [THEME], [TARGET], --target                          | Export template files for customization |
| markpublish labels          | --theme, --target, --<br>templates-dir, --overridden | Inspect static labels and metadata      |