
Tipping point under latent confounding: Delta_crit(x) and tau_crit(x)
Solid black: Delta_crit(x) = |μ_obs(x)| / M(x), with the RIGOROUS M(x)=ybar=1 (Prop. 6.4.2) — note Delta_crit(x) = μ_obs(x) exactly once M(x) is constant. Blue: the corresponding τ_crit computed exactly (root-finding on the quadrature-based δ); pale dashed: Corollary 6.4.1 as currently written (first-order only) — note it degenerates near x=0.5, where it is uninformative.
1.00
0.75
0.50
0.25
0.00
0.00
0.25
0.50
0.75
1.00
Treatment quantile x
Delta_crit(x) [copula-ratio scale]
tau_crit(x), exact [Kendall's tau scale]
tau_crit(x), first-order (Cor. 6.4.1 as written)