# **Bode Plots**




Fig. 4 Tire cornering force frequency response under cyclic yaw.

ESE 505 & MEAM 513

Bruce D. Kothmann

VOL. 8, NO. 9, SEPTEMBER 1971

J. AIRCRAFT

2014-03-19

Synthesis of Tire Equations for Use in Shimmy and Other Dynamic Studies



# Response to Sinusoidal Input & Bode Plot

$$u(t) = \sin(\omega t)$$

$$y(t) = M \sin(\omega t + \phi)$$

$$G(j\omega) = Me^{j\phi}$$

Response to Unit Sinusoidal Input of Frequency  $\omega$  is Sinusoidal Output of Frequency  $\omega$  with Magnitude M and Phase Shift  $\phi$ , where  $G(j\omega)=Me^{j\phi}$ 

Bode Plot = Standard Way of Graphing 
$$G(j\omega)$$

$$\underline{M}$$
  $\hat{\underline{M}}$ 

Use Logarithmic Units for Magnitude

$$\hat{M} = 20\log_{10}(M)$$

$$0.5 - 6$$

Also Use Logarithmic Scaling for Frequency


## **Example: First-Order Lag**

$$G(s) = \frac{2}{s+1}$$

$$\omega \ll 1 \Rightarrow \begin{cases} \hat{M} = 6 \\ \phi = 0 \end{cases}$$


$$\omega \gg 1 \Rightarrow \begin{cases} \hat{M} = 6 - 20 \log_{10} \omega \\ \phi = -90^{\circ} \end{cases}$$

Draw Asymptotes & Sketch Actual Curves





#### First-Order Lag: Time → Frequency





ESE 505 & MEAM 513: Bode Plots

## Example: High-Pass Filter


$$G(s) = \frac{6s}{s+2} = \underbrace{3s}_{G_1} \underbrace{\frac{1}{0.5s+1}}_{G_2}$$

$$\hat{M} = 20\log_{10}(M_1M_2) = \hat{M}_1 + \hat{M}_{2}^{\text{gg}} + \hat{M}_{2}^{\text{gg}}$$

$$\phi = \phi_1 + \phi_2$$


$$\hat{M}_1 = 9 + 20\log_{10}(\omega)$$
$$\phi = +90^{\circ}$$

Draw Asymptotes For Each Term, Then Sum & Sketch Actual Curves





## High-Pass Filter : Time → Frequency






## Example: Second-Order System

$$G(s) = \frac{0.4}{s^2 + s + 4}$$

$$\omega \ll 2 \Rightarrow \begin{cases} \hat{M} = -20 \\ \phi = 0 \end{cases}$$


$$\omega = 2 \Rightarrow \begin{cases} \hat{M} = 20\log_{10}(0.2) = -14\\ \phi = -90^{\circ} \end{cases}$$

$$\omega \gg 2 \Rightarrow \begin{cases} \hat{M} = -8 - 40 \log_{10} \omega \\ \phi = -180^{\circ} \end{cases}$$






# Second-Order System : Time → Frequency






ESE 505 & MEAM 513: Bode Plots

## Damping Ratio Effect on Bode Plot (Magnitude)





# Damping Ratio Effect on Bode Plot (Phase)





#### Example: Notch Filter


$$G(s) = \frac{s^2 + 0.2s + 1}{s^2 + s + 1}$$

$$\omega \ll 1 \Rightarrow \begin{cases} \hat{M} = 0 \\ \phi = 0^{\circ} \end{cases}$$

$$\omega = 1 \Rightarrow \begin{cases} \hat{M} = 20\log_{10}(0.2) = -14 \\ \phi = 0^{\circ} \end{cases}$$

$$\omega \gg 1 \Longrightarrow \begin{cases} \hat{M} = 0 \\ \phi = 0^{\circ} \end{cases}$$

Asymptotes Not Very Useful Here—Need Details!




BDK: 2014-03-19

Bode Diagram



#### General Approach



 $N_Z$ = number of zeros @ origin (negative for poles @ origin)  $K_o$  = Gain When All Other Terms Written In Form Shown




# Example: 3<sup>rd</sup>-Order System with Zero

$$G(s) = \frac{50s + 50}{s(s^2 + s + 25)}$$

$$G(s) = \frac{2}{s} (s+1) \frac{1}{\left(\frac{s^2}{5^2} + 2(0.1)\frac{s}{5} + 1\right)}$$
Slope of -20db/dec
Passing Through
Zero db @ 2 rps

Lightly Damped
Second-Order Pole
@ 5rps

Zero @ 1rps




BDK: 2014-03-19



#### Space Telescope

THE Space Telescope, shown in Fig. 1, has a 2.4-m telescope designed to allow scientists to observe the universe with a clarity and to distances never before achieved.




 $http://www.gsfc.nasa.gov/gsfc/service/gallery/fact\_sheets/spacesci/hst3-01/hubble\_space\_telescope\_systems.htm$ 



ESE 505 & MEAM 513 : Bode Plots

# Space Telescope Pointing Controller






ESE 505 & MEAM 513 : Bode Plots

## Space Telescope Dynamics

1) Structural modes: The solar array and optical telescope assembly modes have large modal coefficients. For example, the value of the solar array inertia about the Space Telescope center of mass is almost one-half that of the Space Telescope centerbody, which comprises the support systems module and optical telescope assembly. The control system sample rate and compensation are chosen to stabilize the modes. The command generator shapes maneuvers to limit structural excitations during maneuvers.





# Using Bode Plot to Understand Dynamics


$$\frac{\theta}{Q} = \left[\frac{1}{I_V s^2}\right] \left[\frac{(1 - K_B)s^2 + 2\varsigma\omega_B s + \omega_B^2}{s^2 + 2\varsigma\omega_B s + \omega_B^2}\right]$$
Usual Rigid-
"Filter" To Account for

Usual Rigid-Body Response

Structural Vibration


 $K_{\rm B} \sim 0.5$  is an Easily Excited Mode  $\zeta \sim 0.02$  (or Less) is Typical!

(Plot has  $\omega_n=1$ ; Actual Space Station Modes Much Lower Frequency)





# Bode Plot Paper (Magnitude)





ESE 505 & MEAM 513 : Bode Plots

### Bode Plot Paper (Phase)

