
Separate Chaining:

The idea is to make each cell of hash table point to a linked list of records that have same hash function value.

Let us consider a simple hash function as "**key mod 7**" and sequence of keys as 50, 700, 76, 85, 92, 73, 101.



Open Addressing

Like separate chaining, open addressing is a method for handling collisions. In Open Addressing, all elements are stored in the hash table itself. So at any point, the size of the table must be greater than or equal to the total number of keys (Note that we can increase table size by copying old data if needed).


Open Addressing is done in the following ways:

a) Linear Probing: In linear probing, we linearly probe for next slot. For example, the typical gap between two probes is 1 as seen in the example below.

Let hash(x) be the slot index computed using a hash function and S be the table size

```
If slot hash(x) % S is full, then we try (hash(x) + 1) % S If (hash(x) + 1) % S is also full, then we try (hash(x) + 2) % S If (hash(x) + 2) % S is also full, then we try (hash(x) + 3) % S
```

Let us consider a simple hash function as "key mod 7" and a sequence of keys as 50, 700, 76, 85, 92, 73, 101.



b) Quadratic Probing We look for i²'th slot in i'th iteration.

```
let hash(x) be the slot index computed using hash function. If slot hash(x) % S is full, then we try (hash(x) + 1*1) % S If (hash(x) + 1*1) % S is also full, then we try (hash(x) + 2*2) % S If (hash(x) + 2*2) % S is also full, then we try (hash(x) + 3*3) % S
```

c) <u>Double Hashing</u> We use another hash function hash2(x) and look for i*hash2(x) slot in i'th rotation.

```
let hash(x) be the slot index computed using hash function. If slot hash(x) % S is full, then we try (hash(x) + 1*hash2(x)) % S If (hash(x) + 1*hash2(x)) % S is also full, then we try (hash(x) + 2*hash
```

Comparison of above three:

Linear probing has the best cache performance but suffers from clustering. One more advantage of Linear probing is easy to compute.

Quadratic probing lies between the two in terms of cache performance and clustering. Double hashing has poor cache performance but no clustering. Double hashing requires more computation time as two hash functions need to be computed.

S.1	No. Separate Chaining	Open Addressing
1.	Chaining is Simpler to implement.	Open Addressing requires more computation.
2.	In chaining, Hash table never fills up we can always add more elements to chain.	
3.	Chaining is Less sensitive to the has function or load factors.	Open addressing requires extra care to avoid clustering and load factor.
4.	Chaining is mostly used when it is unknown how many and how frequences where the control is the control in the control is the control in the control in the control in the control is the control in the	Open addressing is used when the ntly frequency and number of keys is known.
5.	Cache performance of chaining is not good as keys are stored using linked list.	Open addressing provides better cache performance as everythin is stored in the same table.
6.	Wastage of Space (Some Parts of has table in chaining are never used).	In Open addressing, a slot can be used even if an input doesn't ma to it.
7.	Chaining uses extra space for links.	No links in Open addressing