### Implementing Jump and Crouch in the Python API

- the files which need to be modified are split into two groups
  - server side (dhewm3 engine)
  - client side (python)
- server side files: neo/game/Player.cpp, neo/game/Player.h, neo/game/ai/pybot.cpp neo/game/ai/pybot.h
- client side files: python-bot/botbasic.py, python-bot/botcache.py, python-bot/botlib.py, python-bot/python\_doommarine.py

## Implementing Jump and Crouch in the Python API

- these are guidelines on how to implement stepUp (crouch and jump)
- the notes will require you to add extra code on the server side, the client should be complete

# Test code: python\_doommarine.py

add this code somewhere appropriate in python\_doommarine.py and ensure that it is called!

python-bot/python\_doommarine.py

```
def test_crouch_jump (b):
    b.reset ()
    b.stepup (-2, 3*12)
    b.select (['move'])
    # time.sleep (2)
    b.stepup (100, 4*12)
    b.select (['move'])
```

## Test code: python\_doommarine.py

- can see the new method stepvec which is a Z-axis movement
  - in doom3 the Z-axis movement, results in the player self returning back to the neutral position
  - gravity pulls the player back to the ground, and likewise happens if the player crouches

### stepup in botlib.py

add stepup after the method right

python-bot/botlib.py

```
#
# stepup - makes the bot jump or crouch.
#

def stepup (self, velup, dist):
    return self._cache.stepup (velup, dist)
```

# stepup in botlib.py

#### python-bot/botcache.py

```
#
# stepup -
#

def stepup (self, velup, dist):
    self.delpos (self.me ())
    return self._basic.stepup (velup, dist)
```

#### python-bot/botbasic.py

#### python-bot/botbasic.py

```
#
# stepup -
#

def stepup (self, velocity, dist):
    l = "step_up %d %d\n" % (velocity, dist)
    if debug_protocol:
        print "requesting a", l
    self.s.send (1)
    l = self.getLine ()
    if debug_protocol:
        print "doom returned", l
    return int (1)
```

## Server side changes

■ add the declaration of the method stepUp

neo/game/Player.h

```
bool isVisible (idEntity *enemy);
int Fire (bool firing);
int Ammo (void);
int stepUp (int vel, int dist);
int Turn (int angle, int angle_vel);
int GetYaw (void);
void doTurn (int angle);
void select (int bitmask);
int ChangeWeapon (int new_weapon);
```

#### stepUp implementation inside Player.cpp

#### neo/game/Player.cpp

```
/*
=========
idPlayer::stepUp (crouch or jump)
=========
* /
int idPlayer::stepUp (int vel, int dist)
  int old = (int) usercmd.upmove;
  // gameLocal.Printf( "stepUp %d %d0, vel, dist );
 usercmd.upmove = (signed char) vel;
 usercmd.forwardmove = 0;
 usercmd.rightmove = 0;
 buttonMask = 0;
 buttonMask = BUTTON_RUN;
 pulseCount.set run (dist);
 usercmd.buttons | = BUTTON_RUN;
  gameLocal.usercmds[entityNumber] = usercmd;
  return old;
```

### stepUp implementation inside Player.cpp

- note that inorder for the stepUp to function correctly it will require changes made to the Think method in the same file
- you should assign

```
usercmd.upmove = 0;
gameLocal.usercmds[entityNumber].upmove = 0;
```

when get\_run () == 0

#### stepUp implementation inside Player.cpp

- now you need to make changes to pybot.cpp to interpret the step\_up string passed by python and decode its two parameters
  - follow though the reload\_weapon changes to see which classes need to be changed
- it might be useful to examine the stepVec method and how it is implemented
  - your stepUp method should be similar