Object-Oriented Programming

Iuliana Bocicor

RAI

Smart pointers in STL

Object-Oriented Programming

Iuliana Bocicor iuliana@cs.ubbcluj.ro

Babes-Bolyai University

2017

Overview

Object-Oriented Programming

Iuliana Bocicor

RAII

Smart pointers

RAII

RAII I

Object-Oriented Programming

Iuliana Bocicor

RAII

Smart pointers in STL • **RAII** = Resource Acquisition Is Initialization.

Resources

- E.g.: memory, files, sockets, database connections.
- Resources are acquired before use and then released after one has finished working with them (preferably, they should be released as soon as possible).
- Failing to release a resource can cause leaks and even crashes.
- RAII is used to avoid resource leaks and to write exceptionsafe code.

Example of resource leak I

Object-Oriented Programming

> Iuliana Bocicor

RAII

```
void resourceLeak()
 try
     int* a = new int{ 2 };
     throw std::exception { "Hello! An exception
         has occured!\n" };
     delete a;
 catch (std::exception& e)
     cout << e.what();</pre>
```

Example of resource leak II

Object-Oriented Programming

> Iuliana Bocico

RAII

Smart pointers in STL

• How can this be solved?

- One solution (workaround): clean up in the catch block. **?**Why is this not a good solution?
- Another solution: using RAII.

The idea I

Object-Oriented Programming

Iuliana Bocicor

RAII

- The compiler automatically calls:
 - constructors to initialize objects;
 - destructors, when the objects' scope is finished.
- When creating an object, we take responsibility for the resources in it. The constructor is responsible with resource allocation.
- The destructor does the clean up: the resource should be deallocated in the destructor.

The idea II

Object-Oriented Programming

Iuliana Bocicor

RAII

- As the compiler automatically calls constructors and destructors, the resource will correctly be managed.
- In this way, there will be no resource leaks.
- Advantages over garbage collection (from other programming languages):
 - RAII offers automatic management for different kinds of resources, not just memory.
 - The runtime environment is faster, as there is no separate mechanism involved (like the garbage collector).

How is it done?

Object-Oriented Programming

> Iuliana Bocicor

RAII

Smart pointer in STL

- Create a wrapper for your object using resource allocation: allocation in constructor, deallocation in destructor.
- Use the wrapper object (directly) wherever you need the object.
- The resource will be deallocated when the wrapper's scope is left.

DEMO

RAII for pointers (*Lecture8_demo* - SmartPointer, SmartPointerTemplate).

RAII in STL

Object-Oriented Programming

> Iuliana Bocicor

RAII

- You have been already using RAII!
- When an object of type ifstream or ofstream, the constructor will automatically open the file.
- When the object gets destroyed, the destructor automatically closes the file.
- The STL containers manage memory using the RAII programming idiom. Remember your dynamic vector?
- There are "smart pointers" defined in STL, which use RAII for "smart" memory management.

Smart pointers in STL I

Object-Oriented Programming

> Iuliana Bocicor

RAI

- In modern C++, raw pointers are used only in certain cases: "small code blocks of limited scope, loops, or helper functions where performance is critical and there is no chance of confusion about ownership" (https://msdn.microsoft.com/en-us/library/hh279674.aspx).
- Smart pointers are used instead.
- Smart pointers are class templates.
- A smart pointer object is declared on the stack and initialized with a raw pointer. When it goes out of scope, its destructor is invoked.

Smart pointers in STL II

Object-Oriented Programming

Iuliana Bocicor

RAI

- The smart pointer owns the raw pointer ⇒ it is responsible for it (memory deallocation).
- Objects are automatically cleaned up when the smart pointers go out of scope or are set to point at something else or nothing they get deleted when nobody is interested in them any more.
- STL smart pointers defined in the std namespace, in the header <memory>.

Smart pointers in STL III

Object-Oriented Programming

> Iuliana Bocico

RAII

- There ar 3 types of smart pointers in STL:
 - std::unique_ptr
 - std::shared_ptr
 - std::weak_ptr

std::unique_ptr |

Object-Oriented Programming

Iuliana Bocicor

RAI

- Such a smart pointer owns its object uniquely.
- It retains *exclusive ownership* of the object, it does not share the object.
- It is impossible for two unique_ptr objects to own the same object.
- It cannot be copied. **?** Could such an object be passed by value?

std::unique_ptr ||

Object-Oriented Programming

Iuliana Bocicor

RAI

Smart pointers in STL

- It can be moved to a new owner: the resource is transferred to the new owner.
- When it goes out of scope, the owned object is destroyed.
- It should be constructed with the make_unique function.

DEMO

unique_ptr (*Lecture8_demo_Smart_pointers_STL* - exampleUniquePtr).

std::shared_ptr |

Object-Oriented Programming

> Iuliana Bocicor

RAI

- Retains shared ownership of the object.
- Several shared_ptr object may own the same object.
- Uses reference counting: when multiple shared pointers own the same object, these are keeping track of how many "copies" there are.
- The owned object is deleted only when the last remaining owning shared_ptr is destroyed or have given up ownership (has been reset).

std::shared_ptr ||

Object-Oriented Programming

> Iuliana Bocicor

RAI

Smart pointers in STL

- It can be copied and moved (move transfers ownership).
- shared_ptr has more overhead than unique_ptr (because of the internal reference counting), therefore, whenever possible, prefer unique_ptr.
- It should be constructed with the make_shared function.

DEMO

shared_ptr (*Lecture8_demo_Smart_pointers_STL* - example-SharedPtr).

std::weak_ptr |

Object-Oriented Programming

Iuliana Bocicor

RAI

- Used to access the underlying object of a shared_ptr without causing the reference count to be incremented.
- Is usually used to avoid dependency cycles.
 E.g.: 2 classes Team and Member
 - A team has pointers to its members.
 - Each member can have a pointer to the team it belongs to.
 - **?** If all pointers (to members and to team) are shared_ptr, what happens when the team goes out of scope? (Answer: memory leak but how and why?)
 - Therefore, the members should have a weak pointer to their team.

std::weak_ptr ||

Object-Oriented Programming

> Iuliana Bocicor

RAI

Smart pointers in STL

- The underying object in a weak_ptr can still be deleted even though there is a weak_ptr reference to it.
- weak_ptr can be used to create a shared_ptr.

DEMO

 $weak_ptr \quad (\textit{Lecture8_demo_Smart_pointers_STL} \quad - \quad teamMembersSharedPtr, \; exampleWeakPtr).$

Advantages of smart pointers

Object-Oriented Programming

> Iuliana Bocicor

RAI

Smart pointers in STL

- Smart pointes increase productivity and improve the robustness of the program.
- The programmer does not need to be concerned with memory management (provided the smart pointers are used correctly).
- They help in avoiding memory leaks and writing exceptionsafe code.

Smart developers use smart pointers. (Kate Gregory)

Homework I

Object-Oriented Programming

Iuliana Bocicor

RAI

- Write an application to keep the aircraft evidence in a country.
- Each aircraft has a unique identifier and a model, is suitable only for certain activities (e.g. public transportation, medical emergencies, leisure time, military) and can reach a certain maximum altitude.
- An aircraft can be one of the following three: helicopter, plane or hot air balloon.

Homework II

Object-Oriented Programming

> Iuliana Bocicor

RAI

Smart pointers in STL

A helicopter:

- has the following additional characteristic: isPrivate, specifying whether the helicopter belongs to the state or to a private entity.
- is suitable for activities like: military, medical emergencies, public transportation and leisure time (only if it is private).
- can reach a maximum altitude of 12 km.

A plane:

- has the following additional characteristics: isPrivate, specifying whether the plane belongs to the state or to a private entity and main wings (the plane can be either monoplane or biplane).
- is suitable for activities like: military, public transportation and leisure time (only if it is biplane).
- can reach a maximum altitude of 26 km.

Homework III

Object-Oriented Programming

Iuliana Bocicor

RAI

Smart pointers in STL

A hot air balloon:

- has the following additional characteristics: weight limit, specifying the maximum weight limit for the balloon.
- is suitable for activities like: leisure time.
- can reach a maximum altitude of 21 km.
- The application should allow the following:
 - Add any type of aircraft.
 - Display all aircraft which can be used for a certain activity and save them to a file having the activity's name.
 - Diplay all aircraft which can reach at least a given altitude.