

CloudICP V100R023C00

Interface Reference

RESTful + FunctionalComponents

Contents

Overview

Agent Server Interfaces (RESTful)

About This Document

Intended Audience

Security Statement

Symbol Conventions

Change History

V100R023C00

V600R019C00SPC680

V600R019C00SPC640

V600R019C00SPC631

V600R019C00SPC630

V100R022C00

V600R019C00SPC590

V100R021C00

V600R019C00SPC500

V600R019C00SPC580

V600R019C00SPC309

V600R019C00

V600R019C00SPC100

V600R019C00

V600R006C10

V600R006C10SPC100

V600R006C10

V200R001C80

V200R001C80SPC703

V200R001C80SPC702

V200R001C80SPC701

V200R001C80SPC700

V200R001C80SPC600

V200R001C80SPC500

V200R001C80SPC300

V200R001C80SPC200

V200R001C80SPC100

V200R001C80

V200R001C60

V200R001C60SPC100

V200R001C60

Basic Interfaces and Events

Interfaces

Online Agent: onlineagent

Logging In

Forcibly Logging In

Logging In Through CAC Authentication

Forcibly Logging In Through CAC Authentication

Detecting Heartbeat

Querying Configured Skill Queues

Querying Configured Skill Queues of the Specified Agents

Setting Automatic Answering

Resetting Skill Queues

Setting Idle

Setting Busy

Canceling the Busy State

Requesting Rest

Canceling Rest

Entering the Work State

Quitting the Work State

Changing the Password (Extended)

Setting Automatic Entry to Idle State

Sending a Note (Extended)

Logging Out

Forcibly Logging Out

Forcibly Logging Out with a Cause Code

Getting Agent Status

- Changing the Busy Reason Code
- Unified Logging In (Public Cloud)
- Voice Call: voicecall
 - Making an Outgoing Call
 - Answering a Call
 - Making an Internal Call
 - Answering a Call in the Phone Linkage State
 - Rejecting a Call in the Phone Linkage State
 - Restoring a Line in the Phone Linkage State
 - Asking for Internal Help
 - Muting an Ongoing Call
 - Unmuting a Muted Call
 - Holding a Call
 - Unholding a Call
 - Transferring a Call
 - Canceling a Transfer
 - Performing Two-Stage Dialing (Extended)
 - Making a Three-Party Call
 - Connecting a Held Call
 - Disconnecting a Call of a Specified ID
 - Dropping a Call
 - Requesting an Agent for Call Pickup
 - Setting the Customer Level
 - Internal Call to a Skill Queue
- Text Message: textchat
 - Responding to a Text Chat
 - Sending a Text Message
 - Requesting an Internal Text Chat
 - Transferring a Text Chat
 - Terminating a Text Chat
 - Rejecting a Text Chat
 - Sending Content to a Customer Without Call
 - Confirming the Receiving of Non-real-time Call Content
 - Confirming the Receiving of a Text Message
 - Obtaining Call Content
 - Obtaining Call Information
 - Querying Content of Interaction Without Call Between an Agent and Customers
 - Uploading a Rich Media File
 - Downloading a Rich Media File
 - Initiating a Three-Party Help Call
- Recording and Playback: recordplay
 - Starting Playing an Announcement
 - Pausing an Announcement
 - Resuming an Announcement
 - Fast Forwarding
 - Rewinding
 - Stopping Playing the Announcement
 - Query Recording
 - Query RecordingEx
- Queue Device: queuedevice
 - Querying Access Code Information of a VDN
 - Querying IVR Information of a VDN
 - Obtaining the Number of Users in a Configured Skill Queue
 - Obtaining the Number of Users in a Skill Queue
 - Querying the Skill Queues to Which a Specified Agent Has Logged In
 - Obtaining the Skill Queue Information of a Specified VDN
 - Obtaining the Skill Queue Information of the Home VDN of an Agent
 - Obtaining the Number of Users in a Specified Skill Queue
 - Querying the Statistics About a Set of Skill Queues
 - Querying the Statistics About the Next Set of Skill Queues of the Home VDN of an Agent
 - Querying the Device Status
 - Querying the Sub-media Type of a Skill Queue
 - Adding Queue Monitoring
 - Stopping Queue Monitoring
- Agent Group: agentgroup
 - Querying Information About All Agent Groups of the Home VDN
 - Querying Group Information About a Specified Agent
 - Querying Information About All Online Agents of the Home VDN
 - Querying Agent Information About the Group by A Supervisor
 - Querying Agent Information About the Group
 - Querying Detailed Information About A Specified Agent
 - Querying Whether an Agent Is An Administrator
 - Querying Whether an Agent Is an Inspection Supervisor

Querying Whether an Agent Is A Report Administrator
Querying Whether an Agent Is Authorized with Co-Group Pickup Permission
Querying Whether an Agent Is a Supervisor
Querying Whether an Agent Is an Inspector
Querying Whether an Agent Is Authorized with Outbound Permission
Querying Whether an Agent Is Authorized with Internal Call Permission
Querying State Information About All Agents of the Home VDN
Querying Information About Idle Agents
Querying All Resting Reason Codes of the Home VDN
Querying Agent Information About a Specified State
Querying State Information About Agents That Have Logged In to the Platform
Querying Information About Agents in Text Chat
Querying Agent Information About a Configured Skill Queue
Querying Information About Agents That Have Signed In to a Skill Queue
Querying Phone Numbers of Agents That Have Logged In to the Home VDN
Querying WAS Configuration Names of All Agents of the Home VDN
Querying the Work ID List of a Configured Skill Queue
Querying Agent Resting Information
Querying the State and Skills of a Specified Agent Before Logging In
Querying Information About Specified Agents in Batches
Performing a Fuzzy Query of Online Agents by Using a Keyword
Querying the Work ID of an Agent Based on a Phone Number
Batch Querying IP addresses of Agents
Querying the Work ID Using the Third-Party Account
Checking Whether an Agent Has the Permission to Download Files Based on the Agent ID

Call Data: calldata

Call-Associated Data

- Configuring Call-Associated Data
- Configuring Call-Associated Data (Expanded)
- Configuring Call-Associated Data (Bean Expansion Interface)
- Querying Call-Associated Data (Bean Expansion Interface)
- Querying Call-Associated Data

Held Calls

- Querying the List of Held Calls
- Querying the List of Held Calls of a Specified Agent (Expanded)
- Querying the Number of Held Calls of a Specified Agent

Querying Call Information

Querying Call Information Before Answering a Call
Querying Call Information About the Home VDN
Querying Information About All Call IDs
Querying Call Information by Call ID
Querying Call IDs of a Specified Agent
Querying the Number of Current Calls of an Agent
Querying All Call Information of a Specified Agent
Querying Current Call Statistics Information About an Agent
Querying Information About Queuing Calls in a Specified Skill Queue
Querying Whether the Agent Is Processing or Is to Process a Call
Querying Information About Queuing Calls in a Specified IVR System
Querying Information About Queuing Calls in a Private Queue
Querying Phone Number Information About Parties Making Calls on a Specified Agent
Querying the Number of Calls in a Specified IVR System
Querying Whether an Agent Has the Permission to Release a Specified Call
Querying the Geographical Location Based on the Calling Number
Updating the Geographical Location Based on the Calling Number
Querying MSD Data by Call ID

Agent Event: agentevent

AGENT POLL Mode

- Obtaining the Events of a Single Agent in Polling Mode (Normal)

Query Monitoring: querymonitor

Querying the Local System Time of the Main CCS Server
Querying the Server Version
Search System State Information
Querying Cluster Service Information
Querying the Service Cluster Information About a Specified Agent
Querying the Service Cluster Information About All Agents
Querying the Information About a Specified Service Cluster
Querying the Traffic Statistics Information About a Specified Skill Queue
Configuring the Effectiveness of the Agent Handshake Timer
Setting the Number of Instant Calls That an Agent can Handle Simultaneously

Real-Time Quality Control: qualitycontrol

Inserting
Listening On
Intercepting

- Starting Monitoring
- Stopping Monitoring
- Stopping Whispering
- Requesting Whispering
- Switching Among Whispering, Listening, and Inserting
- Canceling Listening and Inserting
- Indicating an Agent in Busy State Forcibly
- Indicating an Agent in Idle State Forcibly
- Forcibly Logging Out
- Releasing a Call Forcibly
- Screen Inspection
 - Querying Inspection Tasks
 - Reporting the Port Number of Screen Recording
 - Start Screen Inspection
 - Stopping Screen Inspection
 - Starting and Stopping Screen Recording Playback
 - Deleting Real-Time Screen Inspection, Immediate Screen Recording, and Scheduled Screen Recording Tasks
 - Notifying the CCS of the Startup Result of a Screen Recording or Screen Inspection Task
 - Deleting an Inspection Task
- Querying Information About All Agents That Can Be Monitored
- Adjusting the Skill Queue of a Specified Agent
- Applying for Joining a Multimedia Conference
- Obtaining the Recording Duration
- Generating the Recording Download Path
- Downloading a Recording File
- Forcibly Showing Busy with a Reason Code
- Multimedia Conference: multimediaconf
 - Applying for a Multimedia Conference
 - Inviting an Agent to Join a Multimedia Conference
 - Reporting a Multimedia Conference Joining Result
 - Stopping a Multimedia Conference
 - Querying the Multimedia Conference Status
- Conference Call: agentconf
 - Applying for a Conference Call
 - Answering a Conference Call
 - Rejecting a Conference Call
 - Exiting a Conference Call
 - Releasing a Conference Call
 - Placing a Participant on Hold
 - Unholding a Participant
 - Applying for Conference Extension by a Conference Chair
 - Transferring the Conference Chair Rights
 - Batch Inviting Participants
 - Batch Deleting Participants
 - Modifying a Participant Attribute
 - Playing Announcement for a Conference Call
 - Stopping Announcement for a Conference Call
 - Playing Announcement for a Conference Call Channel
 - Stopping Playing Announcement for a Conference Call Channel
 - Changing the Number of Conference Participants
 - Batch Querying Conference Information
 - Querying a Call ID of a Participant
 - Querying the Conference ID of an Ongoing Conference Call on the VDN
- Emailcall: emailcall
 - Answering a Call
 - Ending a Call
 - Replying to an Email Call
 - Sending an Email
 - Querying the Email Configuration of an Agent
- ECC Interfaces: eccconfig
 - Adding a Phone Number to the Blacklist
 - Querying a Phone Number in the Blacklist
 - Querying All Phone Numbers in the Blacklist
 - Deleting a Phone Number from the Blacklist
 - Deleting All Phone Numbers from the Blacklist
 - Reading Configuration Information Based on configId
 - Adding a Phone Number to the Redlist
 - Querying a Phone Number in the Redlist
 - Querying All Phone Numbers in the Redlist
 - Deleting a Phone Number from the Redlist
 - Deleting All Phone Numbers from the Redlist
 - Querying the Number of Abandoned Calls
 - Querying Abandoned Call Records

Querying Prank Call Records

Third-Party Control: thirdcontrol

- Instructing an Agent to Make an Outbound Call
- Instructing an Agent to Answer a Call
- Instructing an Agent to Set the Status

Events

Events Related to Agent States

- AgentState_Busy (Talking)
- AgentState_Work (Working)
- AgentState_Ready (Idle)
- AgentState_SetNotReady_Success (Indicating Busy Successfully)
- AgentState_CancelNotReady_Success (Quitting the Busy State Successfully)
- AgentState_Force_SetNotReady (Forcing To Enter the Busy State Successfully)
- AgentState_SetRest_Success (Requesting Rest Successfully)
- AgentState_CancelRest_Success (Quitting the Resting State Successfully)
- AgentState_Rest_Timeout (Rest Timeout Reminder)
- AgentState_SetWork_Success (Turning to the Working State)
- AgentState_CancelWork_Success (Quitting the Working State)

Events Related to Voice Call

- AgentEvent_Talking (Turning to the Talking State)
- AgentEvent_Dialing (Turning to Dialing State (for SAP))
- AgentEvent_Customer_Alerting (Customer Ringing)
- AgentEvent_Hold (Holding a Call Successfully)
- AgentEvent_Conference (Entering Three-Party Conversation Successfully)
- AgentEvent_Call_Out_Fail (Making an Outgoing Call Unsuccessfully)
- AgentEvent_Inside_Call_Fail (Making an Internal Call Unsuccessfully)
- AgentEvent_No_Answer (No Answer from an Agent for a Long Time)
- AgentEvent_Call_Release (Agent Exiting a Call)
- AgentEvent_Customer_Release (User Exiting a Call)
- AgentEvent_Auto_Answer (Automatic Answering a Call)
- AgentEvent_Ringing (Incoming Call Reminder)
- AgentEvent_Connect_Fail (Failure to Connect to an Agent)
- AgentEvent_Consult_Fail (Failure to Ask for Help)
- AgentEvent_SipInfo (Receiving a SipInfo Message)
- AgentEvent_AbandonCall (Notifying an Abandoned Call)
- AgentEvent_SuccTransResult (Notifying the Success Transfer Result)
- AgentEvent_ReleaseRequest (Request Release Events)
- AgentEvent_ReleaseResponse (Response to Releasing A Call)
- AgentEvent_No_Answer_From_Cti (No Reply From an Agent for a Long Time)
- AgentEvent_Incoming_CallInfo (Incoming Call Notification Event)
- AgentEvent_TransOutResult (Notifying the Transfer-Out Result)
- AgentEvent_Asr_Notify (Real-Time Speech-to-Text Notification)
- OUTBOUND_DETECT_EVENT (Outgoing Call Event with a Failure Cause Code)
- AgentEvent_Third_Control (Third-Party Control Event)
- AgentEvent_Inside_Call_Queue_Fail (Transferring a call to a skill queue fails)

Events Related to Outgoing Call

- AgentEvent_Release_Preview (Previewed Outgoing Call Released)
- AgentEvent_Agent_Occupied (Agent Preoccupied)
- AgentEvent_Preview (Previewed Outgoing Call Initiated)

Events Related to Recording Playback

- AgentMediaEvent_Play (Recording Playback Started)
- AgentMediaEvent_Play_Succ (Recording Playback Succeeded)
- AgentMediaEvent_Play_Fail (Recording Playback Failed)
- AgentMediaEvent_StopPlayDone (Recording Playback Stopped)
- AgentMediaEvent_PausePlayDone (Recording Playback Paused)
- AgentMediaEvent_ResumePlayDone (Recording Playback Resumed)
- AgentMediaEvent_JumpPlayDone (Recording Playback Fast-Forwarded)
- AgentMediaEvent_Record (Recording Started)
- AgentMediaEvent_Record_Fail (Recording Start Failed)
- AgentMediaEvent_PauseRecordDone (Recording Paused)
- AgentMediaEvent_ResumeRecordDone (Recording Resumed)
- AgentMediaEvent_StopRecordDone (Recording Stopped)
- AgentMediaEvent_StartRecordScreen_Succ (Starting Screen Recording Succeeded)
- AgentMediaEvent_StartRecordScreen_Fail (Starting Screen Recording Failed)
- AgentMediaEvent_StopRecordScreen_Succ (Stopping Screen Recording Succeeded)
- AgentMediaEvent_StopRecordScreen_Fail (Stopping Screen Recording Failed)

Events Related to Text Chat

- AgentChat_Ring (Ringing Before a Text Chat)
- AgentChat_Connected (Text Chat Session Connected)
- AgentChat_Disconnected (Text Chat Session Disconnected)
- AgentChat_DataRecvd (Obtaining Messages During a Text Chat)
- AgentChat_DataRecvdEx (Obtaining a Reply Message in a Text Chat)
- AgentChat_TransferStart (Text Chat Call Transfer Started)

AgentChat_TransferFailed (Text Chat Call Transfer Failed)
AgentChat_CallOutCreated (Internal Text Chat Call Created)
AgentChat_CalloutFailed (Internal Text Chat Call Failed)
AgentChat_Swapd (Notification of Invalid Text Chats (Server Switchover))
AgentChat_WithoutCallConfirm (Supplementary Reply Message)
AgentChat_NoRealTimeCall (Non-real-time Call Content Notification)
AgentChat_PostDataSuccess (Successfully Sending the Text Chat Content)
AgentChat_PostDataFailed (Sending the Text Chat Content Failed)

Events Related to Real-time Quality Control

QC_AgentState_Notify (Agent Monitoring Notification Event)

Events Related to RMS

CTI_START_CALL_EVENT (Call Starting)
CTI_STOP_CALL_EVENT (Call Ending)
CTI_AGENT_LOGIN_EVENT (Login)
CTI_AGENT_LOGOUT_EVENT (Logout)

Events Related to Physical Phone

AgentOther_PhoneUnknow (Phone Status Unknown)
AgentOther_PhoneRelease (Phone in On-Hook State)
AgentOther_PhoneOffhook (Phone in Off-Hook State)
AgentOther_PhoneAlerting (Phone in Ringing State)
AgentOther_PhoneBusy (Physical Phone of an Agent Busy)

Events Related to Multimedia Conference

AgentEvent_JoinConf (Notification of a Multimedia Conference Message)
AgentEvent_OnMultimediaConfState (Notification of the Multimedia Conference Status)
AgentEvent_OnStopMultimediaConf (Multimedia Conference Stopped)

Events Related to Phone Linkage

AgentEvent_linkageCapability (Events Related to Phone Linkage Results)
AgentEvent_linkagePhoneStatus (Phone Status)
AgentEvent_linkagePhoneMute (Call Muted in the Phone Linkage State)
AgentEvent_linkagePhoneUnMute (Muted Call Unmuted in the Phone Linkage State)
AgentEvent_linkagePhoneCallOut (Outgoing Call Made in the Phone Linkage State)
AgentEvent_linkagePhoneTransferOut (Call Transferred in the Phone Linkage State)
AgentEvent_linkagePhoneTransferOut_Result (The Result Of Call Transferred in the Phone Linkage State)

Conference Call Events

AgentConf_RequestSuccess (Successfully Applying for a Conference Call)
AgentConf_RequestFailed (Applying for a Conference Call Failed)
AgentConf_SelfJoinResult (Agent Joined a Conference Call)
AgentConf_Timeout (Conference Timeout Reminder)
AgentConf_Ringing (Ringing of a Conference Call)
AgentConf_ParticipantChanged (Participant Changed)
AgentConf_SelfLeaveResult (Agent Leaved a Conference Call)
AgentConf_PresidentChanged (Conference Chair Changed)
AgentConf_StopVoice (Conference Announcement Ended)
AgentConf_StopParticipantVoice (Conference Channel Announcement Ended)
AgentConf_SipInfo (Conference SipInfo Message)

Email Events

AgentMail_Ringing (Ringing of an Email Call)
AgentMail_Connected (Email Call Setup)
AgentMail_Received (Email Received)
AgentMail_Disconnected (Email Call Released)
AgentMail_Remind (Email Reminder)
AgentMail_CallOutFailed (Outgoing Email Failed)
AgentMail_NoAnswer (No Answer to an Email Call)

Other Agent-Related Events

AgentOther_InService (Login Success)
AgentOther_ShutdownService (Logout Success)
AgentOther_WasSwaped (WAS Server Switchover)
Agent_Recover (Agent Recovered)
AgentOther_Note (Note Received)
AgentOther_Bulletin (Bulletin Received)
AgentOther_All_Agent_Busy (All Agents in Busy State)
AgentOther_CallInPrivateQueue (Call Entering a Private Queue)
AgentOther_CallOutPrivateQueue (Call Exiting a Private Queue)
AgentOther_BeQcStart (Inspection on an Agent Started)
AgentOther_BeQcStop (Inspection on an Agent Stopped)
Agent_QueueMonitor_Detail (Monitoring Queue Details)
Agentevent_UserLocation_Notify (Location Information Notification Event)
AgentEvent_MSD_Notify (MSD Data Notification Event)

Extended Interfaces and Events

Interfaces

Online Agent: onlineagent
Logging In to the CCS Only
Forcibly Logging In to the CCS Only

- Forcibly Logging In Without Binding the Agent Phone Number
- Setting Self-Recording Function
- Changing the Password
- Setting Indication of Call Forwarding/Call Forwarding on Busy
- Sending a Note
- Binding an Agent Phone Number
- Setting Whether to Answer Incoming Calls
- Publishing a Bulletin

Voice Call: voicecall

- Making a Previewed Outgoing Call
- Reporting Sound
- Performing Two-Stage Dialing
- Requesting a Call
- Freezing Image
- Unfreezing Image
- Releasing the Connection of a Specified Phone Number
- Hanging Up
- Dropping a Call (for VTM)
- Sending the SipInfo Message

Recording and Playback: recordplay

- Starting Recording
- Starting Recording (File Name Automatically Generated by the System)
- Pausing Recording
- Resuming Recording
- Stopping Recording
- Starting Screen Recording
- Stopping Screen Recording
- Obtaining the Screen Recording Authentication Information

Real-Time Quality Control: qualitycontrol

- Switching Between Listening and Inserting
- Making an Agent Rest Forcibly
- Configuring Automatic Recording for an Inspected Agent
- Canceling Automatic Recording for an Inspected Agent

Agent Event: agentevent

- AGENT POLL Mode
 - Obtaining All Agent Events by Polling
- HTTP PUSH Mode
 - Sending Agent Events to a Specified Service

Configuration Parameter: queryconfig

- Obtaining the Operation Parameters of a Multimedia Client
- Obtaining the Media Gateway Information
- Obtaining VDN System Configuration Information

Telepresence Call: vccall

- Answering a Call
- Ending a Call

ECC Interfaces: eccoconfig

- Adding Agent Skill Queue Monitoring
- Removing Agent Skill Queue Monitoring
- Querying a Specified Wireless Device
- Querying All Wireless Devices
- Applying for Wireless Device Resources
- Releasing Wireless Device Resources
- Setting VoiceCodes Recording Parameters
- Setting VoiceCodes Recording Parameters (Extended)

Events

Telepresence Call Events

- AgentVCCall_PhoneStatus (Telepresence Phone Status)
- AgentVCCall_Ringing (Call Ringing)
- AgentVCCall_Connected (Call Setup)
- AgentVCCall_AnswerFailed (Call Answering Failed)
- AgentVCCall_NoAnswer (No Answering of a Telepresence Call)
- AgentVCCall_Release (Call Released)
- AgentVCCall_ReleaseFailed (Call Releasing Failed)
- AgentVCCall_RecordStart (Recording Started)
- AgentVCCall_RecordEnd (Recording Ended)
- AgentVCCall_RecordFailed (Recording Failed)

Appendix

- Error Codes
- Agent Status
- Operating Status of Agents
- Call Types
- Media Types
- Error Codes about Multimedia Conferences

- Device Types
- pushUrl Request
- Rich Media File Restrictions
- ICS Server Interface (RESTful)
- About This Document
 - Intended Audience
 - Symbol Conventions
 - Change History
 - V100R023C00
 - V600R019C00SPC630
 - V100R022C00
 - V600R019C00SPC590
 - V600R019C00
 - V600R019C00SPC100
 - V600R019C00
 - V600R006C10
 - V600R006C10SPC100
 - V600R006C10
 - V200R001C80
 - V200R001C80SPC701
 - V200R001C80SPC700
 - V200R001C80SPC600
 - V200R001C80SPC500
 - V200R001C80SPC300
 - V200R001C80SPC200
 - V200R001C80SPC100
 - V200R001C80
 - V200R001C60
 - V200R001C60SPC100
 - V200R001C60
- Interfaces
 - The Description Of Interface Parameter
 - User Login and Logout Interfaces
 - Logging In
 - Logging In (Extended)
 - Logging Out
 - Detecting Heartbeat
 - Quasi-Real-Time Calling Interfaces
 - Creating Quasi-Real-Time Calls
 - Ending Quasi-Real-Time Calls
 - Canceling Queuing Calls
 - Sending Text Messages
 - Obtaining Queuing Information
 - Uploading a Rich Media File
 - Downloading a Rich Media File
 - Confirming Message Receiving
 - Querying CDRs
 - Interfaces for Obtaining Events
 - Obtaining Events of a Specified User
 - Obtaining Events of a Specified appld
 - Interfaces for Querying Queue Devices
 - Querying Queue Statistics Based on the Access Code
 - Querying Queue Statistics Based on ID of the Skill Queue
 - Multimedia Conference Interfaces
 - Applying for a Multimedia Conference and Requiring the Current Agent to Participate in the Conference
 - Re-inviting the Current Agent to Participate in the Multimedia Conference
 - Ending the Multimedia Conference
 - Reporting Conference Participation Results
 - Parameter Configuration Interfaces
 - Obtaining the Operation Parameters of a Multimedia Client
 - Obtaining the Media Gateway Information
 - Verification Code Interfaces
 - Obtaining the Call Verification Code
 - Server Connection Interfaces
 - Sending Messages Without Call
 - Confirming the Receiving of a Message Sent by an Agent Without Call
 - Sending an AML SMS Message When There Is No Call
 - Sending a Certificate Expiration Alarm
- Events
 - Call Events
 - WECC_WEBM_CALL_CONNECTED (Call Setup)
 - WECC_WEBM_CALL_DISCONNECTED (Call Disconnection)
 - WECC_WEBM_CALL_QUEUING (Call Queuing)

- WECC_WEBM_QUEUE_TIMEOUT (Queuing Timeout)
- WECC_WEBM_CANCEL_QUEUE (Queuing Cancellation)
- WECC_WEBM_CALL_FAIL (Call Failure)
- WECC_WEBM_CALL_TRANSFER (Call Transfer)
- WECC_CHAT_POSTDATA_SUCC (Message Sending Success)
- WECC_CHAT_POSTDATA_FAIL (Message Sending Failure)
- WECC_CHAT_RECEIVEDATA (Message Receiving Success)
- WECC_CHAT_RECEIVEDATA_EX (Receiving of an Agent's Message Requiring a Reply)

Multimedia Conference Events

- WECC_MEETING_PREPARE_JOIN (Will Participate in the Multimedia Conference)
- WECC_MEETING_STOP (Notifying the Conference Ending)
- WECC_MEETING_STATUS (Notifying the Conference Status)

Inspection Notification Events

- WECC_BE_QC_START (Starting the Inspection)
- WECC_BE_QC_STOP (Stopping the Inspection)

Other Related Events

- WECC_PROVIDER_IN_SERVER (User Login)
- WECC_PROVIDER_SHUTDOWN (Automatic User Logout)
- WECC_USER_LONGTIME_NOOPERATE (No Operations Within a Long Period of Time)
- WECC_MESSAGE_WITHOUTCALL_EVENT (Agent Sending Content to a User Without Call)

Appendix

- Error Codes
- Pushing a Request Based on pushUrl
- Rich Media File Restrictions

CMS Server Interface (RESTful)

About This Document

- Intended Audience
- Symbol Conventions

Change History

- V100R023C00
 - V600R019C00SPC630
- V100R022C00
 - V600R019C00SPC590
- V600R019C00
 - V600R019C00SPC201
 - V600R019C00SPC100
 - V600R019C00
- V600R006C10
 - V600R006C10SPC100
 - V600R006C10
- V200R001C80
 - V200R001C80SPC700
 - V200R001C80SPC600
 - V200R001C80SPC500
 - V200R001C80SPC300
 - V200R001C80SPC200
 - V200R001C80SPC100
 - V200R001C80
- V200R001C60
 - V200R001C60SPC100

Interfaces

- Notices for Interface Use
- Interfaces for authentication
 - Authenticating Agents
- Interfaces for Synchronizing the WAS Configuration Data
 - Synchronizing CTI Data
 - Synchronizing VDN Data
 - Testing CTI Synchronization
 - Testing VDN Synchronization
 - Obtaining the Information of All VDNs
 - Obtaining the Agent Information of a Specified VDN
 - Obtaining the Agent Group Information of a Specified VDN
 - Obtaining the Resting Reason Information of a Specified VDN
 - Obtaining the Service Type Information of a Specified VDN
 - Obtaining the Skill Information of a Specified VDN
 - Obtaining the Skill Group Information of a Specified VDN
 - Obtaining the Called Configuration Information of a Specified VDN
 - Obtaining the Configuration Information Version

Interfaces for Querying Historical Indexes

- Obtaining Monitoring Indexes About Agents
- Obtaining Monitoring Indexes About Skills
- Obtaining Monitoring Indexes About IVR Flows
- Obtaining Monitoring Indexes About VDNs

Interfaces for Querying Real-Time Indexes

- Obtaining Monitoring Indexes About Agents

- Obtaining Monitoring Indexes About Skills

- Interface for Obtaining Monitoring Indexes About VDNs

Real-Time Interfaces

- Querying the Call Information of Specified Access Codes

- Querying the System Access Code Information of a Specified VDN

- Querying the Agent Resting Condition of a Specified VDN

- Bulk Querying the Agents Who Have Signed In to the Specified Skill Queues

- Bulk Querying the Skill Queues to Which the Specified Agents Have Signed In

- Interface for Bulk Querying the Agent Information

- Querying Agent Phone Numbers of a Specified VDN

- Querying the Current Call Information of a Specified Agent

- Querying the Information About All Agents of a Specified VDN

- Querying the Current State Information About All Agents of a Specified VDN

- Querying the Static Configuration Information About All Agents of a Specified VDN

- Bulk Querying the Call Information of Agents

- Querying Private Calls of the Specified Agent

- Querying the Basic Call Information of a Specified Call ID

- Querying the Detailed Call Information of a Specified Call ID

- Querying the Detailed Status Information About the IVR Flow of a Specified VDN

- Querying the Access Code Information About the IVR Flow of a Specified VDN

- Bulk Querying the Extended Information of Skill Queues

- Bulk Querying the Call Statistics of Skill Queues in the Last Five Minutes

- Querying the Status Information of a Specified Skill Queue

- Bulk Querying the Configuration Information of Skill Queues

- Bulk Querying the Detailed Statistics of Skill Queues

- Querying the Information About All Skill Queues of a Specified VDN

- Bulk Querying All Queuing Calls in Skill Queues

- Bulk Querying the Number of Calls that a Skill Queue Picks Up from Other Skill Queues in the Case that Multiple Skill Queues Have Waiting Calls

- Querying the Service Type Information of a Specified VDN

- Querying the Server Time of the CTI Platform

- Querying the Current License Usage Condition of the System

- Querying the Current License Usage Condition of a Specified VDN

- Querying the Agent Resting Reason Codes of a Specified VDN

- Querying All VDNs in a Specified Call Center

- Querying the Number of Agents in Different States in Agent Groups

- Querying the Number of Agents in Different States in Skill Queues

- Querying the Agent Status Change Reason in a Specified VDN

Report interface

- Downloading Voice Call CDRs of a VDN

Interface for Managing Inspection User Groups

- Adding an Agent to an Inspector Group

- Querying All Inspector Groups of a Specified VDN

Secondary Development Guide

- Voice CDR Development Guide

Appendix

- Error Codes

- WAS Synchronization Data Tables

- WAS Synchronization Status

- Media Types

- Device Types

Historical Monitoring Indexes

- Agent

- Skill

- IVR

- VDN

- Return Result of the Daily Statistics About the Trend Traffic at an Interval of 15, 30, or 60 Minutes

Real-Time Monitoring Indexes

- Agent

- Skill

- VDN

Agent Status

- Operating Status of Agents

- Call Status

- Call Features

- Agent Permission Values

- Call Type

- Call Release Cause Codes

- Cause Why a Call Accesses or Leaves the Device

Voice Interface (ActiveX)

- About This Document

- Intended Audience

Symbol Conventions

Change History

V100R023C00

V600R019C00SPC630

V100R022C00

V600R019C00SPC590

V600R019C00

V600R019C00

V600R006C10

V600R006C10

V200R001C80

V200R001C80SPC700

V200R001C80SPC600

V200R001C80SPC500

V200R001C80SPC400

V200R001C80SPC300

V200R001C80SPC200

V200R001C80SPC100

V200R001C80

Overview

Introduction

Development Environment

Applicable Scope

Conventions

Terms Explanation

Data Types

Basic Data Types

Interface Description

Initialization Interfaces

SetConfig

GetConfig

SetLogLevel

SetLogSaveDays

SetAudioRtpType

SetSipTlsMode

GetResultDesc

GetLocalIpAddr

SetSipServerInfo

SetLocalInfo

Register

Deregister

UnInit

Call Interfaces

Call

AnonymousCall

Answer

CallEx

AnonymousCallEx

AnswerEx

Release

DtmfDial

SendSipInfo

Mute

UnMute

Hold

UnHold

Transfer

IntercomCall

IntercomAnswer

GetCurrentCall

SetVideoWindow

SetVideoWindowEx

Phone Linkage Interfaces

CallJointStart

CallJointStop

Conference Interfaces

CreateLocalConf

DestroyLocalConf

AddToLocalConf

DelFromLocalConf

MuteLocalConf

HoldLocalConf

Device Interfaces

- GetDevices
- SetDeviceIndex
- SetVolume
- GetVolume
- SetSoundCardAidConfig
- ControlAudioAidDevice
- GetVolumeEx
- SetVolumeEx
- GetGainByCall
- SetGainByCall
- SetAudioDeviceByName
- StartPlayMediaFile
- StopPlayMediaFile
- GetVideoDevices
- SnapShot
- SetVideoDeviceIndex
- OpenPreview
- ClosePreview
- Event Description
 - Initialization Events
 - VoiceInitResultEvent
 - VoiceRegisterResultEvent
 - VoiceDeregisterResultEvent
 - VoiceExceptionEvent
 - Call Events
 - VoiceTalkOutgoingEvent
 - VoiceStartCallResultEvent
 - VoiceTalkAlertingEvent
 - VoiceTalkRingBackEvent
 - VoiceSrtpResultEvent
 - VoiceTalkConnectedEvent
 - VoiceTalkReleaseEvent
 - VoiceSipInfoArrivedEvent
 - VoiceNetworkQosNotifyEvent
 - VoiceHoldResultEvent
 - VoiceUnHoldResultEvent
 - VoiceTransferResultEvent
 - Phone Linkage Events
 - VoiceCallJointStartResultEvent
 - VoiceCallJointStopResultEvent
 - VoiceStatusNotifyEvent
 - Conference Events
 - VoiceAddToLocalConfResultEvent
 - VoiceDelFromLocalConfResultEvent
 - VoiceDestroyLocalConfResultEvent
 - VoiceHoldLocalConfResultEvent
 - Device Events
 - VoiceAidProcessStatusEvent
 - VoiceControlAudioAidDeviceResultEvent
 - VoiceVolumeExEvent
 - VoiceGainByCallEvent
 - VoiceSnapshotResultEvent
- Return Codes
- JSSDK Interface (JavaScript)
 - About This Document
 - Intended Audience
 - Symbol Conventions
 - Change History
 - V100R023C00
 - V600R019C00SPC680
 - V600R019C00SPC670
 - V600R019C00SPC640
 - V600R019C00SPC636
 - V600R019C00SPC630
- Overview
 - Introduction
 - Development Environment
 - Applicable Scope
 - Conventions
 - Terms Explanation
- Interface Description
 - Initialization Interfaces
 - Initializing the JS SDK

- Forcibly Initializing the MSP
- Querying Version Number
- Event Registration
- Deregistration
- Registration
- Call Interfaces
 - Dial
 - Answer
 - Release
 - Reject
 - mute
 - getCurrentCall
- Device Interfaces
 - GetSoundDevice
 - SetSoundDevice
 - QueryCameraAbility
 - GetVolume
 - SetVolume
 - CheckMSPIsInstall
- Event Definition
 - Media Service Notification Events
 - OnGetSoundDeviceResult
 - OnSetSoundDeviceResult
 - OnGetVolumeResult
 - OnSetVolumeResult
 - OnMuteMicOrSpeakerResult
 - OnUnmuteMicOrSpeakerResult
 - OnUpdateMsp
 - GetResultDesc
 - Resource Status Notification Event
 - OnUserStatusNotify
 - OnMicOrSpeakerStateNotify
 - Call Events
 - OnDialOutProceeding
 - OnDialOutRinging
 - OnCallConnect
 - OnDialOutFailure
 - OnCallRelease
 - OnDialInRinging
 - OnConnectProceeding
 - OnCallException
- Return Code
- Conference Interfaces (ActiveX)
 - About This Document
 - Intended Audience
 - Safety Notices
 - Reference Documents
 - Symbol Conventions
 - Change History
 - V100R023C00
 - V600R019C00SPC630
 - V100R022C00
 - V600R019C00SPC590
 - V600R019C00
 - V600R019C00
 - V600R006C10
 - V600R006C10
 - V200R001C80
 - V200R001C80SPC703
 - V200R001C80SPC702
 - V200R001C80SPC701
 - V200R001C80SPC700
 - V200R001C80SPC600
 - V200R001C80SPC500
 - V200R001C80SPC400
 - V200R001C80SPC300
 - V200R001C80SPC200
 - V200R001C80SPC100
 - V200R001C80
- Overview
 - Conference OCX Overview
 - Development and Operating Environment Requirements
- Data Type

Interface Description

Structure

Conference Basic Interfaces

- JoinConf
- LeaveConf
- TerminateConf
- GetPresenter
- LimitDataFlowSize
- SetVideoCodec
- SetLogLevel
- SetLogSaveDays
- GetResultDesc

Video Interfaces

- GetLocalVideoDevices
- OpenVideoDevice
- CloseVideoDevice
- StartDrawVideo
- StopDrawVideo
- PauseVideo
- ResumeVideo
- NotifyVideoCmd
- GetSupportVideoParams
- GetVideoCurrentParam
- SetVideoCurrentParam
- Snapshot

I/O Interfaces

- SendMessage
- SendFile
- CancelSendingFile
- ReceiveFile
- CancelReceiveFile

Multimedia Collaboration Interfaces

- SetDisplayShareScreenWnd
- GetApplicationList
- AddApplicationToShare
- DeleteSharedApplication
- StartShareScreen
- StopShareScreen
- RequestOperationPrivilege
- SetOperationPrivilege
- SetShareScreenDisplaySize

Document Sharing Interfaces

- ShareFileSetDisplayWnd
- ShareFileSetDisplaySize
- ShareFileOpen
- ShareFileGetFileInfo
- ShareFileClose
- ShareFileSave
- ShareFileSpecifiedPage
- ShareFilePreviousPage
- ShareFileNextPage
- ShareFileSwitch
- ShareFileZoomControl
- ShareFileMoveByHand
- ShareFileAutoMoveByHand

Event Description

Conference Basic Events

- ConfInitResultEvent
- JoinConfResultEvent
- MemberEnterConfEvent
- MemberLeaveConfEvent
- TerminateConfResultEvent
- ConfNetWorkDisconnectedEvent
- ConfNetWorkReconnectedEvent
- LoadComponentFailedEvent
- ConfNetWorkStatusEvent
- ConfRemainingTimeEvent
- ConfNetworkQosNotifyEvent

Video Events

- VideoSwitchEvent
- ConfVideoDisconnectedEvent
- ConfVideoReconnectedEvent
- ConfVideoNotifyEvent

- ConfVideoFlowWarningEvent
- I/O Events
 - MessageArrivedEvent
 - FileTranProgressEvent
 - FileTranOverEvent
 - FileArrivedEvent
- Multimedia Collaboration Events
 - StartShareScreenResultEvent
 - SharingOwnerNotifyEvent
 - ShareScreenStateNotifyEvent
 - OperationPrivilegeRequestEvent
 - OperationPrivilegeStateEvent
 - ShareScreenWndSizeEvent
- Document Sharing Events
 - ShareFileLoadingProgressEvent
 - ShareFileOpenEvent
 - ShareFileCurrentPageEvent
 - ShareFileCloseEvent
- Return Code
 - Public Return Codes
 - Meeting Return Code
- VRC Interface (ActiveX)
- About This Document
 - Overview
 - Intended Audience
 - Symbol Conventions
 - Change History
 - Issue 06 (2017-06-20)
 - Issue 05 (2017-05-17)
 - Issue 04 (2016-05-30)
 - Issue 03 (2014-08-30)
 - Issue 02 (2014-05-30)
 - Issue 01 (2012-06-25)
- API Reference
 - QC Console Interfaces
 - InitializeQC
 - StartMonitor
 - StartMonitorEx
 - StopMonitor
 - StopMonitorEx
 - GetLastErrorCode
 - Playback
 - PlaybackFor3
 - PlaybackMedia
 - PlaybackEncryptMedia
 - Agent Console Interfaces
 - InitializeAgentEx
 - ExitAgent
 - Public Interfaces
 - Uninitialize
 - SetRunParam
 - SetRecordParam
 - Events
 - OnPlayEnd
 - OnMonitorStop
 - OnNotifyInitAgentResult
- Data Reference
 - Enumeration
 - PLAY_FILE_NAME
 - PLAY_FILE_INFO
 - Error Codes
- AgentOther_PhoneRelease (Phone in On-Hook State)
- AgentState_Ready (Idle)
- Call Types
 - AgentMediaEvent_PausePlayDone (Recording Playback Paused)
 - AgentEvent_ReleaseRequest (Request Release Events)
 - AgentOther_PhoneOffhook (Phone in Off-Hook State)
 - AgentState_Busy (Talking)
 - AgentOther_PhoneAlerting (Phone in Ringing State)
 - AgentEvent_Call_Release (Agent Exiting a Call)
 - AgentEvent_Customer_Release (User Exiting a Call)
 - AgentEvent_SuccTransResult (Notifying the Success Transfer Result)
 - AgentMediaEvent_Play (Recording Playback Started)

AgentEvent_Inside_Call_Fail (Making an Internal Call Unsuccessfully)
AgentEvent_Connect_Fail (Failure to Connect to an Agent)
AgentMediaEvent_Play_Succ (Recording Playback Succeeded)
AgentMediaEvent_StopPlayDone (Recording Playback Stopped)
AgentMediaEvent_Play_Fail (Recording Playback Failed)
AgentState_Work (Working)
AgentMediaEvent_JumpPlayDone (Recording Playback Fast-Forwarded)
AgentEvent_Customer_Alerting (Customer Ringing)
AgentEvent_Talking (Turning to the Talking State)
Agent Status

Overview

Version Mapping

CloudICP V100R023C00

Running Environment Requirements

The interface reference applies to the following operating systems:

- 32-bit Windows 7 operating system (professional edition)
- 64-bit Windows Server 2008 R2

Technical Support

- Dial technical support hotline 400-060-0808.
- Visit technical support website <http://support.td-tech.com>.

Copyright © Chengdu TD-Tech Co., Ltd.

Agent Server Interfaces (RESTful)

[About This Document](#)

[Basic Interfaces and Events](#)

[Extended Interfaces and Events](#)

[Appendix](#)

Copyright © Chengdu TD-Tech Co., Ltd.

About This Document

[Intended Audience](#)

[Security Statement](#)

[Symbol Conventions](#)

[Change History](#)

Parent topic: [Agent Server Interfaces \(RESTful\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Intended Audience

This document guides the secondary development of service software on the agent side. Development personnel must have the following skills:

- Be familiar with the JSON format.
- Be familiar with knowledge related to HTTP request sending.

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Security Statement

Interfaces are not compatible with earlier versions. Although certain interfaces are marked as abandoned, they can still be used. Maintenance is not provided for the abandoned interfaces. Sites adopting earlier versions can use new interfaces to replace the abandoned interfaces according to actual situations.

Secondary development engineers must use security interfaces for development in strict accordance with this document.

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Symbol Conventions

The symbols that may be found in this document are defined as follows.

Symbol	Description
 DANGER	Indicates an imminently hazardous situation which, if not avoided, will result in death or serious injury.
 WARNING	Indicates a potentially hazardous situation which, if not avoided, could result in death or serious injury.
 CAUTION	Indicates a potentially hazardous situation which, if not avoided, may result in minor or moderate injury.
 NOTICE	Indicates a potentially hazardous situation which, if not avoided, could result in equipment damage, data loss, performance deterioration, or unanticipated results. NOTICE is used to address practices not related to personal injury.
 NOTE	Calls attention to important information, best practices and tips. NOTE is used to address information not related to personal injury, equipment damage, and environment deterioration.

Parent topic: [About This Document](#)

Change History

- [V100R023C00](#)
- [V100R022C00](#)
- [V100R021C00](#)
- [V600R019C00](#)
- [V600R006C10](#)
- [V200R001C80](#)
- [V200R001C60](#)

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V100R023C00

[V600R019C00SPC680](#)

[V600R019C00SPC640](#)

[V600R019C00SPC631](#)

[V600R019C00SPC630](#)

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00SPC680

The following tables describe changes made in CloudIPCC V600R019C00SPC680 compared with CloudIPCC V600R019C00SPC670.

Table 1 List of adding error codes

Error Code	Error Code	Changes
200-029	Error Codes	Adding 200-029 error codes
200-030	Error Codes	Adding 200-030 error codes

Table 2 List of modified events

Events Type	Events Name	Changes
Events Related to Phone Linkage State.	AgentEvent_linkagePhoneStatus (Phone Status)	Delete the offline state.

Parent topic: [V100R023C00](#)

V600R019C00SPC640

The following tables describe changes made in CloudIPCC V600R019C00SPC640 compared with CloudIPCC V600R019C00SPC631.

Table 1 List of modified events

Events Type	Events Name	Changes
Events Related to Voice Call	AgentEvent_Incoming_CallInfo (Incoming Call Notification Event)	The return parameter callerIMSI is added.
Events Related to RMS	CTI_START_CALL_EVENT (Call Starting)	The return parameter MSDData and CallerIMSI is added.
Events Related to Real-time Quality Control	QC_AgentState_Notify (Agent Monitoring Notification Event)	The event content subtype QC_AgentState_SMS is added.

Table 2 List of modified interfaces

Interface Type	Interface Name	Changes
transfer call: transfer	Transferring a Call	The input parameter imsi is added.

Table 3 List of adding error codes

Error Code	Error Code	Changes
100-031	Error Codes	Adding 100-031 error codes

Parent topic: [V100R023C00](#)

V600R019C00SPC631

The following tables describe changes made in CloudIPCC V600R019C00SPC631 compared with CloudIPCC V600R019C00SPC630.

Table 1 List of modified events

Events Type	Events Name	Changes
Events Related to Voice Call	AgentEvent_Incoming_CallInfo (Incoming Call Notification Event)	The return parameter callerIMSI is added.
Events Related to RMS	CTI_START_CALL_EVENT (Call Starting)	The return parameter MSDData and CallerIMSI is added.
Events Related to Real-time Quality Control	QC_AgentState_Notify (Agent Monitoring Notification Event)	The event content subtype QC_AgentState_SMS is added.

Table 2 List of modified interfaces

Interface Type	Interface Name	Changes
transfer call: transfer	Transferring a Call	The input parameter imsi is added.

Table 3 List of adding error codes

Error Code	Error Code	Changes
100-031	Error Codes	Adding 100-031 error codes

Parent topic: [V100R023C00](#)

V600R019C00SPC630

The following tables describe changes made in CloudIPCC V600R019C00SPC630 compared with CloudIPCC V600R019C00SPC591.

Table 1 List of new interfaces

Interface Type	Interface Name
Agent Interfaces: msdbycallid	Querying MSD Data by Call ID
Agent Events: AgentEvent_MSD_Notify	AgentEvent_MSD_Notify (MSD Data Notification Event)

Table 2 List of adding error codes

Error Code	Error Code	Changes
200-028	Error Codes	Adding 200-028 error codes

Parent topic: [V100R023C00](#)

V100R022C00

V600R019C00SPC590

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00SPC590

The following tables describe changes made in CloudIPCC V600R019C00SPC590 compared with CloudIPCC V600R019C00SPC580.

Table 1 List of new interfaces

Interface Type	Interface Name
Agent Interfaces: recordinfoagents	Query_RecordingEx
Agent Interfaces: recordinfo	Query_Recording

Parent topic: [V100R022C00](#)

V100R021C00

[V600R019C00SPC500](#)

[V600R019C00SPC580](#)

[V600R019C00SPC309](#)

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00SPC500

The following tables describe changes made in CloudIPCC V600R019C00SPC500 compared with CloudIPCC V600R019C00.

Interface Changes

Table 1 List of new interfaces

Interface Type	Interface Name
ECC Interfaces: eccconfig	Setting_VoiceCodes_Recording_Parameters_(Extended)

Parent topic: [V100R021C00](#)

Table 1 List of modified interfaces

Interface Type	Interface Name	Changes
inner call: callinner	2.2.1.2.3 Making an internal call	update mediaability's ability

Parent topic: [V100R021C00](#)

Table 1 List of new interfaces

Interface Type	Interface Name
Recording and Playback: recordplay	2.2.1.4.7-Query Recording

Parent topic: [V100R021C00](#)

V600R019C00

V600R019C00SPC100

V600R019C00

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00SPC100

The following tables describe changes made in CloudIPCC V600R019C00SPC200 compared with CloudIPCC V600R019C00.

Table 1 List of new events

Event Name	Changes
Events Related to Voice Call	AgentEvent_Inside_Call_Queue_Fail (Transferring a call to a skill queue fails).
Other Agent-Related Events	Agent_QueueMonitor_Detail (Monitoring Queue Details).

Table 2 List of new interfaces

Interface Type	Interface Name
Online Agent: onlineagent	Changing the Busy Reason Code
Voice Call: voicecall	Internal Call to a Skill Queue
Queue Device: queuedevice	Adding Queue Monitoring
	Stopping Queue Monitoring
Real-Time Quality Control: qualitycontrol	Forcibly Showing Busy with a Reason Code

Parent topic: [V600R019C00](#)

V600R019C00

The following tables describe changes made in CloudIPCC V600R019C00 compared with CloudIPCC V600R006C10.

Event Changes

Table 1 List of new events

Event Name	Changes
Events Related to Voice Call	OUTBOUND_DETECT_EVENT (Outgoing Call Event with a Failure Cause Code)
	AgentEvent_Third_Control (Third-Party Control Event)

Table 2 List of new interfaces

Interface Type	Interface Name
Agent Group: agentgroup	Querying the Work ID Using the Third-Party Account
Third-Party Control Interface: thirdcontrol	Instructing an Agent to Make an Outbound Call
	Instructing an Agent to Answer a Call
Call Data: calldata	Querying the Geographical Location Based on the Calling Number
	Updating the Geographical Location Based on the Calling Number

Table 3 List of modified interfaces

Interface Type	Interface Name	Changes
Agent Group: agentgroup	Querying Detailed Information About A Specified Agent	The output parameter thirdAccount is added.

Parent topic: [V600R019C00](#)

V600R006C10

[V600R006C10SPC100](#)

[V600R006C10](#)

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R006C10SPC100

The following tables describe changes made in CloudIPCC V600R006C10SPC100 compared with CloudIPCC V600R006C10.

Interface Changes

Table 1 List of new interfaces

Interface Type	Interface Name
Online Agent: onlineagent	Detecting Heartbeat

Table 2 List of modified interfaces

Interface Type	Interface Name	Changes
Online Agent: onlineagent	Logging In	The input parameter pushUrl is added.
	Forcibly Logging In	The input parameter pushUrl is added.
	Logging In Through CAC Authentication	The input parameter pushUrl is added.
	Forcibly Logging In Through CAC Authentication	The input parameter pushUrl is added.
	Logging In to the CCS Only	The input parameter pushUrl is added.
	Forcibly Logging In to the CCS Only	The input parameter pushUrl is added.
	Forcibly Logging In Without Binding the Agent Phone Number	The input parameter pushUrl is added.
Real-Time Quality Control: qualitycontrol	Generating the Recording Download Path	The input parameter recordFileName is added.

Table 3 List of modified parameter descriptions

Interface Type	Interface Name	Changes
Call Data: calldata	Configuring Call-Associated Data (Bean Expansion Interface)	The description of the isWriteBill parameter is modified to the following: Indicates whether the key/value pair is saved to the database. (0: no; 1: yes; -1: invalid). The default value is 0.
	Querying Call-Associated Data (Bean Expansion Interface)	The description of the isWriteBill parameter is modified to the following: Indicates whether the key/value pair is saved to the database. (0: no; 1: yes; -1: invalid).

Event Changes

Table 4 List of new events

Event Name	Changes
Events Related to Voice Call	AgentEvent_Asr_Notify (Real-Time Speech-to-Text Notification)

Parent topic: [V600R006C10](#)

V600R006C10

The following tables describe changes made in IPCC V600R006C10 compared with IPCC V200R001C80.

Interface Changes

Table 1 List of new interfaces

Interface Type	Interface Name
Online Agent: onlineagent	Logging In Through CAC Authentication
	Forcibly Logging In Through CAC Authentication
Text Message: textchat	Obtaining Call Content
	Obtaining Call Information
	Querying Content of Interaction Without Call Between an Agent and Customers
	Uploading a Rich Media File
	Downloading a Rich Media File
Real-Time Quality Control: qualitycontrol	Obtaining the Recording Duration
Configuration Parameter: queryconfig	Obtaining VDN System Configuration Information
ECC Interfaces: eccconfig	ECC Interfaces: eccconfig

Table 2 List of modified interfaces

Interface Type	Interface Name	Changes
Voice Call: voicecall	Making an Outgoing Call	The mediaability parameter supports value 2 .
Text Message: textchat	Sending Content to a Customer Without Call	The interface title is changed to "Sending Content to a Customer Without Call."
Call Data: calldata	Querying Call Information	The return parameter mediaAbility is added.
	Querying Call Information Before Answering a Call	The return parameter mediaAbility is added.
	Querying Call Information by Call ID	The return parameter mediaAbility is added.
	Querying Information About Queuing Calls in a Specified Skill Queue	The return parameter mediaAbility is added.
	Querying Information About Queuing Calls in a Specified IVR System	The return parameter mediaAbility is added.

Event Changes

Table 3 List of modified events

Event Type	Event Name	Changes
Events Related to Voice Call	AgentEvent_Talking (Turning to the Talking State)	The return parameter mediaAbility is added.
	AgentEvent_Auto_Answer (Automatic Answering a Call)	Return parameters feature and mediaAbility are added.
	AgentEvent_Ringing (Incoming Call Reminder)	Return parameters feature and mediaAbility are added.
Events Related to Text Chat	AgentChat_Ring (Ringing Before a Text Chat)	Return parameters realCaller , userInfo , displayName , and subMediaType are added.
	AgentChat_DataRecved (Obtaining Messages During a Text Chat)	The return parameter chatContentType is added.
	AgentChat_DataRecvedEx (Obtaining a Reply Message in a Text Chat)	The return parameter chatContentType is added.

Parent topic: [V600R006C10](#)

V200R001C80

[V200R001C80SPC703](#)

[V200R001C80SPC702](#)

[V200R001C80SPC701](#)

[V200R001C80SPC700](#)

[V200R001C80SPC600](#)

[V200R001C80SPC500](#)

[V200R001C80SPC300](#)

[V200R001C80SPC200](#)

[V200R001C80SPC100](#)

[V200R001C80](#)

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC703

The following tables describe changes made in IPCC V200R001C80SPC703 compared with IPCC V200R001C80SPC702.

Interface Changes

Table 1 List of new interfaces

Interface Type	Interface Name
Real-Time Quality Control: qualitycontrol	Generating the Recording Download Path
	Downloading a Recording File

Table 2 List of modified interfaces

Interface Type	Interface Name	Changes
Online Agent: onlineagent	Logging In	Change the default value of the input parameter releasephone to true .
	Forcibly Logging In	Change the default value of the input parameter releasephone to true .
	Logging In to the CCS Only	Change the default value of the input parameter releasephone to true .
	Forcibly Logging In to the CCS Only	Change the default value of the input parameter releasephone to true .
	Forcibly Logging In Without Binding the Agent Phone Number	Change the default value of the input parameter releasephone to true .

Parent topic: [V200R001C80](#)

V200R001C80SPC702

No change is made in IPCC V200R001C80SPC702 compared with IPCC V200R001C80SPC701.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC701

The following tables describe changes made in IPCC V200R001C80SPC701 compared with IPCC V200R001C80SPC700.

Table 1 List of modified interfaces

Interface Type	Interface Name	Changes
Online Agent: onlineagent	Logging Out	Optimized the description of the interface.
	Forcibly Logging Out	Optimized the description of the interface.
	Forcibly Logging Out with a Cause Code	Optimized the description of the interface.
Recording and Playback: recordplay	Fast Forwarding	Input arguments seekPosition are added.
	Rewinding	Input arguments seekPosition are added.
Queue Device: queuedevice	Querying the Statistics About a Set of Skill Queues	Optimized the description of the interface.
	Querying the Statistics About the Next Set of Skill Queues of the Home VDN of an Agent	Optimized the description of the interface.
	Querying the Device Status	Optimized the description of the interface.
	Querying the Sub-media Type of a Skill Queue	Optimized the description of the interface.
Agent Group: agentgroup	Querying Agent Information About the Group	Optimized the description of the interface.
	Querying Detailed Information About A Specified Agent	Optimized the description of the interface.
	Querying State Information About All Agents of the Home VDN	The return parameter ctiStatus is added.
	Querying Information About Agents That Have Signed In to a Skill Queue	Optimized the description of the interface.
	Querying the State and Skills of a Specified Agent Before Logging In	Optimized the description of the interface.
	Querying Information About Specified Agents in Batches	Optimized the description of the interface.
	Performing a Fuzzy Query of Online Agents by Using a Keyword	Optimized the description of the interface.
	Batch Querying IP addresses of Agents	Optimized the description of the interface.
Call Data: calldata	Querying the List of Held Calls	Optimized the description of the interface.
	Querying the List of Held Calls of a Specified Agent (Expanded)	Optimized the description of the interface.
	Querying Call Information	Optimized the description of the interface.
	Querying Call Information Before Answering a Call	Optimized the description of the interface.
	Querying Call Information by Call ID	Optimized the description of the interface.
	Querying All Call Information of a Specified Agent	Optimized the description of the interface.
	Querying Information About Queuing Calls in a Specified Skill Queue	Optimized the description of the interface.
	Querying Information About Queuing Calls in a Specified IVR System	Optimized the description of the interface.
	Querying Information About Queuing Calls in a Private Queue	Optimized the description of the interface.

Parent topic: [V200R001C80](#)

V200R001C80SPC700

No change is made in IPCC V200R001C80SPC700 compared with IPCC V200R001C80SPC600.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC600

The following tables describe changes made in IPCC V200R001C80SPC600 compared with IPCC V200R001C80SPC500.

Interface Changes

Table 1 List of new interfaces

Interface Type	Interface Name
Call Data: calldata	Querying Whether an Agent Has the Permission to Release a Specified Call

Table 2 List of modified interfaces

Interface Type	Interface Name	Changes
Agent Group: agentgroup	Querying Information About All Online Agents of the Home VDN	The return parameter currentStateReason is added.
	Querying Agent Information About the Group by A Supervisor	The return parameter currentStateReason is added.
	Querying Agent Information About the Group	The return parameter currentStateReason is added.
	Querying Detailed Information About A Specified Agent	The return parameter currentStateReason is added.
	Querying Agent Information About a Configured Skill Queue	The return parameter currentStateReason is added.
	Querying Information About Agents That Have Signed In to a Skill Queue	The return parameter currentStateReason is added.
	Querying Information About Specified Agents in Batches	The return parameter currentStateReason is added.
	Performing a Fuzzy Query of Online Agents by Using a Keyword	The return parameter currentStateReason is added.

Event Changes

Table 3 List of new events

Event Type	Event Name
Events related to voice call	AgentEvent_Incoming_CallInfo (Incoming Call Notification Event)
	AgentEvent_TransOutResult (Notifying the Transfer-Out Result)

Parent topic: [V200R001C80](#)

V200R001C80SPC500

The following tables describe changes made in IPCC V200R001C80SPC500 compared with IPCC V200R001C80SPC300.

Interface Changes

Table 1 List of new interfaces

Interface Type	Interface Name
Agent Group: agentgroup	Querying Whether an Agent Is Authorized with Internal Call Permission

Table 2 List of modified interfaces

Interface Type	Interface Name	Changes
Text Message: textchat	Sending a Text Message	The maximum length of content is changed to 6144 characters.
	Sending Content to a Customer Without Call	The maximum length of content is changed to 6144 characters.

Parent topic: [V200R001C80](#)

V200R001C80SPC300

The following tables describe changes made in IPCC V200R001C80SPC300 compared with IPCC V200R001C80SPC200.

Interface Changes

Table 1 List of modified interfaces

Interface Type	Interface Name	Changes
Call Data: calldata	Querying Call Information	The input parameter isNoContainLastCall is added.
Text Message: textchat	Sending a Text Message	The maximum length of content is changed to 2048 characters.

Parent topic: [V200R001C80](#)

V200R001C80SPC200

No change is made in IPCC V200R001C80SPC200 compared with IPCC V200R001C80SPC100.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC100

The following tables describe changes made in IPCC V200R001C80SPC100 compared with IPCC V200R001C80.

Interface Changes

Table 1 List of new interfaces

Interface Type	Interface Name
Voice Call: voicecall	Restoring a Line in the Phone Linkage State
	Sending the SiplInfo Message
	Requesting an Agent for Call Pickup
	Setting the Customer Level
Text Message: textchat	Sending Content to a Customer Without Call
	Confirming the Receiving of Non-real-time Call Content
	Confirming the Receiving of a Text Message
Recording and Playback: recordplay	Obtaining the Screen Recording Authentication Information
Queue Device: queuedevice	Obtaining the Skill Queue Information of a Specified VDN
	Obtaining the Skill Queue Information of the Home VDN of an Agent
	Querying the Device Status
	Querying the Sub-media Type of a Skill Queue
Agent Group: agentgroup	Querying the Work ID of an Agent Based on a Phone Number
	Batch Querying IP addresses of Agents
Real-Time Quality Control: qualitycontrol	Applying for Joining a Multimedia Conference
Conference Call: agentconf	Applying for a Conference Call
	Answering a Conference Call
	Rejecting a Conference Call
	Exiting a Conference Call
	Releasing a Conference Call
	Placing a Participant on Hold
	Unholding a Participant
	Applying for Conference Extension by a Conference Chair
	Transferring the Conference Chair Rights
	Batch Inviting Participants
	Batch Deleting Participants
	Modifying a Participant Attribute
	Playing Announcement for a Conference Call
	Stopping Announcement for a Conference Call
	Playing Announcement for a Conference Call Channel
	Stopping Playing Announcement for a Conference Call Channel
	Changing the Number of Conference Participants
	Batch Querying Conference Information
	Querying a Call ID of a Participant
	Querying the Conference ID of an Ongoing Conference Call on the VDN
Email: emailcall	Answering a Call
	Ending a Call
	Replying to an Email Call
	Sending an Email
	Querying the Email Configuration of an Agent
Telepresence Call: vccall	Answering a Call
	Ending a Call

Table 2 List of modified interfaces

Interface Type	Interface Name	Changes
----------------	----------------	---------

Interface Type	Interface Name	Changes
Online Agent: onlineagent	Logging In	Input parameters phonelinkage , checkInWebm , checkInMailm , vcPhoneNumber , and listenStatus are added.
	Forcibly Logging In	Input parameters phonelinkage , checkInWebm , checkInMailm , vcPhoneNumber , and listenStatus are added.
	Resetting Skill Queues	The input parameter skillid is modified to be optional.
	Setting Busy	The input parameter reason is added.
Voice Call: voicecall	Answering a Call	Description about the optimization in the phone linkage state is added.
	Answering a Call in the Phone Linkage State	Tags not supported by interfaces are deleted.
	Rejecting a Call in the Phone Linkage State	Tags not supported by interfaces are deleted.
Text Message: textchat	Sending a Text Message	Input parameters needCheck and chatId are added.
	Transferring a Text Chat	The input parameter mode is added.
Recording and Playback: recordplay	Starting Recording	The description of the input parameter filename is changed to "recording drive letter."
	Starting Screen Recording	The input parameter filename is deleted.
Queue Device: queuedevice	Querying IVR Information of a VDN	The return parameter serviceNo is added.
	Obtaining the Skill Queue Information of a Specified VDN	The return parameters serviceType and realFlag are added.
	Obtaining the Skill Queue Information of the Home VDN of an Agent	The return parameters serviceType and realFlag are added.
Agent Group: agentgroup	Querying Information About All Online Agents of the Home VDN	The return parameters inMultimediaConf and ctiStatus are added.
	Querying Agent Information About the Group by A Supervisor	The return parameters inMultimediaConf and ctiStatus are added.
	Querying Agent Information About the Group	- The return parameters inMultimediaConf and ctiStatus are added. - The limitation for allowing only an inspector to query is deleted.
	Querying Detailed Information About A Specified Agent	The return parameters inMultimediaConf and ctiStatus are added.
	Querying Agent Information About a Configured Skill Queue	The return parameters inMultimediaConf and ctiStatus are added.
	Querying Information About Agents That Have Signed In to a Skill Queue	The return parameters inMultimediaConf and ctiStatus are added.
	Querying Information About Specified Agents in Batches	The return parameters inMultimediaConf and ctiStatus are added.
	Performing a Fuzzy Query of Online Agents by Using a Keyword	The return parameters inMultimediaConf and ctiStatus are added.
Call Data: calldata	Querying Call Information	The return parameters userPriority , trunkNo , and logontimes are added.
	Querying Call Information Before Answering a Call	The return parameters userPriority , trunkNo , and logontimes are added.
	Querying Call Information by Call ID	The return parameters userPriority , trunkNo , and logontimes are added.
	Querying Information About Queuing Calls in a Specified Skill Queue	The return parameters userPriority , trunkNo , and logontimes are added.
	Querying Information About Queuing Calls in a Specified IVR System	The return parameters userPriority , trunkNo , and logontimes are added.
Configuration Parameter: queryconfig	Obtaining the Media Gateway Information	The return parameter mgeDomain is added.

Event Changes

Table 3 List of new events

Event Type	Event Name
Events Related to Voice Call	AgentEvent_SipInfo (Receiving a SipInfo Message)
	AgentEvent_AbandonCall (Notifying an Abandoned Call)
	AgentEvent_SuccTransResult (Notifying the Success Transfer Result)
	AgentEvent_ReleaseRequest (Request Release Events)
Events Related to Text Chat	AgentChat_DataRecvedEx (Obtaining a Reply Message in a Text Chat)
	AgentChat_WithoutCallConfirm (Supplementary Reply Message)
	AgentChat_NoRealTimeCall (Non-real-time Call Content Notification)

Event Type	Event Name
	AgentChat_PostDataSuccess (Successfully Sending the Text Chat Content)
	AgentChat_PostDataFailed (Sending the Text Chat Content Failed)
Events Related to Physical Phone	AgentOther_PhoneBusy (Physical Phone of an Agent Busy)
Events Related to Phone Linkage	AgentEvent_linkageCapability (Events Related to Phone Linkage Results)
	AgentEvent_linkagePhoneStatus (Phone Status)
	AgentEvent_linkagePhoneMute (Call Muted in the Phone Linkage State)
	AgentEvent_linkagePhoneUnMute (Muted Call Unmuted in the Phone Linkage State)
	AgentEvent_linkagePhoneCallOut (Outgoing Call Made in the Phone Linkage State)
	AgentEvent_linkagePhoneTransferOut (Call Transferred in the Phone Linkage State)
Conference Call Events	AgentConf_RequestSuccess (Successfully Applying for a Conference Call)
	AgentConf_RequestFailed (Applying for a Conference Call Failed)
	AgentConf_SelfJoinResult (Agent Joined a Conference Call)
	AgentConf_Timeout (Conference Timeout Reminder)
	AgentConf_Ringing (Ringing of a Conference Call)
	AgentConf_ParticipantChanged (Participant Changed)
	AgentConf_SelfLeaveResult (Agent Leaved a Conference Call)
	AgentConf_PresidentChanged (Conference Chair Changed)
	AgentConf_StopVoice (Conference Announcement Ended)
	AgentConf_StopParticipantVoice (Conference Channel Announcement Ended)
	AgentConf_SipInfo (Conference SipInfo Message)
Email Events	AgentMail_Ringing (Ringing of an Email Call)
	AgentMail_Connected (Email Call Setup)
	AgentMail_Received (Email Received)
	AgentMail_Disconnected (Email Call Released)
	AgentMail_Remind (Email Reminder)
	AgentMail_CallOutFailed (Outgoing Email Failed)
	AgentMail_NoAnswer (No Answer to an Email Call)
Telepresence Call Events	AgentVCCall_PhoneStatus (Telepresence Phone Status)
	AgentVCCall_Ringing (Call Ringing)
	AgentVCCall_Connected (Call Setup)
	AgentVCCall_AnswerFailed (Call Answering Failed)
	AgentVCCall_NoAnswer (No Answering of a Telepresence Call)
	AgentVCCall_Release (Call Released)
	AgentVCCall_ReleaseFailed (Call Releasing Failed)
	AgentVCCall_RecordStart (Recording Started)
	AgentVCCall_RecordEnd (Recording Ended)
	AgentVCCall_RecordFailed (Recording Failed)
Other Agent-Related Events	AgentOther_BeQcStart (Inspection on an Agent Started)
	AgentOther_BeQcStop (Inspection on an Agent Stopped)

Table 4 List of modified events

Event Type	Event Name	Changes
Events Related to Recording Playback	AgentMediaEvent_StopPlayDone (Recording Playback Stopped)	The return parameter cause is added.
	AgentMediaEvent_Record (Recording Started)	Return parameters callId , called , caller , and taskId are added.
	AgentMediaEvent_Record_Fail (Recording Start Failed)	Return parameters recordID , fileName , locationId , callId , called , caller , and taskId are added.
	AgentMediaEvent_StopRecordDone (Recording Stopped)	The return parameter taskId is added.
Events Related to Physical Phone	AgentOther_PhoneRelease (Phone in On-Hook State)	The return parameter phoneState is added.

Parent topic: [V200R001C80](#)

V200R001C80

The following tables describe changes made in IPCC V200R001C80 compared with IPCC V200R001C60SPC100.

Interface Changes

Table 1 List of new interfaces

Interface Type	Interface Name
Online Agent: onlineagent	Changing the Password (Extended)
Voice Call: voicecall	Performing Two-Stage Dialing (Extended)
Agent Group: agentgroup	Performing a Fuzzy Query of Online Agents by Using a Keyword
Configuration Parameter: queryconfig	Obtaining the Operation Parameters of a Multimedia Client
	Obtaining the Media Gateway Information
Multimedia Conference: multimediaconf	Applying for a Multimedia Conference
	Inviting an Agent to Join a Multimedia Conference
	Reporting a Multimedia Conference Joining Result
	Stopping a Multimedia Conference
	Querying the Multimedia Conference Status

Table 2 List of modified interfaces

Interface Type	Interface Name	Changes
Online Agent: onlineagent	Logging In	Input argument entryIp is added. Return parameters loginTime and isForceChange are added.
	Logging In to the CCS Only	Return parameters loginTime and isForceChange are added.
	Forcibly Logging In to the CCS Only	Return parameters loginTime and isForceChange are added.
	Forcibly Logging In	Input argument entryIp is added. Return parameters loginTime and isForceChange are added.
	Forcibly Logging In Without Binding the Agent Phone Number	Return parameters loginTime and isForceChange are added.

Table 3 List of abandoned interfaces

Interface Type	Interface Name	Change Reason
Online Agent: onlineagent	Changing the Password	This interface is abandoned due to security reasons. It can be replaced by the interface Changing the Password (Extended) .
Voice Call: voicecall	Performing Two-Stage Dialing	This interface is abandoned because it does not support "#". It can be replaced by the interface Performing Two-Stage Dialing (Extended) .

Event Changes

Table 4 List of new events

Event Type	Event Name
Events related to multimedia conference	AgentEvent_JoinConf (Notification of a Multimedia Conference Message)
	AgentEvent_OnMultimediaConfState (Notification of the Multimedia Conference Status)
	AgentEvent_OnStopMultimediaConf (Multimedia Conference Stopped)

Parent topic: [V200R001C80](#)

V200R001C60

[V200R001C60SPC100](#)

[V200R001C60](#)

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C60SPC100

No change is made in IPCC V200R001C60SPC100 compared with IPCC V200R001C60.

Parent topic: [V200R001C60](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C60

The following tables describe changes made in IPCC V200R001C60 compared with eSpace CC V200R001C50SPC103.

Interface Changes

Table 1 List of new interfaces

Interface Type	Interface Name
Online Agent: onlineagent	Sending a Note (Extended)
Real-Time Quality Control: qualitycontrol	Adjusting the Skill Queue of a Specified Agent

Table 2 List of modified interfaces

Interface Type	Interface Name	Changes
Online Agent: onlineagent	Logging In	Return parameters sipip and sipport are deleted. The return parameter vdnid is added.
	Logging In to the CCS Only	Return parameters sipip and sipport are deleted. The return parameter vdnid is added.
	Forcibly Logging In to the CCS Only	Return parameters sipip and sipport are deleted. The return parameter vdnid is added.
	Forcibly Logging In	Return parameters sipip and sipport are deleted. The return parameter vdnid is added.
	Forcibly Logging In Without Binding the Agent Phone Number	Return parameters sipip and sipport are deleted. The return parameter vdnid is added.

Table 3 List of abandoned interfaces

Interface Type	Interface Name	Change Reason
Online Agent: onlineagent	Sending a Note	This interface is abandoned due to security reasons. It can be replaced by the interface Sending a Note (Extended) .
Call Data: calldata	Configuring Call-Associated Data	This interface is abandoned due to security reasons. It can be replaced by the interface Configuring Call-Associated Data (Expanded) .

Table 4 List of deleted interfaces

Interface Type	Interface Name
Recording and Playback: recordplay	Querying the voice recording file
	Querying the voice recording files of the self
	Querying the voice recording file by callId
	Querying storage path of the voice recording file in ZIP format
	Querying storage path of the voice recording file in WAV format
	Querying storage path of the voice recording file in WAV format by the ID of the recording
Call Data: calldata	Querying information about the historical call records
	Querying information about the historical call records of the self
Real-Time Quality Control: qualitycontrol	Querying the information about video recording
	Querying the detail of URL

Parent topic: [V200R001C60](#)

Basic Interfaces and Events

[Interfaces](#)

[Events](#)

Parent topic: [Agent Server Interfaces \(RESTful\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Interfaces

[Online Agent: onlineagent](#)

[Voice Call: voicecall](#)

[Text Message: textchat](#)

[Recording and Playback: recordplay](#)

[Queue Device: queuedevice](#)

[Agent Group: agentgroup](#)

[Call Data: calldata](#)

[Agent Event: agentevent](#)

[Query Monitoring: querymonitor](#)

[Real-Time Quality Control: qualitycontrol](#)

[Multimedia Conference: multimediaconf](#)

[Conference Call: agentconf](#)

[Emailcall: emailcall](#)

[ECC Interfaces: eccconfig](#)

[Third-Party Control: thirdcontrol](#)

Parent topic: [Basic Interfaces and Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Online Agent: onlineagent

[Logging In](#)

[Forcibly Logging In](#)

[Logging In Through CAC Authentication](#)

[Forcibly Logging In Through CAC Authentication](#)

[Detecting Heartbeat](#)

[Querying Configured Skill Queues](#)

[Querying Configured Skill Queues of the Specified Agents](#)

[Setting Automatic Answering](#)

[Resetting Skill Queues](#)

[Setting Idle](#)

[Setting Busy](#)

[Canceling the Busy State](#)

[Requesting Rest](#)

[Canceling Rest](#)

[Entering the Work State](#)

[Quitting the Work State](#)

[Changing the Password \(Extended\)](#)

[Setting Automatic Entry to Idle State](#)

[Sending a Note \(Extended\)](#)

[Logging Out](#)

[Forcibly Logging Out](#)

[Forcibly Logging Out with a Cause Code](#)

[Getting Agent Status](#)

[Changing the Busy Reason Code](#)

[Unified Logging In \(Public Cloud\)](#)

Parent topic: [Interfaces](#)

Logging In

Interface Description

This interface is used to log in to the system using an agent's ID and password.

Usage Description

1. Prerequisites
 - An agent has not logged in to the system.
2. Precautions
 - If an agent has not logged in to the system, the agent can use the interface to log in.
 - If an agent has logged in to the system, an error is returned when the agent uses the interface, indicating that the agent has logged in. At this time, the agent can use the forcible login interface to forcibly log in.
3. Use restrictions
 - The agent phone parameter is mandatory during login. You must ensure that the terminal corresponding to the agent phone number is in a normal work state.
 - The current system supports only the non-always-off-hook mode. Therefore, automatic entry to the work state must be enabled. You can set **autoenteridle** to **false** in the login interface or invoke the interface described in [Setting Automatic Entry to Idle State](#) to set automatic entry to the work state after login.

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
Request Body			
password	string	Yes	Indicates the password of an agent. The value contains a maximum of 32 characters.
phonenum	string	Yes	Indicates the phone number of an agent. The value contains a maximum of 24 characters.
autoanswer	boolean	No	Indicates whether automatic answering is enabled. The default value is true . This parameter is valid only for voice calls.
autoenteridle	boolean	No	Indicates whether an agent automatically enters the idle state after call release. The default value is true .
releasephone	boolean	No	Indicates whether an agent enters the non-always-off-hook state after the agent hangs up. The default value is true .
agenttype	int	No	Indicates the type of an agent logged in. The default value is 4 . 4: PC+phone agent 11: PC+phone video agent
status	int	No	Indicates the status of an agent right after the agent logs in. The default status is idle. 4: idle 5: work
ip	string	No	Indicates the local IP address of an agent. The default value is 127.0.0.1 . The parameter is used in real-time screen inspection scenarios. The value contains a maximum of 15 characters.
entryip	string	No	Indicates the IP address of the Agent Gateway that the agent connects to. (This parameter is used in VTM scenarios. The corresponding MS address is transferred to the agent based on entryip .)
checkInWebm	boolean	No	Indicates whether to log in to the WebM media server (which needs to be logged in when an agent processes CTD, text chat, and callback request services). The default value is true .
checkInMailm	boolean	No	Indicates whether to log in to the MailM media server (which needs to be logged in when an agent processes email call services). The default value is false .
vcPhoneNumber	string	No	Indicates the VC number. (The value contains a maximum of 24 characters.)
listenStatus	boolean	No	Indicates whether an inspector can listen to agent operations about logging in and out. The default value is false .
pushUrl	string	No	Indicates the URL for receiving the event. The value contains a maximum of 512 characters. If pushUrl is set, the agent event is pushed to the specified URL. For details, see pushUrl Request .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Set-GUID	string	Indicates the GUID returned after login, which is contained in all the subsequent request messages.
Set-Cookie	string	Indicates the cookie returned after login, which is contained in all the subsequent request messages. Modify the following configuration in the agentgateway/WEB-INF/config/basic.properties file: AGENT.COOKIES.WRITEBACK.FLAG = ON The value ON indicates that a cookie is returned; the value OFF indicates that no cookie is returned.
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the return result. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
vdnid	string	Indicates the VDN ID.
workno	string	Indicates the work ID of an agent.
mediatype	string	Indicates the media server to which an agent logs in, such as TTF (first character: CTI Server; second character: WebM; third character: MailM).
loginTime	string	Indicates the login time (timestamp, in milliseconds).
isForceChange	string	Indicates whether the password must be changed at the first login. If the value is true , an agent must change password at the first login.
serverName	string	Indicates the cluster name of the Agent Server to which an agent logs in.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/onlineagent/1010 HTTP/1.1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"password":"","phonenum":"40038","status":"4","releasephone":"false","agenttype":"4"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Set-Cookie:JSESSIONID=97b3ba90ba17dfcfedea36f99a5fc1bd.AgentGateway1; Path=/; HttpOnly Set-GUID:JSESSIONID=590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"vdnid":1,"workno":"291","mediatype":"TTF","loginTime":"1471585949806","isForceChange":"false","serverName":"AgentGateway1"}}</pre>

Triggered Event

- If the status after login is set to idle, the agent receives the following event after login:
[AgentState_Ready \(Idle\)](#)
- If the status after login is set to work, the agent receives the following event after login:
[AgentState_Work \(Working\)](#)

Error Code

- 100-001
- 100-002
- 100-003
- 100-004
- 100-007
- 100-012
- 100-016
- 110-016
- 999-001

Parent topic: [Online Agent: onlineagent](#)

Forcibly Logging In

Interface Description

This interface is used to forcibly log in to the system using an agent's ID and password.

Usage Description

1. Prerequisites
 - None
2. Precautions
 - If an agent has logged in and the **AGENT_FORCE_LOGOUT_SWITCH** parameter in the **basic.properties** file of the Agent Gateway is set to **OFF**, an error is returned when the agent uses the interface, indicating that the agent has logged in and cannot be forcibly logged out.
3. Use restrictions
 - The agent phone parameter is mandatory during login. You must ensure that the terminal corresponding to the agent phone number is in a normal work state.
 - The current system supports only non-long-connection. Therefore, automatic entry to the work state must be enabled. You can set **autoenteridle** to **false** in the login interface or invoke the interface described in [Setting Automatic Entry to Idle State](#) to set automatic entry to the work state after login.

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/forcelogin
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
Request Body			
password	string	Yes	Indicates the password of an agent. The value contains a maximum of 32 characters.
phonenum	string	Yes	Indicates the phone number of an agent. The value contains a maximum of 24 characters.
autoanswer	boolean	No	Indicates whether automatic answering is enabled. The default value is true (effective only to voice calls).
autoenteridle	boolean	No	Indicates whether an agent automatically enters the idle state after call release. The default value is true .
releasephone	boolean	No	Indicates whether an agent enters the non-always-off-hook state after the agent hangs up. The default value is true .
agenttype	int	No	Indicates the type of an agent who signs in. The default value is 4 . 4: PC+phone agent 11: PC+phone video agent
status	int	No	Indicates the status of an agent right after the agent logs in. The default status is idle. 4: idle 5: work
ip	string	No	Indicates the local IP address of an agent. The default value is 127.0.0.1 . The parameter is used in real-time screen inspection scenarios. The value contains a maximum of 15 characters.
entryip	string	No	Indicates the IP address of the Agent Gateway that the agent connects to. (This parameter is used in VTM scenarios. The corresponding MS address is transferred to the agent based on entryip .)
checkInWebm	boolean	No	Indicates whether to log in to the WebM media server (which needs to be logged in when an agent processes CTD, text chat, and callback request services). The default value is true .
checkInMailm	boolean	No	Indicates whether to log in to the MailM media server (which needs to be logged in when an agent processes email call services). The default value is false .
vcPhoneNumber	string	No	Indicates the VC number. (The value contains a maximum of 24 characters.)
listenStatus	boolean	No	Indicates whether an inspector can listen to login and logout operations of an agent. The default value is false .
pushUrl	string	No	Indicates the URL for receiving the event. The value contains a maximum of 512 characters. If pushUrl is set, the agent event is pushed to the specified URL. For details, see pushUrl Request .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
-----------	-----------	-------------

Parameter	Data Type	Description
Response Header		
Set-GUID	string	Indicates the GUID returned after login, which is contained in all the subsequent request messages.
Set-Cookie	string	Indicates the cookie returned after login, which is contained in all the subsequent request messages. Modify the following configuration in the agentgateway/WEB-INF/config/basic.properties file: AGENT.COOKIE.WRITEBACK.FLAG = ON The value ON indicates that a cookie is returned; the value OFF indicates that no cookie is returned.
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
vdnid	string	Indicates the VDN ID.
workno	string	Indicates the work ID of an agent.
mediatype	string	Indicates the media server to which an agent logs in, such as TTF (first character: CTI Server; second character: WebM; third character: MailM).
loginTime	string	Indicates the login time (timestamp, in milliseconds).
isForceChange	string	Indicates whether the password must be changed at the first login. If the value is true , an agent must change password at the first login.
serverName	string	Indicates the cluster name of the Agent Server to which an agent logs in.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/onlineagent/1010/forcelogin HTTP/1.1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"password":"","phonenum":"40038","status":"4","releasephone":"false","agenttype":"4"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Set-Cookie:JSESSIONID=97b3ba90ba17dfcfedea36f99a5fc1bd.AgentGateway1; Path=/; HttpOnly Set-GUID:JSESSIONID=590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"vdnid":1,"workno":"291","mediatype":"TTF","loginTime":"1471585949806","isForceChange":"false","serverName":"AgentGateway1"}}</pre>

Triggered Event

- If the status after login is set to idle, the agent receives the following event after login:
[AgentState_Ready \(Idle\)](#)
- If the status after login is set to work, the agent receives the following event after login:
[AgentState_Work \(Working\)](#)

Error Code

- 100-001
- 100-003
- 100-004
- 100-007
- 100-012
- 100-015
- 100-016
- 100-024
- 100-031
- 110-016
- 999-001

Parent topic: [Online Agent: onlineagent](#)

Logging In Through CAC Authentication

Interface Description

This interface is used to log in to the system using an agent's CAC authentication information.

Usage Description

1. Prerequisites

- An agent has not logged in to the system.
- The agent has invoked the login interface of the CAC to log in to the CAC and has obtained the token.
- The CAC address information has been configured on the WAS.
- The mapping between agent work IDs and CAC login accounts has been configured on the WAS.

2. Precautions

- If an agent has not logged in to the system, the agent can use the interface to log in.
- If an agent has logged in to the system, an error is returned when the agent uses the interface, indicating that the agent has logged in. At this time, the agent can use the interface for forcible login through CAC authentication to forcibly log in.

3. Use restrictions

- The authentication token of the CAC is mandatory during login.
- The current system supports only non-long-connection. Therefore, automatic entry to the work state must be enabled. You can set **autoenteridle** to **false** in the login interface or invoke the interface described in [Setting Automatic Entry to Idle State](#) to set automatic entry to the work state after login.

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/loginbyportal
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
Request Body			
token	string	Yes	Indicates the CAC authentication token. (The value contains a maximum of 256 characters and cannot be empty.)
phonenum	string	Yes	Indicates the phone number of an agent. (The value contains a maximum of 24 characters.)
autoanswer	boolean	No	Indicates whether automatic answering is enabled. The default value is true (effective only to voice calls).
autoenteridle	boolean	No	Indicates whether an agent automatically enters the idle state after call release. The default value is true .
releasephone	boolean	No	Indicates whether an agent enters the non-always-off-hook state after the agent hangs up. The default value is false .
agenttype	int	No	Indicates the type of an agent who signs in. The default value is 4 . • 4: PC+phone agent • 11: PC+phone video agent
status	int	No	Indicates the status of an agent right after the agent logs in. The default status is idle. • 4: idle • 5: work
ip	string	No	Indicates the local IP address of an agent. The default value is 127.0.0.1 . The parameter is used in real-time screen inspection scenarios. The value contains a maximum of 15 characters.
entryIp	string	No	Indicates the IP address of the Agent Gateway that the agent connects to. (This parameter is used in VTM scenarios. The corresponding MS address is transferred to the agent based on entryIp .)
checkInWebm	boolean	No	Indicates whether to log in to the WebM media server (which needs to be logged in when an agent processes CTD, text chat, and callback request services). The default value is true .
checkInMailm	boolean	No	Indicates whether to log in to the MailM media server (which needs to be logged in when an agent processes email call services). The default value is false .
vcPhoneNumber	string	No	Indicates the VC number. (The value contains a maximum of 24 characters.)
listenStatus	boolean	No	Indicates whether an inspector can listen to login and logout operations of an agent. The default value is false .
pushUrl	string	No	Indicates the URL for receiving the event. The value contains a maximum of 512 characters. If pushUrl is set, the agent event is pushed to the specified URL. For details, see pushUrl Request .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Set-GUID	string	Indicates the GUID returned after login, which is contained in all the subsequent request messages.
Set-Cookie	string	Indicates the cookie returned after login, which is contained in all the subsequent request messages. Modify the following configuration in the agentgateway/WEB-INF/config/basic.properties file: AGENT.COOKIE.WRITEBACK.FLAG = ON The value ON indicates that a cookie is returned; the value OFF indicates that no cookie is returned.
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
vdnid	string	Indicates the VDN ID.
workno	string	Indicates the work ID of an agent.
mediatype	string	Indicates the media server to which an agent logs in, such as TTF (first character: CTI Server; second character: WebM; third character: MailM).
loginTime	string	Indicates the login time (timestamp, in milliseconds).
isForceChange	string	Indicates whether to force an agent to change the password. If the value is true , an agent must change the password after login.
serverName	string	Indicates the cluster name of the Agent Server to which an agent logs in.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/onlineagent/loginbyuportal HTTP/1.1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"token":"MTUwNDc0NDQzMjMzNzcwNjklNzMxMzgzNDk1MDU3OTQ2NjY2OTU5MDE5OjExMDA4BvbnRhcC5pY3AuY29t","password":"","phonenum":"40038","status":"4","releasephone":"false","agenttype":"4"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Set-Cookie:JSESSIONID=97b3ba90ba17dfcfedea36f99a5fc1bd.AgentGateway1; Path=/; HttpOnly Set-GUID:JSESSIONID=590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"vdnid":1,"workno":"291","mediatype":"TTF","loginTime":"1471585949806","isForceChange":"false"}}</pre>

Triggered Event

- If the status after login is set to idle, the agent receives the following event after login:
[AgentState_Ready_\(Idle\)](#)
- If the status after login is set to work, the agent receives the following event after login:
[AgentState_Work_\(Working\)](#)

Error Code

- 100-001
- 100-002
- 100-003
- 100-004
- 100-007
- 100-012
- 100-015
- 100-016
- 100-017
- 110-016
- 999-001

Parent topic: [Online Agent: onlineagent](#)

Forcibly Logging In Through CAC Authentication

Interface Description

This interface is used to forcibly log in to the system using an agent's CAC authentication information.

Usage Description

1. Prerequisites

- The agent has invoked the login interface of the CAC to log in to the CAC and has obtained the token.
- The CAC address information has been configured on the WAS.
- The mapping between agent work IDs and CAC login accounts has been configured on the WAS.

2. Precautions

- If an agent has logged in and the **AGENT_FORCE_LOGOUT_SWITCH** parameter in the **basic.properties** file of the Agent Gateway is set to **OFF**, an error is returned when the agent uses the interface, indicating that the agent has logged in and cannot be forcibly logged out.

3. Use restrictions

- The authentication token of the CAC is mandatory during login.
- The current system supports only non-long-connection. Therefore, automatic entry to the work state must be enabled. You can set **autoenteridle** to **false** in the login interface or invoke the interface described in [Setting Automatic Entry to Idle State](#) to set automatic entry to the work state after login.

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/forceloginbyportal
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
Request Body			
token	string	Yes	Indicates the CAC authentication token. (The value contains a maximum of 256 characters and cannot be empty.)
phonenum	string	Yes	Indicates the phone number of an agent. (The value contains a maximum of 24 characters.)
autoanswer	boolean	No	Indicates whether automatic answering is enabled. The default value is true (effective only to voice calls).
autoenteridle	boolean	No	Indicates whether an agent automatically enters the idle state after call release. The default value is true .
releasephone	boolean	No	Indicates whether an agent enters the non-always-off-hook state after the agent hangs up. The default value is false .
agenttype	int	No	Indicates the type of an agent who signs in. The default value is 4 . • 4: PC+phone agent • 11: PC+phone video agent
status	int	No	Indicates the status of an agent right after the agent logs in. The default status is idle. • 4: idle • 5: work
ip	string	No	Indicates the local IP address of an agent. The default value is 127.0.0.1 . The parameter is used in real-time screen inspection scenarios. The value contains a maximum of 15 characters.
entryip	string	No	Indicates the IP address of the Agent Gateway that the agent connects to. (This parameter is used in VTM scenarios. The corresponding MS address is transferred to the agent based on entryip .)
checkInWebm	boolean	No	Indicates whether to log in to the WebM media server (which needs to be logged in when an agent processes CTD, text chat, and callback request services). The default value is true .
checkInMailm	boolean	No	Indicates whether to log in to the MailM media server (which needs to be logged in when an agent processes email call services). The default value is false .
vcPhoneNumber	string	No	Indicates the VC number. (The value contains a maximum of 24 characters.)
listenStatus	boolean	No	Indicates whether an inspector can listen to login and logout operations of an agent. The default value is false .
pushUrl	string	No	Indicates the URL for receiving the event. The value contains a maximum of 512 characters. If pushUrl is set, the agent event is pushed to the specified URL. For details, see pushUrl Request .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Set-GUID	string	Indicates the GUID returned after login, which is contained in all the subsequent request messages.
Set-Cookie	string	Indicates the cookie returned after login, which is contained in all the subsequent request messages. Modify the following configuration in the agentgateway/WEB-INF/config/basic.properties file: AGENT.COOKIE.WRITEBACK.FLAG = ON The value ON indicates that a cookie is returned; the value OFF indicates that no cookie is returned.
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
result	Map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
vdnid	string	Indicates the VDN ID.
workno	string	Indicates the work ID of an agent.
mediatype	string	Indicates the media server to which an agent logs in, such as TTF (first character: CTI Server; second character: WebIM; third character: MailIM).
loginTime	string	Indicates the login time (timestamp, in milliseconds).
isForceChange	string	Indicates whether to force an agent to change the password. If the value is true , an agent must change the password after login.
serverName	string	Indicates the cluster name of the Agent Server to which an agent logs in.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/onlineagent/forceloginbyuportal HTTP/1.1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"token":"MTUwNDc0NDQzMjMzNzcwNjklNzMzMzglNDA4MTk1MDU3OTQ2NjY2OTU5MDE5OjExMDBADXBvcnRhbc5pY3AuY29t","password":"","phonenum":"40038","status":"4","releasephone":"false","agenttype":"4"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Set-Cookie:JSESSIONID=97b3ba90ba17dfcfedea36f99a5fc1bd.AgentGateway1; Path=/; HttpOnly Set-GUID:JSESSIONID=590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"vdnid":1,"workno":"291","mediatype":"TTF","loginTime":"1471585949806","isForceChange":"false","serverName":"AgentGateway"}}</pre>

Triggered Event

- If the status after login is set to idle, the agent receives the following event after login:
[AgentState_Ready \(Idle\)](#)
- If the status after login is set to work, the agent receives the following event after login:
[AgentState_Work \(Working\)](#)

Error Code

- 100-001
- 100-002
- 100-003
- 100-004
- 100-007
- 100-012
- 100-015
- 100-016
- 100-017
- 110-016
- 999-001

Parent topic: [Online Agent: onlineagent](#)

Detecting Heartbeat

Interface Description

This interface is used to detect an agent's heartbeat after login.

NOTE

If **pushUrl** is set during login of an agent, the agent needs to invoke this interface every minute.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/heartbeat
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
loginTime	long	Indicates the time when an agent logs in (timestamp, in milliseconds).

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/onlineagent/1010/heartbeat HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"loginTime":1512959351001}}</pre>

Triggered Event

- None

Error Code

- 000-003
- 100-006

Parent topic: [Online Agent: onlineagent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying Configured Skill Queues

Interface Description

The interface is used by an agent that has logged in to query configured skill queue information.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/agentskills
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
name	string	Indicates the name of a skill.
id	int	Indicates the ID of a skill.
mediatype	int	Indicates the media type. See Table 1 .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/onlineagent/1010/agentskills HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0", "result": [{"name": "text_chat_jinsitao", "id": 10, "mediatype": 1}, {"name": "voice_jinsitao", "id": 25, "mediatype": 5}]}</pre>

Triggered Event

- None

Error Code

- 000-003
- 100-006
- 100-007

Parent topic: [Online Agent: onlineagent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying Configured Skill Queues of the Specified Agents

Interface Description

The interface is used by an agent that has logged in to query configured skill queue information of specified agents.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/agentskillsbyworkno/{workno}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
workno	int	Yes	Indicates the work ID of the agent to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
name	string	Indicates the name of a skill.
id	int	Indicates the ID of a skill.
mediatype	int	Indicates the media type. See Table 1 .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/onlineagent/1010/agentskillsbyworkno/1020 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0", "result": [{"name": "text chat_jinsitao", "id": 10, "mediatype": 1}, {"name": "voice_jinsitao", "id": 25, "mediatype": 5}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Online Agent: onlineagent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Setting Automatic Answering

Interface Description

This interface is used to set whether agent automatic answering is enabled.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
None
3. Use restrictions
This parameter is valid only for voice calls.

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/autoanswer/{isautoanswer}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
isautoanswer	string	Yes	Indicates whether automatic answering is enabled. true : automatic answering; false : manual answering
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/onlineagent/1010/autoanswer/true HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- None

Error Code

- 100-006

Parent topic: [Online Agent: onlineagent](#)

Resetting Skill Queues

Interface Description

This interface is used to reset skill queues.

Usage Description

1. Prerequisites
An agent has logged in to the system and bound a phone number.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/resetskill/{autoflag}?skillid={skillid}&phonelinkage={phonelinkage}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
autoflag	string	Yes	Indicates whether to automatically log in to the skill queue. true : automatic login; false : manual login.
skillid	string	No	Indicates the ID of a skill queue. (When autoflag is set to false , skillid is mandatory and is a list of skill queue IDs, for example, 1;2;3 . The skill queue that the agent logs in to is the intersection of the value and the skill queues to which the agent belongs. The maximum length of the value is 1024 bytes.)
phonelinkage	int	Yes	Indicates whether to enable phone linkage. 1: yes; 0: no
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/onlineagent/1010/resetskill/false?skillid=&phonelinkage=1 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- None

Error Code

- 000-002

- 100-006
- 100-007

Parent topic: [Online Agent: onlineagent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Setting Idle

Interface Description

This interface is used to set the agent state to idle.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/sayfree
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/onlineagent/1010/sayfree HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- If an agent in busy state invokes the idle setting interface, the agent receives the following event:
[AgentState_CancelNotReady_Success \(Quitting the Busy State Successfully\)](#)
- If an agent in rest state invokes the idle setting interface, the agent receives the following event:
[AgentState_CancelRest_Success \(Quitting the Resting State Successfully\)](#)
- If an agent in work state invokes the idle setting interface, the agent receives the following event:
[AgentState_CancelWork_Success \(Quitting the Working State\)](#)

Error Code

- 100-006
- 100-007

- 100-009

Parent topic: [Online Agent: onlineagent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Setting Busy

Interface Description

This interface is used to set the agent state to busy.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/saybusy?reason={reason}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
reason	int	No	Indicates the busy reason code. The value ranges from 200 to 250. If the value is 0 or left empty, no reason code is set. You can set it to any value in a specified range.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST/agentgateway/resource/onlineagent/1010/saybusy?reason=0 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- [AgentState_SetNotReady_Success \(Indicating Busy Successfully\)](#)

Error Code

- 000-002
- 100-006
- 100-007
- 100-009

Parent topic: [Online Agent: onlineagent](#)

Canceling the Busy State

Interface Description

This interface is used to cancel the busy state of an agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in busy state.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/cancelbusy
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/onlineagent/1010/cancelbusy HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- [AgentState_CancelNotReady_Success \(Quitting the Busy State Successfully\)](#)

Error Code

- 100-006
- 100-007
- 100-009

Parent topic: [Online Agent: onlineagent](#)

Requesting Rest

Interface Description

This interface is used by an agent to request rest.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/rest/{time}/{restcause}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
time	int	Yes	Indicates the rest duration. (Unit: second. Range: 1-86399)
restcause	int	Yes	Indicates the rest reason code. (The value ranges from 0 to 255. The value 0 indicates that there is no rest reason code. You can query the rest reason codes configured on the platform using the Querying All Resting Reason Codes of the Home VDN interface.)
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	POST/agentgateway/resource/onlineagent/1010/rest/200/0 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": {} }

Triggered Event

- [AgentState_SetRest_Success \(Requesting Rest Successfully\)](#)
- If the agent rest event is triggered after the requested rest time, the agent receives the following event:
[AgentState_Rest_Timeout \(Rest Timeout Reminder\)](#)

Error Code

- 100-006
- 100-007

- 100-009

Parent topic: [Online Agent: onlineagent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Canceling Rest

Interface Description

This interface is used by an agent to cancel rest.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in rest state.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/cancelrest
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	POST/agentgateway/resource/onlineagent/1010/cancelrest HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": {} }

Triggered Event

- [AgentState_CancelRest_Success](#) (Quitting the Resting State Successfully).

Error Code

- 100-006
- 100-007
- 100-009

Parent topic: [Online Agent: onlineagent](#)

Entering the Work State

Interface Description

This interface is used by an agent to enter the work state.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/work
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST/agentgateway/resource/onlineagent/1010/work HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- [AgentState_SetWork_Success \(Turning to the Working State\)](#)

Error Code

- 100-006
- 100-007
- 100-009

Parent topic: [Online Agent: onlineagent](#)

Quitting the Work State

Interface Description

This interface is used by an agent to quit the work state.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/cancelwork
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Server.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST/agentgateway/resource/onlineagent/1010/cancelwork HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- [AgentState_CancelWork_Success \(Quitting the Working State\)](#)

Error Code

- 100-006
- 100-007
- 100-009

Parent topic: [Online Agent: onlineagent](#)

Changing the Password (Extended)

Interface Description

This interface is used to change a password.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - The length of the new password must be from 8 to 32 characters.
 - The new password cannot contain more than 2 duplicate characters.
 - The new password cannot contain more than 3 consecutive characters in workno.
 - The new password contains more than 3 types in upper case letter, lower case letter, a number and special character.
 - The new password must be different from the last 5 passwords (configurable on the WAS).
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/modifyaccountpwdex
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
oldPassword	string	Yes	Indicates the old password of an agent. The value contains a maximum of 32 characters.
newPassword	string	Yes	Indicates the new password of an agent. The value contains a maximum of 32 characters.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST/agentgateway/resource/onlineagent/1010/modifyaccountpwdex HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"oldPassword": "cti-1234", "newPassword": "Huawei@123"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Online Agent: onlineagent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Setting Automatic Entry to Idle State

Interface Description

This interface is used to set whether an agent enters the idle state after releasing a call.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
In non-always-off-hook scenarios, automatic entry to the work state must be enabled. Otherwise, the call processing may be abnormal.
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/autoenteridle/{flag}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
flag	string	Yes	Indicates whether an agent enters the idle state. (true : Automatically enter the idle state. false : Enter the work state.)
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST/agentgateway/resource/onlineagent/1010/autoenteridle/false HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Online Agent: onlineagent](#)

Sending a Note (Extended)

Interface Description

This interface is used by an agent to send a note.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/sendnoteletex
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
agentIds	int[]	Yes	Indicates the work IDs of note recipients. A maximum of 100 agent work IDs are supported.
content	string	Yes	Indicates the note content. The value contains a maximum of 1023 bytes.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	array	Indicates the work ID of a recipient who fails to receive the note.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST/agentgateway/resource/onlineagent/1010/sendnoteletex HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"agentIds":[1014,1018,1250,2230],"content":"hello"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0", "result": null}</pre>

Triggered Event

- None

Error Code

- 100-001
- 100-006
- 100-007

Logging Out

Interface Description

This interface is used to log out an agent.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
None
3. Use restrictions
When there is a call on the agent, the agent cannot log out.

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/logout
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/onlineagent/1010/logout HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- [AgentOther_ShutdownService \(Logout Success\)](#)

NOTE

If the agent actively logs out, the event will not always be received. If the event is received, the agent has been logged out.

Error Code

- 100-005
- 100-006
- 100-007
- 100-008

Forcibly Logging Out

Interface Description

This interface is used to forcibly log out an agent.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/forcelogout
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/onlineagent/1010/forcelogout HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- [AgentOther_ShutdownService \(Logout Success\)](#)

NOTE

If the agent actively logs out, the event will not always be received. If the event is received, the agent has been logged out.

Error Code

- None

Parent topic: [Online Agent: onlineagent](#)

Forcibly Logging Out with a Cause Code

Prerequisites

- The agent has logged in.

Interface Description

This interface is used to forcibly log out an agent with a cause code.

Usage Description

- Prerequisites
The agent has logged in.
- Precautions
None
- Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/forcelogoutwithreason/{reason}
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
reason	int	Yes	Indicates the cause code of agent logout (ranging from 1 to 255). This parameter can be set randomly within the specified range.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/onlineagent/1010/forcelogoutwithreason/22 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- [AgentOther_ShutdownService \(Logout Success\)](#)

NOTE

If the agent actively logs out, the event will not always be received. If the event is received, the agent has been logged out.

Error Code

- None

Parent topic: [Online Agent: onlineagent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Getting Agent Status

Prerequisites

- The agent has logged in.

Interface Description

This interface is used to get the current status of the agent.

Usage Description

- Prerequisites
The agent has logged in.
- Precautions
None
- Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/agentstatus
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	Map	For details, see Table 3 .

Table 3 Agent status information

Parameter	Data Type	Description
agentState	int	Indicates the current state of the agent. For details, see: Table 1
isWorking	boolean	The value false indicates that the agent is not in a call. The value true indicates that the agent is in a call.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/onlineagent/1010/agentstatus HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"agentState":4,"isWorking":false}}</pre>

Triggered Event

- None

Error Code

- 000-002

Parent topic: [Online Agent: onlineagent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Changing the Busy Reason Code

Prerequisites

- The agent has logged in.
- The agent is in busy state.

Interface Description

The application invokes this method to set a new busy reason.

Usage Description

1. Prerequisites
The agent has logged in.
The agent is in busy state.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/changebusyreason?reason={reason}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
reason	int	Yes	Indicates the busy reason code. The value is an integer ranging from 200 to 250.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/onlineagent/1002/changebusyreason?reason=201 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006

- 100-022
- 900-001
- 900-002
- 900-003

Parent topic: [Online Agent: onlineagent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Unified Logging In (Public Cloud)

Interface Description

This interface is used to log in to the system using an agent's CAC authentication information.

Usage Description

1. Prerequisites
 - The CAC address information has been configured on the WAS.
 - The mapping between agent work IDs and CAC login accounts has been configured on the WAS.
2. Precautions
 - If the current agent has not logged in or has logged in, you can use this interface to forcibly log in to the system.
3. Use restrictions
 - This interface is provided for the public cloud.
 - The CAC authentication account and password are mandatory and must be carried during login.
 - The current system supports only non-long-connection. Therefore, automatic entry to the work state must be enabled. You can set **autoenteridle** to **false** in the login interface or invoke the interface described in [Setting Automatic Entry to Idle State](#) to set automatic entry to the work state after login.

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/loginbyaccount
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
Request Body			
account	string	Yes	Indicates the authentication account of the CAC. The value contains a maximum of 40 characters and cannot be empty.
password	string	Yes	Indicates the password of the CAC authentication account. The value contains a maximum of 32 characters.
autoanswer	boolean	No	Indicates whether automatic answering is enabled. The default value is true (effective only to voice calls).
autoenteridle	boolean	No	Indicates whether an agent automatically enters the idle state after call release. The default value is true .
releasephone	boolean	No	Indicates whether an agent enters the non-always-off-hook state after the agent hangs up. The default value is true .
agenttype	int	No	Indicates the type of an agent who signs in. The default value is 4 . • 4: PC+phone agent • 11: PC+phone video agent
status	int	No	Indicates the status of an agent right after the agent logs in. The default status is idle. • 4: idle • 5: work
ip	string	No	Indicates the local IP address of an agent. The default value is 127.0.0.1 . The parameter is used in real-time screen inspection scenarios. The value contains a maximum of 15 characters.
entryip	string	No	Indicates the IP address of the Agent Gateway that the agent connects to. (This parameter is used in VTM scenarios. The corresponding MS address is transferred to the agent based on entryip .)
checkInWebm	boolean	No	Indicates whether to log in to the WebM media server (which needs to be logged in when an agent processes CTD, text chat, and callback request services). The default value is true .
checkInMailm	boolean	No	Indicates whether to log in to the MailM media server (which needs to be logged in when an agent processes email call services). The default value is false .
vcPhoneNumber	string	No	Indicates the VC number. (The value contains a maximum of 24 characters.)
listenStatus	boolean	No	Indicates whether an inspector can listen to login and logout operations of an agent. The default value is false .
pushUrl	string	No	Indicates the URL for receiving the event. The value contains a maximum of 512 characters. If pushUrl is set, the agent event is pushed to the specified URL. For details, see pushUrl Request .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Set-GUID	string	Indicates the GUID returned after login, which is contained in all the subsequent request messages.
Set-Cookie	string	Indicates the cookie returned after login, which is contained in all the subsequent request messages. Modify the following configuration in the agentgateway/WEB-INF/config/basic.properties file: AGENT.COOKIE.WRITEBACK.FLAG = ON The value ON indicates that a cookie is returned; the value OFF indicates that no cookie is returned.
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
result	Map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
vdnid	string	Indicates the VDN ID.
workno	string	Indicates the work ID of an agent.
mediatype	string	Indicates the media server to which an agent logs in, such as TTF (first character: CTI Server; second character: WebIM; third character: MailIM).
loginTime	string	Indicates the login time (timestamp, in milliseconds).
isForceChange	string	Indicates whether to force an agent to change the password. If the value is true , an agent must change the password after login.
serverName	string	Indicates the cluster name of the Agent Server to which an agent logs in.
account	string	Indicates the CAC authentication account.
AccessToken	string	Indicates the token returned by the CAC.
phoneNum	string	Indicates the SIP number.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/onlineagent/loginbyaccount HTTP/1.1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"password":"Huawei@4d56","account":"122"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Set-Cookie:JSESSIONID=97b3ba90ba17dfcfedea36f99a5fclbd.AgentGateway1; Path=/; HttpOnly Set-GUID:JSESSIONID=590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 { "result": { "workno": "1002", "loginTime": "1536721625893", "vdnid": 1, "AccessToken": "MTUzNjcYMTQ3Mzc0MzU4OTI5MTcyMDU2NjUxOTg0MjI4MjAzNzc3MDgwODMzOjExMDYBMTA5MTc1LjE5LjE2Mw==", "serverName": "AgentGateway1", "isForceChange": "false", "phoneNum": "10093", "mediatype": "FFF", "account": "122" }, "message": "", "retcode": "0" }</pre>

Triggered Event

- If the status after login is set to idle, the agent receives the following event after login:
[AgentState_Ready \(Idle\)](#)
- If the status after login is set to work, the agent receives the following event after login:
[AgentState_Work \(Working\)](#)

Error Code

- 100-001
- 100-003
- 100-004
- 100-007
- 100-012
- 100-015
- 100-016
- 110-016
- 999-001
- 200-028
- 100-062
- 100-061
- 100-060

Voice Call: voicecall

[Making an Outgoing Call](#)

[Answering a Call](#)

[Making an Internal Call](#)

[Answering a Call in the Phone Linkage State](#)

[Rejecting a Call in the Phone Linkage State](#)

[Restoring a Line in the Phone Linkage State](#)

[Asking for Internal Help](#)

[Muting an Ongoing Call](#)

[Unmuting a Muted Call](#)

[Holding a Call](#)

[Unholding a Call](#)

[Transferring a Call](#)

[Canceling a Transfer](#)

[Performing Two-Stage Dialing \(Extended\)](#)

[Making a Three-Party Call](#)

[Connecting a Held Call](#)

[Disconnecting a Call of a Specified ID](#)

[Dropping a Call](#)

[Requesting an Agent for Call Pickup](#)

[Setting the Customer Level](#)

[Internal Call to a Skill Queue](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Making an Outgoing Call

Interface Description

This interface is used by an agent that has logged in to make an outgoing call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is not answering any call (except a held call).
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/callout
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
caller	string	No	Indicates the calling number. The value is a number of 0-24 digits. This parameter can be left empty. If it is empty, the default calling number of the platform is used.
called	string	Yes	Indicates the called number. The value consists of 1 to 24 digits, asterisk (*), or number sign (#) and cannot be left empty.
skillid	int	No	Indicates the voice skill ID corresponding to the current agent. The value is a number and can be left empty. If the value is empty, the default skill queue ID configured on the platform is used. During report statistics, the traffic data of the current call is collected for the skill.
callappdata	string	No	Indicates the channel-associated data. This parameter can be left empty or contains a maximum of 16000 bytes.
mediaability	int	No	Indicates media capability. The default value is 0 . 0 : audio 1 : video 2 : default capability, negotiated by the agent and user's phone

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	string	Indicates the unique call ID returned upon successful calling.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/voicecall/1010/callout HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8</pre>

Example Type	Reference Format
	Host: 192.168.0.0:8000 {"caller": "40038", "called": "40040", "skillid": 25, "callappdata": "", "mediaability": 1}
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0", "result": "1455885056-1095"}

Triggered Event

- [AgentOther_PhoneAlerting](#) (Phone in Ringing State)
- [AgentOther_PhoneOffhook](#) (Phone in Off-Hook State)
- [AgentState_Busy](#) (Talking)
- [AgentEvent_Customer_Alerting](#) (Customer Ringing)
- [AgentEvent_Talking](#) (Turning to the Talking State)
- [AgentEvent_Call_Out_Fail](#) (Making an Outgoing Call Unsuccessfully)

Error Code

- 000-002
- 100-006
- 100-007
- 200-001
- 200-027

Parent topic: [Voice Call: voicecall](#)

Answering a Call

Interface Description

This interface is used by an agent to answer a voice call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent receives an AgentEvent_Ringing event ([AgentEvent_Ringing\(Incoming Call Reminder\)](#)).
2. Precautions
 - In the phone linkage scenario: If an agent receives the AgentOther_PhoneAlerting event ([AgentOther_PhoneAlerting\(Phone in Ringing State\)](#)), the agent needs to invoke the interface for answering a call in the phone linkage state. After receiving the AgentEvent_Ringing event ([AgentEvent_Ringing\(Incoming Call Reminder\)](#)), the agent can invoke this interface to implement the linkage function.
 - Since IPCC V200R001C80SPC100, the agent can invoke this interface to response to the phone or the call upon receiving the AgentOther_PhoneAlerting event ([AgentOther_PhoneAlerting\(Phone in Ringing State\)](#)). The two modes are supported at the same time.
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/answer
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/voicecall/1010/answer HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- [AgentEvent_Talking\(Turning to the Talking State\)](#)

Error Code

- 100-006
- 100-007
- 200-002

Making an Internal Call

Interface Description

This interface is used by an agent that has logged in to make an internal call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is not answering any call (except a held call).
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/callinner
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
called	string	No	Indicates the called number. The value is a number of 0-24 digits. This parameter can be left empty. If it is empty, the default calling number of the platform is used.
called	string	Yes	Indicates the called number. The value consists of 1 to 24 digits, asterisk (*), or number sign (#) and cannot be left empty.
skillid	string	Yes	Skill queue ID.
callappdata	String	No	Channel-associated data
callcontrolid	long	No	NoPreview control ID.
mediaability	int	Yes	Media capability 0: audio call 2: default

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	string	Indicates the unique call ID returned upon successful calling.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/voicecall/1010/callinner HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"called":"40040","mediaability":2}</pre>

Example Type	Reference Format
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":"1455885056-1095"}</pre>

Triggered Event

- [AgentOther_PhoneAlerting](#) (Phone in Ringing State)
- [AgentOther_PhoneOffhook](#) (Phone in Off-Hook State)
- [AgentState_Busy](#) (Talking)
- [AgentEvent_Customer_Alerting](#) (Customer Ringing)
- [AgentEvent_Talking](#) (Turning to the Talking State)
- [AgentEvent_Inside_Call_Fail](#) (Making an Internal Call Unsuccessfully)

Error Code

- 000-002
- 100-006
- 100-007
- 200-001

Parent topic: [Voice Call: voicecall](#)

Answering a Call in the Phone Linkage State

Interface Description

This interface is used by an agent in the phone linkage state to answer a call after the agent receives the event described in [AgentOther_PhoneAlerting.\(Phone in Ringing State\)](#).

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent receives an AgentOther_PhoneAlerting event ([AgentOther_PhoneAlerting.\(Phone in Ringing State\)](#)).
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/phonepickup
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/voicecall/1010/phonepickup HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- [AgentOther_PhoneOffhook.\(Phone in Off-Hook State\)](#)
- [AgentEvent_Talking.\(Turning to the Talking State\)](#)

Error Code

- 100-006
- 100-007

Parent topic: [Voice Call: voicecall](#)

Rejecting a Call in the Phone Linkage State

Interface Description

This interface is used by an agent in the phone linkage state to reject a call after the agent receives the event described in [AgentOther_PhoneAlerting \(Phone in Ringing State\)](#).

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent receives an AgentOther_PhoneAlerting event ([AgentOther_PhoneAlerting \(Phone in Ringing State\)](#)).
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/phonehangup
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/voicecall/1010/phonehangup HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- [AgentOther_PhoneRelease \(Phone in On-Hook State\)](#)
- [AgentState_SetNotReady_Success \(Indicating Busy Successfully\)](#)

Error Code

- 100-006
- 100-007

Parent topic: [Voice Call: voicecall](#)

Restoring a Line in the Phone Linkage State

Interface Description

In a linkage scenario among multiple IPT and IPCC lines, after an IPT call is released, hold, or transferred to an IPT call, the IPCC line of the phone is held when an agent unholds an IPCC call. If the interface for canceling the holding is invoked, the unhold operation fails. The agent must call the interface for retrieving the IPCC line first.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/resumephoneline
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/voicecall/1010/resumephoneline HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- After the line is successfully restored, the agent receives the following event:

[AgentEvent_linkagePhoneStatus \(Phone Status\)](#)

Error Code

- 200-026
- 100-006
- 100-007

Parent topic: [Voice Call: voicecall](#)

Asking for Internal Help

Interface Description

This interface is used by an agent that has logged in to ask for internal help.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - For video calls, only three-party help is supported.
 - For internal calls, cannot request innerhelp.

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/innerhelp
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
dstaddress	string	Yes	Indicates the helper. When devicetype is set to 1, this parameter indicates a skill queue ID. When devicetype is set to 2, this parameter indicates an agent ID.
devicetype	int	No	Indicates the help device type. The value 1 indicates the skill queue and the value 2 indicates the work ID of the agent. The default value is 2.
mode	int	No	Indicates the help mode. The options are 1 (two-party help) and 2 (three-party help). The default value is 1. For video calls, only three-party help is supported. In two-party help, a user calls agent A, agent A seeks help from agent B, and the call of the user is held. In three-party help, a user calls agent A, agent A seeks help from agent B, and the three parties can talk with each other.
callappdata	string	No	Indicates the call-associated data to be set. This parameter can be left empty or contains a maximum of 16000 bytes.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
result	string	Indicates the unique call ID returned upon successful helping.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/innerhelp HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000 {"dstaddress":49997,"devicetype":2,"mode":1,"callappdata":""}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":0,"result":"1455885056-1095"}</pre>

Triggered Event

- Asking for help during two-party:
[AgentEvent_Hold \(Holding a Call Successfully\)](#)
[AgentEvent_Customer_Alerting \(Customer Ringing\)](#)
[AgentEvent_Talking \(Turning to the Talking State\)](#)
- Asking for help during third-party:
[AgentEvent_Customer_Alerting \(Customer Ringing\)](#)
[AgentEvent_Conference \(Entering Three-Party Conversation Successfully\)](#)

Error Code

- 100-006
- 100-007
- 200-018
- 200-030

Parent topic: [Voice Call: voicecall](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Muting an Ongoing Call

Interface Description

This interface is used by an agent to mute an ongoing call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is making a call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/beginmute
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/beginmute HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 200-003
- 200-004

Parent topic: [Voice Call: voicecall](#)

Unmuting a Muted Call

Interface Description

This interface is used by an agent to unmute a muted call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has muted an ongoing voice call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/endmute
Request Method	POST

Request Message

Table1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/endmute HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 200-007
- 200-008

Holding a Call

Interface Description

This interface is used by an agent to hold an ongoing voice call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in an ongoing voice call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/hold
Request Method	POST

Request Message

Table1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/hold HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- [AgentEvent_Hold \(Holding a Call Successfully\)](#)

Error Code

- 100-006
- 100-007
- 200-013
- 200-014
- 200-029

Unholding a Call

Interface Description

This interface is used by an agent to unhold a held call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has held a call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/gethold?callid={callid}
Request Method	POST

Request Message

Table1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
callid	string	Yes	Indicates the unique call ID.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/gethold?callid=1455885056-1095 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- [AgentEvent_Talking \(Turning to the Talking State\)](#)

Error Code

- 100-006
- 100-007
- 200-015
- 200-016

Parent topic: [Voice Call: voicecall](#)

Transferring a Call

Interface Description

This interface is used by an agent to transfer an established call.

Usage Description

1. Prerequisites

- The agent has logged in.
- The agent is in an ongoing voice call.

2. Precautions

When the agent transfers the incoming call in released transfer mode, the original calling number is sent and the transfer may fail due to carrier's restrictions on the calling number.

3. Use restrictions

- Video calls support only success transfer to agents and skill queues.
- Transfer to agents supports success transfer, released transfer, and designated transfer.
- Transfer to skill queues supports success transfer and released transfer.
- Transfer to IVR supports released transfer and blocked transfer.
- Transfer to access codes supports success transfer and released transfer.
- When an agent calls out, the call cannot be transferred in released transfer mode.

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/transfer
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
devicetype	int	Yes	Indicates the type of the device to which the call is transferred. The value 1 indicates the skill queue, the value 2 indicates the agent, the value 3 indicates IVR, the value 4 indicates the system access code, and the value 5 indicates the outbound number.
address	string	Yes	Indicates the ID of the device to which the call is transferred. The maximum length is 24 bytes. When devicetype is set to 1 , this parameter indicates the skill queue ID. When devicetype is set to 2 , this parameter indicates the agent ID. When devicetype is set to 3 , this parameter indicates the IVR access code. When devicetype is set to 4 , this parameter indicates the system access code. When devicetype is set to 5 , this parameter indicates the external number.
mode	int	Yes	Indicates the transfer mode. In the scenario of transferring a call to an agent, the options are 2 (success transfer), 0 (released transfer), and 3 (designated transfer). In the scenario of transferring a call to a skill queue, the options are 2 (success transfer) and 0 (released transfer). In the scenario of transferring a call to the IVR flow, the options are 0 (released transfer) and 1 (blocked transfer). In the scenario of transferring a call to an access code, the options are 2 (success transfer) and 0 (released transfer). In the scenario of transferring a call to an external number, the options are 1 (released transfer), 2 (success transfer), 3 (talk transfer), and 4 (three-party transfer). The released transfer is not supported for outgoing calls. (For details about common scenarios, see the developer guide.)
callappdata	string	No	Indicates the call-associated data to be set. This parameter can be left empty or contains a maximum of 1024 bytes.
caller	string	No	Indicates the calling number. This parameter is valid when the call is transferred to an external number. The value is a number of 0-24 digits. This parameter can be left empty. If it is empty, the default calling number of the platform is used. When the transfer mode is released transfer, this parameter is invalid. That is, the specified calling number cannot be carried.
mediaability	int	No	Indicates media capability. The default value is 0 . 0 : audio 1 : video It is valid in external call transfers. In other call transfers, the agent type determines whether media capability is mandatory. This parameter is actually invalid because video calls cannot be transferred externally.
imsi	string	No	Indicates the imsi.

Parameter	Data Type	Mandatory (Yes/No)	Description
			This parameter is valid only in mode 1 and 3 when the call is transferred to an external number.

Response Message

Table2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/transfer HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000 {"devicetype":2,"mode":3,"address":"49998","callappdata":"","caller":"40040","mediaability":0}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- If the interface is successfully invoked for released transfer of a call, the agent receives the following events:
 - [AgentOther_PhoneRelease \(Phone in On-Hook State\)](#)
 - [AgentEvent_ReleaseRequest \(Request Release Events\)](#)
 - [AgentEvent_Call_Release \(Agent Exiting a Call\)](#)
 - [AgentEvent_Customer_Release \(User Exiting a Call\)](#)
- If the interface fails to be invoked for released transfer of a call, the agent receives the following event:
 - [AgentEvent_Connect_Fail \(Failure to Connect to an Agent\)](#)
- If the interface is successfully invoked for success transfer of a call, the agent receives the following events:
 - [AgentEvent_Customer_Alerting \(Customer Ringing\)](#)
 - [AgentEvent_SuccTransResult \(Notifying the Success Transfer Result\)](#)
 - [AgentEvent_Call_Release \(Agent Exiting a Call\)](#)
 - [AgentEvent_Customer_Release \(User Exiting a Call\)](#)
 - [AgentOther_PhoneRelease \(Phone in On-Hook State\)](#)
 - [AgentEvent_ReleaseRequest \(Request Release Events\)](#)
- If the interface fails to be invoked for success transfer of a call, the agent receives the following event:
 - [AgentEvent_Connect_Fail \(Failure to Connect to an Agent\)](#)
- If the interface is successfully invoked for designated transfer of a call, the agent receives the following events:
 - [AgentEvent_Customer_Alerting \(Customer Ringing\)](#)
 - [AgentEvent_Call_Release \(Agent Exiting a Call\)](#)
 - [AgentEvent_Customer_Release \(User Exiting a Call\)](#)
 - [AgentOther_PhoneRelease \(Phone in On-Hook State\)](#)
 - [AgentEvent_ReleaseRequest \(Request Release Events\)](#)
- If the interface fails to be invoked for designated transfer of a call, the agent receives the following event:
 - [AgentEvent_Connect_Fail \(Failure to Connect to an Agent\)](#)

Error Code

- 000-002
- 100-006
- 100-007
- 200-012

Parent topic: [Voice Call: voicecall](#)

Canceling a Transfer

Interface Description

This interface is used by an agent to cancel call transfer.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has transferred a call (three-party call to external call).
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/canceltransfer
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/canceltransfer HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- [AgentEvent_Talking \(Turning to the Talking State\)](#)

Error Code

- 100-006
- 100-007
- 200-012

Parent topic: [Voice Call: voicecall](#)

Performing Two-Stage Dialing (Extended)

Interface Description

This interface is used by an agent to perform two-stage dialing during a call. # is supported to dial.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has established a call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/seconddiallex?number={number}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
number	string	Yes	Indicates the number to be dialed for the second time. The value consists of 1 to 24 digits, asterisk (*), or number sign (#).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/seconddiallex?number=30002# HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Voice Call: voicecall](#)

Making a Three-Party Call

Interface Description

This interface is used by an agent to make a three-party call based on an ongoing call or a held call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has established a call.
 - The agent has held a call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/confjoin
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
callid	string	Yes	Indicates the ID of the call that the agent is holding. It cannot be blank.
callappdata	string	No	Indicates the call-associated data to be set. This parameter can be left empty or contains a maximum of 1024 bytes.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/confjoin HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000 {"callid": "1455885056-1095", "callappdata": ""}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- [AgentEvent_Conference \(Entering Three-Party Conversation Successfully\)](#)
- [AgentEvent_Customer_Release \(User Exiting a Call\)](#)

Error Code

- 100-006
- 100-007
- 200-010
- 200-011

Parent topic: [Voice Call: voicecall](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Connecting a Held Call

Interface Description

This interface is used by an agent to connect a held call with an ongoing call. After this operation, the agent's call is released, and a call is established between the other two parties.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has established a call.
 - The agent has held a call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/connecthold/{callid}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
callid	string	Yes	Indicates the ID of the call on hold.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/connecthold/1455885056-1095 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- [AgentEvent_Call_Release \(Agent Exiting a Call\)](#)
- [AgentState_Ready \(Idle\)](#)

Error Code

- 100-006
- 100-007
- 200-005

- 200-006

Parent topic: [Voice Call: voicecall](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Disconnecting a Call of a Specified ID

Interface Description

This interface is used by an agent to disconnect the call with a specified call ID.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in an ongoing call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/dropcall/{callid}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
callid	string	Yes	Indicates the ID of the call to be disconnected.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/dropcall/1455885056-1095 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- [AgentEvent_Call_Release \(Agent Exiting a Call\)](#)
- [AgentEvent_Customer_Release \(User Exiting a Call\)](#)

Error Code

- 100-006
- 100-007
- 200-025

Parent topic: [Voice Call: voicecall](#)

Dropping a Call

Interface Description

This interface is used by an agent to drop an ongoing voice call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in an ongoing voice call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/release
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/voicecall/1010/release HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- [AgentEvent_Call_Release \(Agent Exiting a Call\)](#)
- [AgentEvent_Customer_Release \(User Exiting a Call\)](#)

Error Code

- 100-006
- 100-007
- 200-017

Parent topic: [Voice Call: voicecall](#)

Requesting an Agent for Call Pickup

Interface Description

An agent can designate another agent to answer a voice call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The phone of the designating agent is ringing.
 - The call designated to another agent for pickup is not an internal call.
 - The designated agent and the designating agent belong to the same group.
 - The designated agent has the rights for call pickup.
 - The designated agent is in the idle state.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/snatchpickup?destWorkNo={destWorkNo}
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
destWorkNo	int	Yes	Indicates the designating agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/voicecall/1010/snatchpickup?destWorkNo=1012 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- After the call pickup is successful, the designated agent receives the following event:

[AgentOther_PhoneAlerting \(Phone in Ringing State\)](#)

- After answering the call, the designated agent receives the following event:

[AgentOther_PhoneOffhook \(Phone in Off-Hook State\)](#)

[AgentEvent_Talking \(Turning to the Talking State\)](#)

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Voice Call: voicecall](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Setting the Customer Level

Interface Description

This interface is used by an agent to set the customer level for the current voice call. The setting is only valid to the current call and is not recorded in the customer level table.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in a call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/setcustomerlevel
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
phoneNumber	string	Yes	Indicates the phone number of a customer. Temporarily, this parameter is not in use. It can be any string of no more than 24 characters.
level	int	Yes	Indicates the customer level. The valid customer level codes range from 1 to 254. A larger code indicates a higher customer level and priority.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/voicecall/1010/setcustomerlevel HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"phoneNumber": "70003", "level": 1}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

None

Error Code

- 000-002

- 100-006
- 100-007
- 200-026

Parent topic: [Voice Call: voicecall](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Internal Call to a Skill Queue

Interface Description

This method applies to an internal call to a skill queue or agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - Voice only now.

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/callinnerex2?pdeviceid={pdeviceid}&usmediatype={usmediatype}&helptype={helptype}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
pdeviceid	int	Yes	Indicates the device ID (agent work ID or skill queue ID).
usmediatype	int	Yes	Indicates the media type. Only the value 5 indicating voice is supported.
helptype	int	Yes	Indicates the object from which the agent seeks help (1: skill queue; 2: agent).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	string	Indicates the unique call ID (CallId).

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1002/callinnerex2?pdeviceid=2&usmediatype=5&helptype=1HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":"1455961792-16777554"}</pre>

Triggered Event

- [AgentOther_PhoneAlerting](#) (Phone in Ringing State)
- [AgentOther_PhoneOffhook](#) (Phone in Off-Hook State)
- [AgentState_Busy](#) (Talking)
- [AgentEvent_Customer_Alerting](#) (Customer Ringing)
- [AgentEvent_Talking](#) (Turning to the Talking State)
- [AgentEvent_Inside_Call_Queue_Fail](#) (Transferring a call to a skill queue fails)

Error Code

- 000-002
- 100-006
- 100-007
- 200-001
- 100-021
- 100-023

Parent topic: [Voice Call: voicecall](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Text Message: textchat

[Responding to a Text Chat](#)

[Sending a Text Message](#)

[Requesting an Internal Text Chat](#)

[Transferring a Text Chat](#)

[Terminating a Text Chat](#)

[Rejecting a Text Chat](#)

[Sending Content to a Customer Without Call](#)

[Confirming the Receiving of Non-real-time Call Content](#)

[Confirming the Receiving of a Text Message](#)

[Obtaining Call Content](#)

[Obtaining Call Information](#)

[Querying Content of Interaction Without Call Between an Agent and Customers](#)

[Uploading a Rich Media File](#)

[Downloading a Rich Media File](#)

[Initiating a Three-Party Help Call](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Responding to a Text Chat

Interface Description

This interface is used by an agent to respond to a text chat request.

Usage Description

1. Prerequisites
 - The agent has logged in and has the text chat skill.
 - The agent has received an AgentChat_Ring event ([AgentChat_Ring \(Ringing Before a Text Chat\)](#)).
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/textchat/{workno}/answer/{callid}
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
workno	int	Yes	Indicates the work ID of an agent.
callid	long	Yes	Indicates the ID of the text chat session.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Indicates the text chat session ID returned upon success.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/textchat/1010/answer/1455961792-16777554 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":"1455961792-16777554"}</pre>

Triggered Event

- [AgentState_Busy \(Talking\)](#)
- [AgentChat_Connected \(Text Chat Session Connected\)](#)

Error Code

- 000-002
- 100-006
- 700-001
- 700-002

Sending a Text Message

Interface Description

This interface is used by an agent to send a text message.

Usage Description

1. Prerequisites
 - The agent has logged in and has the text chat skill.
 - The text chat session requested by the agent has been established.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/textchat/{workno}/chatmessage
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
workno	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
callId	string	Yes	Indicates the session ID of a text chat. The ID is mandatory and consists of 1 to 30 characters.
content	string	Yes	Indicates the text chat content. It cannot be blank. It supports a maximum of 6144 characters.
needCheck	boolean	No	Indicates whether the peer party needs to send a confirmation message. The default value is false . This function is only applicable to the SMS service in the ECC scenario. This parameter does not take effect for an internal chat.
chatId	int	No	Indicates the unique number of the currently sent content. This parameter is valid when needCheck is set to true . Upon receiving the content from the agent, the peer replies a confirmation message that contains chatId . The default value is 0 . This parameter can be set randomly within the specified range.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	string	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/textchat/1010/chatmessage HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000 {"callId":"1476952781-16777221","content":"test"}</pre>

Example Type	Reference Format
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":""}</pre>

Triggered Event

When **needCheck** is set to **true**:

- If the agent successfully invokes the interface to send a message but the peer party does not send any confirmation message within 12 seconds, the agent receives the following event:
[AgentChat_PostDataFailed \(Sending the Text Chat Content Failed\)](#)
- If the agent successfully invokes the interface to send a message and then receives a confirmation message from the peer party, the agent receives the following event:
[AgentChat_PostDataSuccess \(Successfully Sending the Text Chat Content\)](#)

Error Code

- 000-002
- 100-006
- 700-001
- 700-012

Parent topic: [Text Message: textchat](#)

Requesting an Internal Text Chat

Interface Description

This interface is used by an agent to request an internal text chat with another agent.

Usage Description

1. Prerequisites
 - The agent has logged in and has the text chat skill.
 - The peer agent has logged in and signed in to the WebM.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/textchat/{workno}/internalcall/{destno}
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
workno	int	Yes	Indicates the work ID of an agent.
destno	int	Yes	Indicates the called work ID.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	string	Indicates the workno of the peer agent returned upon success.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/textchat/1010/internalcall/1011 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":"1010"}</pre>

Triggered Event

- [AgentState_Busy \(Talking\)](#)
- [AgentChat_CallOutCreated \(Internal Text Chat Call Created\)](#)
- [AgentChat_Connected \(Text Chat Session Connected\)](#)
- [AgentChat_CalloutFailed \(Internal Text Chat Call Failed\)](#)

Error Code

- 000-002
- 100-006

- 700-002

Parent topic: [Text Message: textchat](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Transferring a Text Chat

Interface Description

This interface is used by an agent to transfer an established text chat with a customer to another agent.

Usage Description

1. Prerequisites
 - The agent has logged in and has the text chat skill.
 - The agent has established a text chat.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/textchat/{workno}/transfer
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
workno	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
addesstype	int	Yes	Indicates the transfer destination address type. The value 1 indicates work ID and the value 10 indicates skill queue.
destaddr	string	Yes	Indicates the transfer destination address. The value must be a number ranging from 1 to 59999.
callid	string	Yes	Indicates the ID of the text chat session to be transferred. It cannot be blank. It supports a maximum of 30 digits.
attachdata	string	No	Indicates the call-associated data to be set. It can be blank. It supports a maximum of 1024 digits.
mode	int	No	Indicates the transfer type. The default value is 0 . • 0: Released transfer • 1: Success transfer

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/textchat/1010/transfer/ HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000 {"addesstype":1,"destaddr":"291","callid":"1456108492-16777565","attachdata":""}</pre>

Example Type	Reference Format
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- If the interface is successfully invoked for success transfer of a text chat, the agent receives the following events:
[AgentChat_Disconnected \(Text Chat Session Disconnected\)](#)
[AgentChat_TransferStart \(Text Chat Call Transfer Started\)](#)
[AgentEvent_SuccTransResult \(Notifying the Success Transfer Result\)](#)
- If the interface fails to be invoked for success transfer of a text chat, the agent receives the following event:
[AgentChat_TransferFailed \(Text Chat Call Transfer Failed\)](#)
- If the interface is successfully invoked for released transfer of a text chat, the agent receives the following events:
[AgentChat_Disconnected \(Text Chat Session Disconnected\)](#)
[AgentChat_TransferStart \(Text Chat Call Transfer Started\)](#)
- If the interface fails to be invoked for released transfer of a text chat, the agent receives the following event:
[AgentChat_TransferFailed \(Text Chat Call Transfer Failed\)](#)

Error Code

- 000-002
- 100-006
- 700-001
- 700-002

Parent topic: [Text Message: textchat](#)

Terminating a Text Chat

Interface Description

This interface is used by an agent to terminate an ongoing text chat session.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is making a text chat and the session is valid.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/textchat/{workno}/drop/{callid}
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
workno	int	Yes	Indicates the work ID of an agent.
callid	long	Yes	Indicates the ID of the text chat session.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	string	Indicates the text chat session ID returned upon success. It is not returned upon failure.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/textchat/1010/drop/1456111531-16777568 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": "1456111531-16777568"}</pre>

Triggered Event

- [AgentChat_Disconnected \(Text Chat Session Disconnected\)](#)
- [AgentState_Ready \(Idle\)](#)

Error Code

- 000-002
- 100-006
- 700-001

- 700-002

Parent topic: [Text Message: textchat](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Rejecting a Text Chat

Interface Description

This interface is used by an agent to reject a text chat session.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent receives [AgentChat_Ring \(Ringing Before a Text Chat\)](#).
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/textchat/{workno}/reject/{callid}
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
workno	int	Yes	Indicates the work ID of an agent.
callid	long	Yes	Indicates the ID of the text chat session.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	string	Indicates the text chat session ID returned upon success. It is not returned upon failure.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/textchat/1010/reject/1456111531-16777568 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": "1456111531-16777568"}</pre>

Triggered Event

- [AgentChat_Disconnected \(Text Chat Session Disconnected\)](#)
- [AgentState_Ready \(Idle\)](#)

Error Code

- 000-002
- 100-006
- 700-001

- 700-002

Parent topic: [Text Message: textchat](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Sending Content to a Customer Without Call

Interface Description

This interface is used by an agent to send content to the specified customer without call.

NOTE

This interface can be used only to send SMS messages directly to users in the ICP scenario.

Usage Description

1. Prerequisites
 - The agent has logged in to the system and signed in to the WebM.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/textchat/{workno}/sendmessagewithoutcall
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
workno	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
skillId	int	Yes	Indicates the text chat skill.
chatId	int	Yes	Indicates the customized ID of the sent content.
chatReceiver	string	Yes	Indicates the message recipient. The value contains a maximum of 4000 characters.
content	string	Yes	Indicates the message content. The value contains a maximum of 6144 characters and cannot be empty.
jauIP	string	No	Indicates the IP address of the SMS Adapter server. The value contains a maximum of 100 characters.
jauPort	int	No	Indicates the port number of the SMS Adapter.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/textchat/1010/sendmessagewithoutcall HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"skillId": "4", "chatId": "1", "chatReceiver": "121121212", "content": "12121212", "jauIP": "10.177.57.71", "jauPort": "80"}</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": {} }

Triggered Event

- If the customer reports the result after the content is sent successfully, the agent receives the following event:

[AgentChat_WithoutCallConfirm \(Supplementary Reply Message\)](#)

Error Code

- 000-002
- 100-006
- 700-002

Parent topic: [Text Message: textchat](#)

Confirming the Receiving of Non-real-time Call Content

Interface Description

This function is used to send a confirmation message to a user, indicating that the agent has received the non-real-time call content.

NOTE

This interface is only used to confirm that the agent has received an SMS from a user in the ICP scenario.

Usage Description

- Prerequisites
 - The agent has logged in to the system and signed in to the WebM.
 - The agent has received [AgentChat_NoRealTimeCall \(Non-real-time Call Content Notification\)](#).
- Precautions

None
- Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/textchat/{workno}/confirmnorealtimecall
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
workno	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
dataSeqNo	string	Yes	Indicates the number of the non-real-time call content. It supports a maximum of 40 characters. The value is sourced from AgentChat_NoRealTimeCall (Non-real-time Call Content Notification) .
innerSid	int	Yes	Indicates the internal ID of the CTI. The value is sourced from AgentChat_NoRealTimeCall (Non-real-time Call Content Notification) .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/textchat/1010/confirmnorealtimecall HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"dataSeqNo":"1658583507","innerSid":392036552}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

None

Error Code

- 000-002
- 100-006
- 700-002

Parent topic: [Text Message: textchat](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Confirming the Receiving of a Text Message

Interface Description

This function is used to send a confirmation message to a user, indicating that the agent has received the message.

NOTE

This interface is only used to confirm that the agent has received an SMS from a user in the ECC scenario.

Usage Description

1. Prerequisites
 - The agent has logged in to the system and signed in to the WebM.
 - The agent has received the [AgentChat_DataRecvedEx \(Obtaining a Reply Message in a Text Chat\)](#) event.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/textchat/{workno}/confirmmessage
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
workno	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
callId	string	Yes	Indicates the session ID of a text chat. The ID is mandatory and consists of 1 to 30 characters.
sessionId	int	Yes	Indicates the identifier of a user in the CTI. It is obtained from AgentChat_DataRecvedEx (Obtaining a Reply Message in a Text Chat) .
chatId	int	Yes	Indicates the message ID. It is obtained from AgentChat_DataRecvedEx (Obtaining a Reply Message in a Text Chat) .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/textchat/1010/confirmmessage HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"callId":"1476952781-16777221","sessionId":100003,"chatId":1907292548}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

None

Error Code

- 000-002
- 100-006
- 700-002

Parent topic: [Text Message: textchat](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Obtaining Call Content

Interface Description

This interface is used by an agent to query text chat content based on **callId**. A common agent can query only text chat content related to the agent. An agent with the media inspection right can query all text chat content in the VDN.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/textchat/{workno}/callcontent?callId={callId}&pageNo={pageNo}&pageSize={pageSize}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
workno	int	Yes	Indicates the work ID of an agent.
callId	long	Yes	Indicates the call ID for querying content.
pageNo	int	Yes	Indicates the number of a page, which is a pagination condition. The minimum value is 1.
pageSize	int	Yes	Indicates the number of records displayed on a page, which is a pagination condition.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
weccCallContentList	list	For details, see Table 4 .
pageNo	int	Indicates the number of a page, which is a pagination condition.
pageSize	int	Indicates the number of records displayed on a page, which is a pagination condition.
totalCount	int	Indicates the total number of records queried.
totalPageNo	int	Indicates the total number of pages calculated based on the query result.

Table 4 Parameter description of weccCallContentList

Parameter	Data Type	Description
id	long	Indicates the database ID.

Parameter	Data Type	Description
ccId	int	Indicates the contact center ID.
VdnId	int	Indicates the VDN ID.
callId	string	Indicates the call ID.
subMediaType	int	Indicates the sub media type.
sender	string	Indicates the sender.
reciver	string	Indicates the recipient.
contentType	int	Indicates the content type. 0: text 1: content
content	string	Indicates message content.
direction	int	Indicates the sending direction. 0: to an agent 1: to a customer
createTimeLong	long	Indicates the creation time (timestamp, in milliseconds).
updateTimeLong	long	Reserved.
confirmFlag	int	Indicates whether confirmation is required. 0: no 1: yes
status	int	Indicates whether the message has been confirmed. (0: not confirmed; 1: confirmed).
result	string	Indicates the conformation result.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/textchat/1010/callcontent?callId=1456111531-16777568&pageNo=1&pageSize=10 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"totalCount":5,"weccCallContentList":[{"id":30,"ccId":1,"vdnId":1,"callId":"1516934778-16777279","subMediaType":1,"sender":"c2TST88U","reciver":"1045","contentType":0,"content":"aaa","direction":0,"createTimeLong":1516934629000,"updateTimeLong":1516934629000,"confirmFlag":0,"status":0,"result":"0"}],"pageNo":1,"pageSize":1,"totalPageNo":5}}</pre>

Triggered Event

None

Error Code

000-002
100-006
700-018

Parent topic: [Text Message: textchat](#)

Obtaining Call Information

Interface Description

This interface is used by an agent to query call records based on the query criteria. A common agent can query only call records related to the agent. An agent with the media inspection right can query all call records in the VDN.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/textchat/{workno}/callsession
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
workno	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
startTime	long	Yes	Indicates the query start time (timestamp, in milliseconds).
endTime	long	Yes	Indicates the query end time (timestamp, in milliseconds).
pageNo	int	Yes	Indicates the number of a page, which is a pagination condition. The minimum value is 1.
pageSize	int	Yes	Indicates the number of records displayed on a page, which is a pagination condition. The minimum value is 1.
callType	int	No	Indicates the call type. 0: internal call 1: external call
caller	String	No	Indicates the calling party. The value contains a maximum of 32 characters.
called	String	No	Indicates the called party. The value contains a maximum of 32 characters.
realCaller	String	No	Indicates the real name of the calling party. The value contains a maximum of 256 characters. This field is used to supplement the following item: The real name of the calling party in the Creating Quasi-Real-Time Calls can contain only 1 to 20 letters and digits.
callerName	String	No	Indicates the name of the calling party. The value contains a maximum of 256 characters.
mediaType	String	No	Indicates the media type. See Table 1 .
subMediaType	String	No	Indicates the sub media type. The value ranges from 1 to 255. The sub media types can be queried using the interface described in Querying the Sub-media Type of a Skill Queue .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail • 0: Succeed • Other values: Fail

Parameter	Data Type	Description
result	Map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
weccCallBillList	list	For details, see Table 4 .
pageNo	int	Indicates the number of a page, which is a pagination condition.
pageSize	int	Indicates the number of records displayed on a page, which is a pagination condition.
totalCount	int	Indicates the total number of records queried.
totalPageNo	int	Indicates the total number of pages calculated based on the query result.

Table 4 Parameter description of weccCallBillList

Parameter	Data Type	Description
id	long	Indicates the database ID.
cclId	int	Indicates the contact center ID.
vdnId	int	Indicates the VDN ID.
callId	string	Indicates the call ID.
innerCall	int	Indicates whether the call is an internal or external call. The options are as follows: 0 : internal call; 1 : external call.
mediaType	int	Indicates the media type. See Table 1 .
subMediaType	int	Indicates the sub media type.
accessType	int	Reserved.
caller	string	Indicates the calling number.
called	string	Indicates the called number.
accessCode	string	Indicates the access code.
skillId	int	Indicates the ID of a skill.
realCaller	string	Indicates the real calling party.
callerName	string	Indicates the display name.
beginTimeLong	long	Indicates the call start time (timestamp, in milliseconds).
connectTimeLong	long	Indicates the call connection time (timestamp, in milliseconds).
endTimeLong	long	Indicates the call end time (timestamp, in milliseconds).
releaseCause	int	See Table 5 .
platformReleaseCause	string	Table 6
logDateLong	long	Indicates the time when the data is recorded in the database (timestamp, in milliseconds).
callIdNum	int	Indicates the call order.
remark	string	Indicates remarks.
receiveMsgNum	int	Indicates the total number of received messages.
sendMsgNum	int	Indicates the total number of sent messages.

Table 5 Description of releaseCause

Value	Description
1	A user releases the call.
2	An agent transfers the call.
3	An agent releases the call.
4	The call fails to be established.
5	Queuing is canceled.
6	Queuing times out.
7	A user exits.
8	The call is abnormally released.

Table 6 Description of platform releaseCause

Value	Description
1055	The call is normally released.
20153	The call is abnormally released.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/textchat/1010/callsession HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"startTime":1499299200000,"endTime":1503021800000,"pageNo":1,"pageSize":3,"callType":1,"caller":"","called":"","realCaller":"","callerName":"","mediaType":1,"subMediaType":255}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":0,"result":{"totalCount":14,"pageNo":1,"weccCallBillList":[{"id":27,"ccId":1,"vdnId":1,"callId":"1516934778-16777279","innerCall":1,"mediaType":1,"subMediaType":2,"accessType":0,"caller":"c2TST88U","called":"1045","accessCode":"3000401","skillId":6,"realCaller":"c2TST88U","callerName":"c2TST88U","beginTimeLong":1516934869000,"connectTimeLong":1516934870000,"endTimeLong":1516935409000,"releaseCause":3,"platformReleaseCause":"1055","logDateLong":1516935094000,"callidNum":-1,"remark":null,"receiveMsgNum":2,"sendMsgNum":3}],"pageSize":1,"totalPageNo":14}}</pre>

Triggered Event

None

Error Code

- 100-006
- 000-002
- 700-018

Parent topic: [Text Message: textchat](#)

Querying Content of Interaction Without Call Between an Agent and Customers

Interface Description

This interface is used to query content of interaction without call based on the query criteria. A common agent can query only content of interaction without call related to the agent. An agent with the media inspection right can query all content of interaction without call in the VDN.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/textchat/{workno}/contentwithnocall
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
workno	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
startTime	long	Yes	Indicates the query start time (timestamp, in milliseconds).
endTime	long	Yes	Indicates the query end time (timestamp, in milliseconds).
pageNo	int	Yes	Indicates the number of a page, which is a pagination condition. The minimum value is 1.
pageSize	int	Yes	Indicates the number of records displayed on a page, which is a pagination condition. The minimum value is 1.
customer	string	No	Indicates the name of a customer. The value contains a maximum of 64 characters and can be empty.
workNo	string	No	Indicates the work ID of an agent.
subMediaType	int	No	Indicates the sub media type.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
weccnocallcontent	list	See Table 4 .
pageNo	int	Indicates the number of a page, which is a pagination condition. The minimum value is 1.
pageSize	int	Indicates the number of records displayed on a page, which is a pagination condition.

Parameter	Data Type	Description
totalCount	int	Indicates the total number of records queried.
totalPageNo	int	Indicates the total number of pages calculated based on the query result.

Table 4 Parameter description of weccCallBillList

Parameter	Data Type	Description
id	long	Indicates the database ID.
ccId	int	Indicates the contact center ID.
vdnId	int	Indicates the VDN ID.
subMediaType	int	Indicates the sub media type.
sender	string	Indicates the sender.
reciver	string	Indicates the recipient.
content	string	Indicates message content.
direction	int	Indicates the sending direction. 0: to an agent 1: to a customer
status	int	Indicates whether content has been confirmed. (The default value is 0.)
createTime	long	Indicates the creation time.
confirmFlag	int	Indicates whether confirmation is required. 0: no 1: yes
result	string	Indicates the conformation result.
updateTime	long	Indicates the update time.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/textchat/1045/contentwithnocall HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"startTime":1494072000000,"endTime":1502020800000,"customer":"","agentNumber":"261","subMediaType":0,"pageNo":1,"pageSize":5}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {message=, result={weccnocallcontent=[{id=79, ccId=1, vdnId=0, subMediaType=1, sender=1045, reciver=119911, content=119911, direction=1, confirmFlag=0, status=0, createTimeLong=1519614533000, updateTimeLong=1519614533000, result=null}], totalCount=1, pageNo=1, pageSize=5, totalPageNo=1}, retcode=0}</pre>

Triggered Event

None

Error Code

- 100-006
- 000-002
- 700-018

Parent topic: [Text Message: textchat](#)

Uploading a Rich Media File

Interface Description

This interface is used to provide a rich media data transmission channel using the file server after a text chat is established to implement rich media file transmission between agents and customers.

Usage Description

1. Prerequisites
 - The agent has logged in and established a text chat.
 - A rich media file has been configured based on the restrictions described in [Rich Media File Restrictions](#).
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/textchat/{workno}/mediafile?callId={callId}&isNeedConfirm={isNeedConfirm}&chatId={chatId}&msgType={msgType}&remark={remark}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
workno	int	Yes	Indicates the work ID of an agent.
callId	string	Yes	Indicates the call ID of the current text chat. The value contains a maximum of 30 characters.
isNeedConfirm	boolean	No (The value is considered as false if it is empty.)	Indicates whether confirmation from the peer party is required.
chatId	long	Yes when isNeedConfirm is true	Indicates the message ID. The value ranges from 1 to 4294967295.
msgType	string	Yes	Indicates the message type. The value contains a maximum of 10 characters. The value is self defined, used to describe the uploaded file type.
remark	string	No	Indicates remarks. The value contains a maximum of 1024 characters.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
HTTP file format complying with the standards.			

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	See Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
filePath	string	Indicates the path on the file server.
fileName	string	Indicates the name of the file uploaded.

Parameter	Data Type	Description
chatId	long	Indicates the message ID.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/textchat/1010/mediafile?callId=1456108492-16777565&isNeedConfirm=false&chatId=1&msgType=22&remark=test HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"filePath":"XXXX","fileName":"XXXX","chatId":"XXXX"}}</pre>

Triggered Event

When **isNeedConfirm** is set to **true**:

- If the agent successfully invokes the interface to send a message but the peer party does not send any confirmation message within 12 seconds, the agent receives the following event:

[AgentChat_PostDataFailed \(Sending the Text Chat Content Failed\)](#)

- If the agent successfully invokes the interface to send a message and receives a confirmation message, the agent receives the following event:

[AgentChat_PostDataSuccess \(Successfully Sending the Text Chat Content\)](#)

Error Code

- 100-006
- 700-013
- 700-001
- 700-014
- 700-015
- 700-012

Parent topic: [Text Message: textchat](#)

Downloading a Rich Media File

Interface Description

This interface is used to provide a rich media data transmission channel using the file server after a text chat is established to implement rich media file transmission between agents and customers.

Usage Description

1. Prerequisites
 - The agent has logged in and established a text chat.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/textchat/{workno}/mediafile?filePath={filePath}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
workno	int	Yes	Indicates the work ID of an agent.
filePath	String	Yes	Indicates the download path of a rich media file (the value contains a maximum of 200 characters).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

- If the request succeeds, the corresponding file content is returned.
- If the request fails, the corresponding error code and error information are returned, as described in [Table 2](#)

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/textchat/1010/mediafile?filePath=xxx HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"xxx"}</pre>

Triggered Event

None

Error Code

100-006
700-013
700-016
700-017

Initiating a Three-Party Help Call

Prerequisites

- The agent has logged in.

Interface Description

When an agent talks with a user, the agent directly initiates a help call to another agent to form a three-party conversation.

Request Method

POST. This interface supports only POST, but not PUT, GET, DELETE, or other methods.

Request URL

http(s)://ip:port/agentgateway/resource/textchat/{agentid}/innerhelp

In the URL, *ip* indicates the IP address of the Agent Gateway server, *port* indicates the HTTP or HTTPS port number of the Agent Gateway server, and *agentid* indicates the agent ID.

Request Message

- Message header

Parameter	Data Type	Mandatory (Yes/No)	Description
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	No	Indicates the agent authentication information.

- Message body

The following provides an example of the request message body of this interface:

```
{"dstaddress":"187","callId":"1526960019-16777231","callappdata":""}
```

[Table 1](#) describes the parameters in the request message body of this interface.

Table 1 Parameter description

Parameter	Data Type	Mandatory (Yes/No)	Description
dstaddress	string	Yes	Indicates the agent who is asked for help.
callId	string	Yes	Indicates the session ID of a text chat. The ID is mandatory and consists of 1 to 30 characters.
callappdata	string	No	Indicates the call-associated data to be set. This parameter can be left empty.

Response Message

The following provides an example of the response message body of this interface:

```
{"message":"","retcode":"0"}
```

[Table 2](#) describes the parameters in the response message body of this interface.

Table 2 Parameter description

Parameter	Data Type	Description
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail

Triggered Event

- After this interface is invoked, the text chat event (AgentChat_CallOutCreated) is triggered.

Error Code

- 000-002
- 100-006
- 700-001
- 700-002

Parent topic: [Text Message: textchat](#)

Recording and Playback: recordplay

[Starting Playing an Announcement](#)

[Pausing an Announcement](#)

[Resuming an Announcement](#)

[Fast Forwarding](#)

[Rewinding](#)

[Stopping Playing the Announcement](#)

[Query Recording](#)

[Query RecordingEx](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Starting Playing an Announcement

Interface Description

This interface is used to start playing an announcement for an agent.

NOTE

Any recorded file can be played by using this interface. Therefore, there are security risks, and you need to use this interface with caution in secondary development.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is not in a three-party call.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/play
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
voicepath	string	Yes	Indicates the file path. The value contains a maximum of 100 characters.
startpostion	long	No	Indicates the position where the playback starts (timestamp, in milliseconds).
volumechange	string	No	Indicates the playback volume. The default value is 50 . The value is a numeric string of 0 to 5 digits.
speedchange	string	No	Indicates the playback speed. The default value is 50 . The value is a numeric string of 0 to 5 digits.
times	int	No	Indicates the times of playback. The default value is 1 .
codeformat	int	No	Indicates the file coding format. Only the value 0 is supported now. The default value is 0 .
locationid	int	No	Indicates the node location information. The default value is -1 , and the value ranges from -1 to 65535 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/recordplay/{agentid}/play HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8</pre>

Example Type	Reference Format
	Host: 192.168.0.0:8000 {"voicepath":"/root/temp/Users/filename","startpostion":12,"volumechange":20,"speedchange":20,"times":1,"codeformat":0,"locationid":0}
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": {} }

Triggered Event

- If an announcement is successfully played, the agent receives the following events:
[AgentMediaEvent_Play \(Recording Playback Started\)](#)
[AgentMediaEvent_Play_Succ \(Recording Playback Succeeded\)](#)
- If an announcement fails to be played, the agent receives the following events:
[AgentMediaEvent_Play_Fail \(Recording Playback Failed\)](#)
[AgentMediaEvent_StopPlayDone \(Recording Playback Stopped\)](#)

Error Code

- 000-002
- 100-006
- 100-007
- 500-007

Parent topic: [Recording and Playback: recordplay](#)

Pausing an Announcement

Interface Description

This interface is used to pause an announcement.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is playing an announcement.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/pauseplay
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/textchat/1010/pauseplay HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- [AgentMediaEvent_PausePlayDone \(Recording Playback Paused\)](#)

Error Code

- 100-006
- 100-007
- 500-003

Parent topic: [Recording and Playback: recordplay](#)

Resuming an Announcement

Interface Description

This interface is used to resume an announcement for an agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has paused an announcement.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/resumeplay
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/textchat/1010/resumeplay HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- [AgentMediaEvent_ResumePlayDone \(Recording Playback Resumed\)](#)

Error Code

- 100-006
- 100-007
- 500-005

Parent topic: [Recording and Playback: recordplay](#)

Fast Forwarding

Interface Description

This interface is used to fast forward the playback of a recorded file.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is playing an announcement.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/forefast/{time}?seekPosition={seekPosition}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
time	int	Yes	Indicates the fast-forward duration, in seconds. The value ranges from 1 to 999999999.
seekPosition	int	Yes	Indicates relative position of redirection (default value is 0, 0 indicates current position in a file, 1 indicates file header, 2 indicates end of a file).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/textchat/1010/forefast/10?seekPosition=0 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- [AgentMediaEvent_JumpPlayDone \(Recording Playback Fast-Forwarded\)](#)

Error Code

- 100-006
- 100-007
- 500-002

Rewinding

Interface Description

This interface is used to rewind the playback of a recorded file.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is playing an announcement.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/backfast/{time}?seekPosition={seekPosition}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
time	int	Yes	Indicates the rewind duration, in seconds. The value ranges from 1 to 9999999999.
seekPosition	int	Yes	Indicates relative position of redirection (default value is 0, 0 indicates current position in a file, 1 indicates file header, 2 indicates end of a file).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/textchat/1010/backfast/10?seekPosition=0 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- [AgentMediaEvent_JumpPlayDone \(Recording Playback Fast-Forwarded\)](#)

Error Code

- 100-006
- 100-007
- 500-001

Stopping Playing the Announcement

Interface Description

This interface is used to stop playing an announcement.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is playing an announcement.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/stopplay
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/textchat/1010/stopplay HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- [AgentMediaEvent_StopPlayDone \(Recording Playback Stopped\)](#)

Error Code

- 100-006
- 100-007
- 500-009

Parent topic: [Recording and Playback: recordplay](#)

Query Recording

Interface Description

Query the recording information of the specified time range.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

请求URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/recordinfo
请求方法	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
beginTime	string	Yes	Recording start time
endTime	string	Yes	Recording end time
phoneNum	string	Yes	Agent phone number
caller	string	No	caller or callee number

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Recording list information, see Table 3

Table 3 result description

Parameter	Data Type	Description
callId	string	Unique identification of call corresponding to recording
caller	string	Recording caller number
callee	string	Recording callee number
agentId	string	Agent id
beginTime	string	Recording begin time
endTime	string	Recording end time
fileUrl	string	Recording file path

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/recordplay/110/recordinfo HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"phoneNum": "616003", "beginTime": "2021-07-31 23:18:04", "endTime": "2021-08-01 01:18:03", "caller": "616005"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"result":[{"callId":"1626473880-114","caller":"616005","callee":"1610","agentId":"103","beginTime":"2021-07-31 23:18:04","endTime":"2021-07-31 23:28:04","fileUrl":"z:\\1\\0\\20210717\\103\\0618002.V3"}],"message":"","retcode":"0"}</pre>

Triggered Event

NA

Error Code

- 100-025
- 100-026
- 100-027
- 100-028
- 100-029

Parent topic: [Recording and Playback: recordplay](#)

Query RecordingEx

Interface Description

Query the recording information of the specified time range.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

请求URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/recordinfoagents
请求方法	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
beginTime	string	Yes	Recording start time
endTime	string	Yes	Recording end time
callee	string	Yes	callee number
caller	string	Yes	caller number
agents	List<String>	Yes	agents list

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Recording list information, see Table 3

Table 3 result description

Parameter	Data Type	Description
callId	string	Unique identification of call corresponding to recording
caller	string	Recording caller number
callee	string	Recording callee number
agentId	string	Agent id
beginTime	string	Recording begin time
endTime	string	Recording end time
fileUrl	string	Recording file path

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/recordplay/110/recordinfoagents HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"phoneNum": "616003", "beginTime": "2021-07-31 23:18:04","endTime": "2021-08-01 01:18:03","caller": "616005", "callee": "1001","agentsIds": "[101,102]"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"result":[{"callId":"1626473880-114","caller":"616005","callee":"1610","agentId":"103","beginTime":"2021-07-31 23:18:04","endTime":"2021-07-31 23:28:04","fileUrl":"z:\\1\\0\\20210717\\103\\0618002.V3"}],"message":"","retcode":"0"}</pre>

Triggered Event

NA

Error Code

- 100-025
- 100-026
- 100-027
- 100-028
- 100-029
- 100-030

Parent topic: [Recording and Playback: recordplay](#)

Queue Device: queuedevice

[Querying Access Code Information of a VDN](#)

[Querying IVR Information of a VDN](#)

[Obtaining the Number of Users in a Configured Skill Queue](#)

[Obtaining the Number of Users in a Skill Queue](#)

[Querying the Skill Queues to Which a Specified Agent Has Logged In](#)

[Obtaining the Skill Queue Information of a Specified VDN](#)

[Obtaining the Skill Queue Information of the Home VDN of an Agent](#)

[Obtaining the Number of Users in a Specified Skill Queue](#)

[Querying the Statistics About a Set of Skill Queues](#)

[Querying the Statistics About the Next Set of Skill Queues of the Home VDN of an Agent](#)

[Querying the Device Status](#)

[Querying the Sub-media Type of a Skill Queue](#)

[Adding Queue Monitoring](#)

[Stopping Queue Monitoring](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying Access Code Information of a VDN

Interface Description

This interface is used to query the access code information of the home VDN to which an agent has logged in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queuedevice/{agentid}/innoinfo
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	array	Indicates the return result of a successful query, that is, an access code. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
description	string	Indicates the description of an access code.
id	int	Indicates the ID of an access code.
inno	string	Indicates the access code.
vdnid	int	Indicates the VDN ID.
mediatype	int	Media Types

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/queuedevice/1010/innoinfo HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"description": "1008","id": 10,"inno": "1008","vdnid": 1,"mediatype": 1}, {"description": "1011","id": 11,"inno": "1011","vdnid": 1,"mediatype": 1}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 600-003

Parent topic: [Queue Device: queuedevice](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying IVR Information of a VDN

Interface Description

This interface is used to query the IVR information of the home VDN to which an agent has logged in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queuedevice/{agentid}/ivrinfo
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	array	Indicates the return result of a successful query, that is, the IVR information. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
access	string	Indicates the access code of an IVR flow.
id	int	Indicates the ID of an IVR flow.
description	string	Indicates the description of an IVR flow.
serviceNo	int	Indicates the ID of a service type.

Interface Example

Example Type	Reference Format
Example of a request packet	GET /agentgateway/resource/queuedevice/1010/ivrinfo HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{ "access": "3431", "id": 1, "description": "play voice", "serviceNo": 1, "access": "60012", "id": 2, "description": "transferToSkill", "serviceNo": 1 }] }

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 600-004

Parent topic: [Queue Device: queuedevice](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Obtaining the Number of Users in a Configured Skill Queue

Interface Description

This interface is used to query the number of users in a skill queue configured for the current agent that has logged in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queuedevice/{agentid}/waitnum
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	int	Indicates the number of users in a skill queue returned after a successful query.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/queuedevice/1010/waitnum HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":0}</pre>

Triggered Event

- None

Error Code

- 100-006

Parent topic: [Queue Device: queuedevice](#)

Obtaining the Number of Users in a Skill Queue

Interface Description

This interface is used to query the number of users in a skill queue to which an agent has logged in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queuedevice/{agentid}/waitnumbyagent
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	int	Indicates the number of users in a skill queue returned after a successful query.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/queuedevice/1010/waitnumbyagent HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":0}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Queue Device: queuedevice](#)

Querying the Skill Queues to Which a Specified Agent Has Logged In

Interface Description

The interface is used to query the skill queues to which a specified agent has logged in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queuedevice/{agentid}/agentskill/{workNo}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
workNo	int	Yes	Indicates the work ID of the agent to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	array	Indicates the return result of a successful query, that is, skill queue information. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
name	string	Indicates the name of a skill.
id	int	Indicates the ID of a skill.
mediatype	int	Media Types

Interface Example

Example Type	Reference Format
Example of a request packet	GET /agentgateway/resource/queuedevice/1010/agentskill/1011 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{"name": "Text chat_madeqiang", "id": 1, "mediatype": 1}, {"name": "Text chat_jinsitao", "id": 10, "mediatype": 1}] }

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 600-001

Parent topic: [Queue Device: queuedevice](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Obtaining the Skill Queue Information of a Specified VDN

Interface Description

The interface is used to obtain the skill queue information of a specified VDN after an agent signs in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queuedevice/{agentid}/vdnskill/{vdnid}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
vdnid	int	Yes	Indicates the ID of the VDN to be queried. The value ranges from 1 to 512.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	array	Indicates the return result of a successful query, that is, skill queue information. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
name	string	Indicates the name of a skill.
id	int	Indicates the ID of a skill.
mediatype	int	Media Types
serviceType	int	Indicates the ID of a service type.
realFlag	int	Indicates whether it is in a real queue. 1: real queue 0: virtual queue

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/queuedevice/1010/vdnskill/1 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>

Example Type	Reference Format
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"name":"voice","id":1,"mediatype":5,"serviceType":1,"realFlag":1}, {"name":"callback","id":2,"mediatype":4,"serviceType":1,"realFlag":1}, {"name":"wechat","id":3,"mediatype":1,"serviceType":1,"realFlag":1}, {"name":"email","id":4,"mediatype":6,"serviceType":3,"realFlag":1}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 600-002

Parent topic: [Queue Device: queuedevice](#)

Obtaining the Skill Queue Information of the Home VDN of an Agent

Interface Description

The interface is used to obtain the skill queue information of the home VDN of an agent that has logged in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queuedevice/{agentid}/agentvdnskill
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	array	Indicates the return result of a successful query, that is, skill queue information. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
name	string	Indicates the name of a skill.
id	int	Indicates the ID of a skill.
mediatype	int	Media Types
serviceType	int	Indicates the ID of a service type.
realFlag	int	Indicates whether it is in a real queue. 1 : real queue 0 : virtual queue

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/queuedevice/1010/agentvdnskill HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"name":"voice","id":1,"mediatype":5,"serviceType":1,"realFlag":1}, {"name":"callback","id":2,"mediatype":4,"serviceType":1,"realFlag":1},</pre>

Example Type	Reference Format
	<pre>{ "name": "wechat", "id": 3, "mediatype": 1, "serviceType": 1, "realFlag": 1 }, { "name": "email", "id": 4, "mediatype": 6, "serviceType": 3, "realFlag": 1 }}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 600-005

Parent topic: [Queue Device: queuedevice](#)

Obtaining the Number of Users in a Specified Skill Queue

Interface Description

This interface is used to query the number of users in a specified skill queue of the current agent that has logged in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queuedevice/{agentid}/skillwaitnum/{skillid}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
skillid	int	Yes	Indicates the ID of the skill queue to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	int	Indicates the number of users in a skill queue returned after a successful query.

Interface Example

Example Type	Reference Format
Example of a request packet	GET /agentgateway/resource/queuedevice/1010/waitnum HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 { "message": "", "retcode": "0", "result": 0 }

Triggered Event

- None

Error Code

- 100-006

Parent topic: [Queue Device: queuedevice](#)

Querying the Statistics About a Set of Skill Queues

Interface Description

This interface is used to query the statistics about a set of skill queues after an agent logs in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queuedevice/{agentid}/queryacdstat
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
skills	List	Yes	Indicates a list of skill queue IDs. The array contains a maximum of 100 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	array	Indicates the return result of a successful query, that is, skill queue statistics. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
pilotNbr	string	Indicates the pilot number (access code) of an ACD group.
deviceNo	int	Indicates the ID of a skill queue.
queueSize	int	Indicates the number of calls that are currently waiting in the skill queue.
queueTime	long	Indicates the longest waiting time (sec) among all queuing calls.
loadFactor	int	This parameter is not used.
estWaitTime	long	This parameter is not used.
loggedOnAgents	int	Indicates the number of agents who have registered with the skill queue.
availAgents	int	Indicates the number of agents available in the skill queue.
transferFlg	int	Indicates the transfer flag. 0 : release; 2 : transfer.
transferDeviceType	int	Indicates the device type. See Device Types .
transferDeviceNo	int	Indicates the device number.

Parameter	Data Type	Description
skillDescrip	string	Indicates the skill description.
resourceIdleRate	int	This parameter is not used.
serviceLevel	int	This parameter is not used.
oldCallIdEx	object	Indicates the call ID information object with the maximum waiting duration. For the parameter description of oldCallIdEx , see Table 4 .
maxQueueSize	int	Indicates the maximum number of calls that can wait in the queue.

Table 4 Parameter description of oldCallIdEx

Parameter	Data Type	Description
dateTime	Date	Indicates the call access time.
dsn	int	Indicates the number of a task to which a call accesses.
server	int	Indicates the unique ID of a server.
handle	int	Indicates the number of times that a call accesses a task.


NOTE

The method for converting oldCallIdEx to callId is as follows:

```

StringBuilder buffer = new StringBuilder(24);
buffer.append(dateTime);
buffer.append('-');
long identify = ((long) server << 24) + ((long) handle << 16) + dsn;
buffer.append(identify);

```

Interface Example

Example Type	Reference Format
Example of a request packet	<pre> POST /agentgateway/resource/queuedevice/1010/queryacdstat HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"skills": [1, 10]} </pre>
Example of a response packet	<pre> HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0", "result": [{"pilotNbr": "", "deviceNo": 1, "queueSize": 0, "queueTime": 0, "loadFactor": 65535, "estWaitTime": 0, "loggedOnAgents": 1, "availAgents": 1, "transferFlg": 0, "transferDeviceType": 255, "transferDeviceNo": 65535, "skillDescrip": "Text chat_madeqiang", "resourceIdleRate": 100, "serviceLevel": 100, "oldCallIdEx": {"dateTime": 4294967295000, "dsn": 65535, "server": 255, "handle": 255}, "maxQueueSize": 100}, {"pilotNbr": "1009", "deviceNo": 10, "queueSize": 0, "queueTime": 0, "loadFactor": 65535, "estWaitTime": 0, "loggedOnAgents": 2, "availAgents": 2, "transferFlg": 0, "transferDeviceType": 255, "transferDeviceNo": 65535, "skillDescrip": "Text chat_jinsitao", "resourceIdleRate": 100, "serviceLevel": 100, "oldCallIdEx": {"dateTime": 4294967295000, "dsn": 65535, "server": 255, "handle": 255}, "maxQueueSize": 100}]} </pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Queue Device: queuedevice](#)

Querying the Statistics About the Next Set of Skill Queues of the Home VDN of an Agent

Interface Description

This interface is used to query the statistics about the next set of skill queues of the home VDN that an agent has logged in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queuedevice/{agentid}/queryskillstat
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
skills	List	Yes	Indicates a list of skill queue IDs. The array contains a maximum of 100 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the return result of a successful query, that is, skill queue statistics. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
connectedCallNumIn20	long	Indicates the number of calls that are connected within 20s (internal time interval of the CTI).
allCallNum	long	Indicates the number of calls within 5 minutes (internal time interval of the CTI).
totalCallNums	long	Indicates the total number of calls that are processed and being processed within 5 minutes (internal time interval of the CTI)
processingCallNums	long	Indicates the number of calls that are being processed.
maxCallWaitTimes	long	Indicates the longest call waiting time in the last five minutes (internal time interval of the CTI).
callWaitNums	long	Indicates the number of queuing calls (or waiting calls).
evenCallTime	long	Indicates the average call duration in the last five minutes (internal time interval of the CTI).
evenWaitTime	long	Indicates the average call waiting time in the last five minutes (internal time interval of the CTI).
agentLoginNums	long	Indicates the number of agents that have logged in.

Parameter	Data Type	Description
agentTalkingNums	long	Indicates the number of talking agents.
agentIdleNums	long	Indicates the number of idle agents.
agentAvailableNums	long	Indicates the number of agents who are available. If an agent can talk with multiple call users, the value of this parameter may be different from the number of idle agents.
agentSetBusyNums	long	Indicates the number of agents in the busy state.
agentRestNums	long	Indicates the number of resting agents.
agentMaxIdleTime	long	Indicates the longest idle duration among all agents in the last five minutes (internal time interval of the CTI).
agentWorkNums	long	Indicates the number of agents in the work state
agentStudyNums	long	Reserved.
agentOccupyNums	long	Reserved.
agentPreOccupyNums	long	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/queuedevice/1010/querieskillstat HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"skills":[1,10]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"connectedCallNumIn20": 0,"allCallNum": 0,"totalCallNums": 0,"processingCallNums": 1,"maxCallWaitTimes": 0,"callWaitNums": 0,"evenCallTime": 0,"evenWaitTime": 0,"agentLoginNums": 2,"agentTalkingNums": 1,"agentIdleNums": 1,"agentAvailableNums": 2,"agentSetBusyNums": 0,"agentRestNums": 0,"agentMaxIdleTime": 10045,"agentWorkNums": 0,"agentStudyNums": 0,"agentOccupyNums": 0,"agentPreOccupyNums": 0}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Queue Device: queuedevice](#)

Querying the Device Status

Interface Description

This interface is used by an agent that has logged in to query information about the device status.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queuedevice/{agentid}/querydevicestatus?deviceType={deviceType}&deviceNo={deviceNo}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
deviceType	int	Yes	Indicates the device type (1: queue; 2: agent; 3: IVR).
deviceNo	int	Yes	Indicates the device ID.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
deviceType	int	Indicates the device type (1: queue; 2: agent; 3: IVR).
deviceNo	int	Indicates the device ID.
pilotNo	string	Indicates the pilot number (access code).
transferType	int	Reserved.
tDeviceType	int	Indicates the type of the target device (1: queue; 2: agent; 3: IVR).
tDeviceNo	int	Indicates the ID of the target device.
callNum	int	Indicates the number of calls in a queue or the number of ongoing calls. When an agent queries a skill queue, the number of calls in the skill queue is returned. When an agent queries the calls of the agent, the number of ongoing and queuing calls is returned. When an agent queries the calls of the IVR, the number of ongoing calls of the IVR is returned.
callIds	array	Indicates the array of CallId .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/queuedevice/1010/querydevicestatus?deviceType=1&deviceNo=2 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"deviceType":1,"deviceNo":1,"pilotNo":"60015","transferType":0,"tDeviceType":255,"tDeviceNo":65535,"callNum":2,"callIds": ["1476188727-102","1476188728-103"]}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Queue Device: queuedevice](#)

Querying the Sub-media Type of a Skill Queue

Interface Description

This interface is used by an agent that has logged in to query the sub-media type of a textchat skill queue.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queuedevice/{agentid}/querysubmediatype?skillId={skillId}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
skillId	int	Yes	Indicates the ID of a skill queue.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
subMediaType	int	Indicates the sub media type.
subMediaTypeDescribe	string	Indicates the description of a sub-media type.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/queuedevice/1010/querysubmediatype?skillId=5 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"subMediaType":3,"subMediaTypeDescribe":"message"}}</pre>

Triggered Event

- None

Error Code

- 100-006

- 100-007

Parent topic: [Queue Device: queuedevice](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Adding Queue Monitoring

Interface Description

This interface is used to add queue monitoring based on the queue ID after an agent logs in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queuedevice/{agentid}/addqueuedevicemonitor?skillId={skillId}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
skillId	int	Yes	Indicates the ID of a skill queue.
Request Header			
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/queuedevice/{agentid}/addqueuedevicemonitor?skillId={skillId} HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 103-016
- 103-026
- 103-027
- 103-028

Parent topic: [Queue Device: queuedevice](#)

Stopping Queue Monitoring

Interface Description

This interface is used to stop queue monitoring based on the queue ID after an agent logs in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queuedevice/{agentid}/delqueuedevicemonitor?skillId={skillId}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
skillId	string	No	Indicates the ID of a skill queue. (If this parameter is not transferred, all queue monitoring tasks of the agent are removed.)
Request Header			
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/queuedevice/103/delqueuedevicemonitor HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 103-016
- 103-026
- 103-027

Parent topic: [Queue Device: queuedevice](#)

Agent Group: agentgroup

[Querying Information About All Agent Groups of the Home VDN](#)
[Querying Group Information About a Specified Agent](#)
[Querying Information About All Online Agents of the Home VDN](#)
[Querying Agent Information About the Group by A Supervisor](#)
[Querying Agent Information About the Group](#)
[Querying Detailed Information About A Specified Agent](#)
[Querying Whether an Agent Is An Administrator](#)
[Querying Whether an Agent Is an Inspection Supervisor](#)
[Querying Whether an Agent Is A Report Administrator](#)
[Querying Whether an Agent Is Authorized with Co-Group Pickup Permission](#)
[Querying Whether an Agent Is a Supervisor](#)
[Querying Whether an Agent Is an Inspector](#)
[Querying Whether an Agent Is Authorized with Outbound Permission](#)
[Querying Whether an Agent Is Authorized with Internal Call Permission](#)
[Querying State Information About All Agents of the Home VDN](#)
[Querying Information About Idle Agents](#)
[Querying All Resting Reason Codes of the Home VDN](#)
[Querying Agent Information About a Specified State](#)
[Querying State Information About Agents That Have Logged In to the Platform](#)
[Querying Information About Agents in Text Chat](#)
[Querying Agent Information About a Configured Skill Queue](#)
[Querying Information About Agents That Have Signed In to a Skill Queue](#)
[Querying Phone Numbers of Agents That Have Logged In to the Home VDN](#)
[Querying WAS Configuration Names of All Agents of the Home VDN](#)
[Querying the Work ID List of a Configured Skill Queue](#)
[Querying Agent Resting Information](#)
[Querying the State and Skills of a Specified Agent Before Logging In](#)
[Querying Information About Specified Agents in Batches](#)
[Performing a Fuzzy Query of Online Agents by Using a Keyword](#)
[Querying the Work ID of an Agent Based on a Phone Number](#)
[Batch Querying IP addresses of Agents](#)
[Querying the Work ID Using the Third-Party Account](#)
[Checking Whether an Agent Has the Permission to Download Files Based on the Agent ID](#)

Parent topic: [Interfaces](#)

Querying Information About All Agent Groups of the Home VDN

Interface Description

This interface is used to query the information about all agent groups of the home VDN of the agent that has logged in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/grouponvdm
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, an information list of agent groups. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
name	string	Indicates the name of an agent group.
id	int	Indicates the ID of an agent group.
monitorno	int	Indicates the work ID of a supervisor.
monitorname	string	Indicates the name of a supervisor.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/grouponvdm HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"id":1,"name":"group3","monitorno":109,"monitorname":"109"}, {"id":2,"name":"group5","monitorno":111,"monitorname":"111"}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying Group Information About a Specified Agent

Interface Description

This interface is used by an agent that has logged in to query the group information about a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/groupbyagent/{workno}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of the agent that has logged in.
workno	int	Yes	Indicates the work ID of the queried agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Indicates the return result of a successful query, that is, the information about a group. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
name	string	Indicates the name of an agent group.
id	int	Indicates the ID of an agent group.
monitorno	int	Indicates the work ID of a supervisor.
monitorname	string	Indicates the name of a supervisor.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/groupbyagent/111 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"id":2,"name":"group5","monitorno":111,"monitorname":"111"}}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 300-003
- 300-004

Parent topic: [Agent Group: agentgroup](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying Information About All Online Agents of the Home VDN

Interface Description

This interface is used to query the information about all online agents of the home VDN that the agent that has logged in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/onlineagentonvdn
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, an information list of agents. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
workno	string	Indicates the work ID of an agent.
name	string	Indicates the name of an agent.
status	int	Indicates the state of an agent. See Table 1 .
ctiStatus	int	Indicates the platform state of an agent. See Table 2 .
groupid	int	Indicates the ID of an agent group.
groupname	string	Indicates the name of an agent group.
mediatype	string	Reserved.
vdnid	int	Indicates the ID of the home VDN.
phonenum	string	Indicates the phone number of an agent.
currentstatetime	long	Indicates the duration of the current status, in seconds.
logindate	long	Indicates the login time (timestamp, in milliseconds).
inMultimediaConf	int	Indicates whether an agent is in a multimedia conference. • 0: no • 1: yes

Parameter	Data Type	Description
currentStateReason	int	Indicates the reason code of the current status. You can customize the rest reason code or busy reason code.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/onlineagentonvndn HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": [{"workno":"153","name":"153","status":"4","ctiStatus":"1","groupid":3,"groupname":"group_test","mediatype":"TTT","vdnid":1, "phonenumber":"70002","currentstatetime":137,"logindate":1473402213000,"inMultimediaConf":1,"currentStateReason":0}, {"workno":"156","name":"156","status":"4","ctiStatus":"1","groupid":3,"groupname":"group_test","mediatype":"TTT", "vdnid":1,"phonenumber":"70001","currentstatetime":11465,"logindate":1473390884000,"inMultimediaConf":0,"currentStateReason":0}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying Agent Information About the Group by A Supervisor

Interface Description

The interface is used by a supervisor that has logged in to query information about all the agents of the agent group.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent that has logged in is a supervisor.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/agentongroup
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, an information list of agents. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
workno	string	Indicates the work ID of an agent.
name	string	Indicates the name of an agent.
status	int	Indicates the state of an agent. See Table 1 .
ctiStatus	int	Indicates the platform state of an agent. See Table 2 .
groupid	int	Indicates the ID of an agent group.
groupname	string	Indicates the name of an agent group.
skilllist	array	Indicates the array of skill queues. See Table 4 .
mediatype	string	Reserved.
vdnid	int	Indicates the ID of the home VDN.
phonenumber	String	Indicates a phone number.
currentstatetime	long	Indicates the duration of the current status, in seconds.
logindate	long	Indicates the login time (timestamp, in milliseconds).

Parameter	Data Type	Description
inMultimediaConf	int	Indicates whether an agent is in a multimedia conference. 0: no 1: yes
currentStateReason	int	Indicates the reason code of the current status. You can customize the rest reason code or busy reason code.

Table 4 Parameter description of skilllist

Parameter	Data Type	Description
name	string	Indicates the name of a skill.
id	int	Indicates the ID of a skill.
mediatype	int	Indicates the media type.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/agentongroup HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": [{"workno":"151","name":"","skilllist":[],"status":"2","ctiStatus":"0","groupid":3,"groupname":"group_test", "mediatype":"FFF","vdnid":1,"phonenummer":"","currentstatetime":62103,"logindate":4294967295000, "inMultimediaConf":0,"currentStateReason":0},{workno":"153","name":"153","skilllist":[],"status":"4","ctiStatus":"1", "groupid":3,"groupname":"group_test","mediatype":"TTT","vdnid":1,"phonenummer":"70002", "currentstatetime":401,"logindate":1473402213000,"inMultimediaConf":1,"currentStateReason":0}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 300-001
- 300-002

Parent topic: [Agent Group: agentgroup](#)

Querying Agent Information About the Group

Interface Description

The interface is used by an inspector that has logged in to query information about all the agents of the agent group with a specified agent group ID.

NOTE

The interface needs to query the skills of each agent, so there is a performance bottleneck. If there are more than 100 agents, do not use the interface.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - When **groupid** does not exist and the current agent is a supervisor, the information about all members of the group to which the supervisor belongs is returned.

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/agentongroupex?groupid={groupid}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
groupid	int	Yes	Indicates the ID of an agent group.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, an information list of agents. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
workno	string	Indicates the work ID of an agent.
name	string	Indicates the name of an agent.
status	int	Indicates the state of an agent. See Table 1 .
ctiStatus	int	Indicates the platform state of an agent. See Table 2 .
groupid	int	Indicates the ID of an agent group.
groupname	string	Indicates the name of an agent group.
skilllist	list	Indicates the skill list of an agent. For the parameter description of skilllist , see Table 4 .
mediatype	string	Reserved.
vdnid	int	Indicates the ID of the home VDN.

Parameter	Data Type	Description
phonenumber	string	Indicates the phone number of an agent.
currentstatetime	long	Indicates the duration of the current status, in seconds.
logindate	long	Indicates the login time (timestamp, in milliseconds).
inMultimediaConf	int	Indicates whether an agent is in a multimedia conference. 0: no 1: yes
currentStateReason	int	Indicates the reason code of the current status. You can customize the rest reason code or busy reason code.

Table 4 Parameter description of skilllist

Parameter	Data Type	Description
name	string	Indicates the name of a skill.
id	int	Indicates the ID of a skill.
mediatype	int	Media Types

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/qagentongroupex?groupid=2 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": [{"workno":"151","name":"","status":"2","ctiStatus":"0","groupid":3,"groupname":"group_test","skilllist":[, "mediatype":"FFF","vdnid":1,"phonenumber":"","currentstatetime":62226,"logindate":4294967295000,, "inMultimediaConf":0, "currentStateReason":0}, {"workno":"153","name":"153","status":"4","ctiStatus":"1","groupid":3,"groupname":"group_test", "skilllist":[{"name":"textchat","id":11,"mediatype":1}, {"name":"voice","id":9,"mediatype":5}], "mediatype":"TTT","vdnid":1, "phonenumber":"70002","currentstatetime":524,"logindate":1473402213000,, "inMultimediaConf":1,"currentStateReason":0}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 300-001
- 300-002

Parent topic: [Agent Group: agentgroup](#)

Querying Detailed Information About A Specified Agent

Interface Description

This interface is used by an agent that has logged in to query the detailed information about a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/agentbyworkno/{workno}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of the agent that has logged in.
workno	int	Yes	Indicates the work ID of the queried agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Indicates the return result of a successful query, that is, the agent information. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
workno	string	Indicates the work ID of an agent.
name	string	Indicates the name of an agent.
status	int	Indicates the state of an agent. See Table 1 .
citStatus	int	Indicates the platform state of an agent. See Table 2 .
groupid	int	Indicates the ID of an agent group.
groupname	string	Indicates the name of an agent group.
skilllist	list	Indicates the skill list of an agent. For the parameter description of skilllist , see Table 4 .
mediatype	string	Reserved.
vdnid	int	Indicates the ID of the home VDN.
phonenumber	string	Indicates the phone number of an agent.
currentstatetime	long	Indicates the duration of the current status, in seconds.
logindate	long	Indicates the login time (timestamp, in milliseconds).

Parameter	Data Type	Description
inMultimediaConf	int	Indicates whether an agent is in a multimedia conference. 0: no 1: yes
currentStateReason	int	Indicates the reason code of the current status. You can customize the rest reason code or busy reason code.
callids	list	This parameter is not used.
thirdAccount	string	Indicates a third-party account, which matches the agent work ID.

Table 4 Parameter description of skilllist

Parameter	Data Type	Description
name	string	Indicates the name of a skill.
id	int	Indicates the ID of a skill.
mediatype	int	Media Types

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/agentbyworkno/20011 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{ "workno":"20011","name":"20011","status":"4","ctiStatus":"1","groupid":1,"groupname":"jst", "skilllist":[{"name":"clicktodial_jst","id":10,"mediatype":2}, {"name":"callback","id":2,"mediatype":4}, {"name":"webchat","id":3,"mediatype":1}, {"name":"email","id":4,"mediatype":6}, {"name":"voice_hym","id":5,"mediatype":5}, {"name":"voice","id":6,"mediatype":5}, {"name":"webchat_jst","id":9,"mediatype":1}}, "mediatype":"TTT","vdnid":6, "phonenumber":"70942","currentstatetime":1210,"logindate":1501125758000, "callids":[],"inMultimediaConf":0,"currentStateReason":0,"thirdAccount": "FENG"}}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying Whether an Agent Is An Administrator

Interface Description

This interface is used to judge whether the agent that has logged in is an administrator by the agent ID.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/issystem
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	boolean	Indicates the return result, true or false , of a successful query. • true: The agent is an administrator. • false: The agent is not an administrator.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/issystem HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": true}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying Whether an Agent Is an Inspection Supervisor

Interface Description

This interface is used to judge whether the agent that has logged in is an inspection supervisor by the agent ID.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/isspymonitor
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	boolean	Indicates the return result, true or false , of a successful query. • true: The agent is an inspector supervisor. • false: The agent is not an inspector supervisor.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/isspymonitor HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": true}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying Whether an Agent Is A Report Administrator

Interface Description

This interface is used to judge whether the agent that has logged in is a report administrator by the agent ID.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/isreportmanager
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	boolean	Indicates the return result, true or false , of a successful query. • true: The agent is a report administrator. • false: The agent is not a report administrator.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/isreportmanager HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": false}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying Whether an Agent Is Authorized with Co-Group Pickup Permission

Interface Description

This interface is used to judge whether the agent that has logged in is authorized with co-group pickup permission by the agent ID.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/ispickup
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	boolean	Indicates the return result, true or false , of a successful query. • true: The agent has the co-group pickup permission. • false: The agent has no co-group pickup permission.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/ispickup HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": false}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying Whether an Agent Is a Supervisor

Interface Description

This interface is used to judge whether the agent that has logged in is a supervisor by the agent ID.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/ismonitor
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	boolean	Indicates the return result, true or false , of a successful query. • true: The agent is a supervisor. • false: The agent is not a supervisor.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/ismonitor HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": false}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying Whether an Agent Is an Inspector

Interface Description

This interface is used to judge whether the agent that has logged in is an inspector by the agent ID.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/iscensor
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	boolean	Indicates the return result, true or false , of a successful query. • true: The agent is an inspector. • false: The agent is not an inspector.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/iscensor HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": false}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying Whether an Agent Is Authorized with Outbound Permission

Interface Description

This interface is used to judge whether the agent that has logged in is authorized with outbound permission by the agent ID.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/iscallout
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	boolean	Indicates the return result, true or false , of a successful query. • true: The agent has the outbound permission. • false: The agent has no the outbound permission.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/iscallout HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": true}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying Whether an Agent Is Authorized with Internal Call Permission

Interface Description

This interface is used to judge whether the agent that has logged in is authorized with internal-call permission by the agent ID.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/isinnercall
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	boolean	Indicates the return result, true or false , of a successful query. • true: The agent has the internal call permission. • false: The agent has no internal call permission.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/isinnercall HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": true}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying State Information About All Agents of the Home VDN

Interface Description

This interface is used by an agent that has logged in to query the state information about all the agents of the home VDN.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/allagentstatus
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, a list of current agent state. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
workno	string	Indicates the work ID of an agent.
name	string	Indicates the name of an agent.
status	string	Indicates the current state of an agent. See Table 1
ctiStatus	string	Indicates the platform state of an agent. See Table 2 .

Interface Example

Example Type	Reference Format
Example of a request packet	GET /agentgateway/resource/agentgroup/1010/allagentstatus HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{ "workno": "118", "status": "2", "name": "118", "ctiStatus": "0"}, { "workno": "153", "status": "7", "name": "153", "ctiStatus": "0"}] }

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying Information About Idle Agents

Interface Description

This interface is by an agent that has logged in to query information about all the idle agents on the platform.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/idleagent
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
workno	string	Indicates the work ID of an agent.
name	string	Indicates the name of an agent.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/idleagent HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"workno":"156","name":"156"}]}</pre>

Triggered Event

- None

Error Code

- 100-006

- 100-007

Parent topic: [Agent Group: agentgroup](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying All Resting Reason Codes of the Home VDN

Interface Description

This interface is used by an agent that has logged in to obtain all the resting reason codes of the home VDN.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/restreason
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, an information list of resting reason codes. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
restReasonId	int	Indicates the code of a resting reason.
restReason	string	Indicates the description of the resting reason.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/restreason HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"restReasonId": 100,"restReason": "Unwell"]}</pre>

Triggered Event

- None

Error Code

- 100-006

- 100-007

Parent topic: [Agent Group: agentgroup](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying Agent Information About a Specified State

Interface Description

This interface is used by an agent that has logged in to query the agent information about a specified state.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/agentlistbystatus?status={status}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
status	string	Yes	Indicates the agent status to be queried. Multiple status values are separated by commas (.). The maximum length is 20 characters. For details about the agent status, see Table 1 .
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, a list of agent states. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
workno	string	Indicates the work ID of an agent.
name	string	Indicates the name of an agent.
status	string	Indicates the current status of an agent. For details, see Table 1 .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/agentlistbystatus?status=1,2 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"workno":"153","status":"7","name":"153"}, {"workno":"148","status":"7","name":"148"}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying State Information About Agents That Have Logged In to the Platform

Interface Description

This interface is used by an agent that has logged in to query state information about agents that have logged in to the platform.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/alllocalagentstatus
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, a list of agent states. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
workno	string	Indicates the work ID of an agent.
name	string	Indicates the name of an agent.
status	string	Indicates the current status of an agent. For details, see Table 1 .

Interface Example

Example Type	Reference Format
Example of a request packet	GET /agentgateway/resource/agentgroup/1010/alllocalagentstatus HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{ "workno": "156", "status": "4", "name": "156" }, { "workno": "153", "status": "7", "name": "153" }] }

Triggered Event

- None

Error Code

- None

Parent topic: [Agent Group: agentgroup](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying Information About Agents in Text Chat

Interface Description

This interface is used by an agent that has logged in to obtain information about agents in text chats.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/allchatagents
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, a list of agents in text chat. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
workno	string	Indicates the work ID of an agent.
name	string	Indicates the name of an agent.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/allchatagents HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"workno":"153","name":"153"}]}</pre>

Triggered Event

- None

Error Code

- 100-006

- 300-002

Parent topic: [Agent Group: agentgroup](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying Agent Information About a Configured Skill Queue

Interface Description

This interface is used by an agent that has logged in to query detailed agent information about a skill queue by the configured skill queue ID.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/agentbyconfigedskill/{skillid}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
skillid	int	Yes	Indicates the ID of the skill queue to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, a list of agents. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
workno	string	Indicates the work ID of an agent.
name	string	Indicates the name of an agent.
status	int	Indicates the state of an agent. See Table 1 .
ctiStatus	int	Indicates the platform state of an agent. See Table 2 .
groupid	int	Indicates the ID of an agent group.
mediatype	string	Reserved.
vdnid	int	Indicates the ID of the home VDN.
phonenum	string	Indicates the phone number of an agent.
currentstatetime	long	Indicates the duration of the current status, in seconds.
logindate	long	Indicates the login time (timestamp, in milliseconds).
inMultimediaConf	int	Indicates whether an agent is in a multimedia conference. 0 : no 1 : yes

Parameter	Data Type	Description
currentStateReason	int	Indicates the reason code of the current status. You can customize the rest reason code or busy reason code.

Interface Example

Example Type	Reference Format
Example of a request packet	<code>GET /agentgateway/resource/agentgroup/1010/agentbyconfigedskill/5 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</code>
Example of a response packet	<code>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{ "workno": "153", "name": "153", "status": "7", "ctiStatus": "5", "groupid": "3", "mediatype": "TTT", "vdnid": "1", "phonenumber": "70002", "currentstatetime": "103", "logindate": "1473402213000", "inMultimediaConf": "1", "currentStateReason": "0" }, { "workno": "160", "name": "160", "status": "2", "ctiStatus": "0", "groupid": "0", "mediatype": "FFF", "vdnid": "1", "phonenumber": "", "currentstatetime": "154756", "logindate": "4294967295000", "inMultimediaConf": "0", "currentStateReason": "0" }] }</code>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying Information About Agents That Have Signed In to a Skill Queue

Interface Description

This interface is used by an agent that has logged in to query the detailed information about agents that have signed in to a skill queue by skill queue ID.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/agentbyskill/{skillid}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
skillid	int	Yes	Indicates the ID of the skill queue to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, a list of agents. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
workno	string	Indicates the work ID of an agent.
name	string	Indicates the name of an agent.
status	int	Indicates the state of an agent. See Table 1 .
ctiStatus	int	Indicates the platform state of an agent. See Table 2 .
groupid	int	Indicates the ID of an agent group.
groupname	string	This parameter is not used.
skilllist	list	This parameter is not used.
callids	list	This parameter is not used.
mediatype	string	Reserved.
vdnid	int	Indicates the ID of the home VDN.
phonenummer	string	Indicates the phone number of an agent.
currentstatetime	long	Indicates the duration of the current status, in seconds.

Parameter	Data Type	Description
logindate	long	Indicates the login time (timestamp, in milliseconds).
inMultimediaConf	int	Indicates whether an agent is in a multimedia conference. 0: no 1: yes
currentStateReason	int	Indicates the reason code of the current status. You can customize the rest reason code or busy reason code.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/agentbyskill/3 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": [{"workno":"20011","name":"20011","status":"4","ctiStatus":"1","groupid":1,"groupname":null, "skilllist":[],"mediatype":"TTT","vdnid":6,"phonenumber":"70942","currentstatetime":1376,"logindate":1501125758000, "callids":[],"inMultimediaConf":0,"currentStateReason":0}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 300-002

Parent topic: [Agent Group: agentgroup](#)

Querying Phone Numbers of Agents That Have Logged In to the Home VDN

Interface Description

This interface is used by an agent that has logged in to query the phone numbers of agents that have logged in to the home VDN of the agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/loggedinagentphoneonvdn
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the return result of a successful query, that is, the phone number of an agent that has logged in. Key: Work ID Value: Phone number

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/loggedinagentphoneonvdn HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"49999": "70084","291": "70083","161": "70085"}}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying WAS Configuration Names of All Agents of the Home VDN

Interface Description

This interface is used by an agent who has logged in to query the WAS configuration names of all agents in the same VDN.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/agentwasnameonvdn
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the found WAS configuration names of all agents. Key: work ID Value: agent name configured on the WAS

Interface Example

Example Type	Reference Format
Example of a request packet	GET /agentgateway/resource/agentgroup/1010/agentwasnameonvdn HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "102": "WAS configuration administrator-XXX", "103": "WAS configuration administrator-XXX" } }

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying the Work ID List of a Configured Skill Queue

Interface Description

This interface is used by an agent that has logged in to query the work ID list of agents configured with the same skill queue of the agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/agentidsbyskill/{skillid}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
skillid	int	Yes	Indicates the ID of the skill queue to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, the work ID list of agents configured with the skill ID.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/agentidsbyskill/5 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[106,291,46666,49999]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying Agent Resting Information

Interface Description

This interface is used by an agent that has logged in to query the agent resting information in batches by agent ID.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/agentrestinfo
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Indicates the return result of a successful query, that is, the details of the resting agents on the VDN. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
agentsrestdetails	list	Indicates a detailed list of resting agents on the VDN. For the parameter description of agentsrestdetails , see Table 4 .
allowrestnum	int	Indicates the number of agents that are allowed to rest.
onrestnum	int	Indicates the number of agents that are resting.
waitrestnum	int	Indicates the number of agents that are waiting for a rest.

Table 4 Parameter description of agentsrestdetails

Parameter	Data Type	Description
agentname	string	Indicates the name of an agent.
workno	int	Indicates the work ID of an agent.
cantrestreason	int	Indicates the reason why an agent is not allowed to rest. This parameter is valid only for agents who are waiting to rest.
fullskillid	int	Indicates the ID of a skill queue whose agents are all busy when the rest time is reached.
begintime	long	Indicates the start time for rest (timestamp, in milliseconds).

Parameter	Data Type	Description
restduration	long	Indicates the rest duration (in seconds).

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/agentrestinfo HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"agentsrestdetails": [{"agentname": "291","workno": 291,"cantrestreason": 100,"fullskillid": 65535, "begintime": 1456212955000,"restduration": 600},{ "agentname": "", "workno": 49999,"cantrestreason": 4, "fullskillid": 10,"begintime": 1456212965000,"restduration": 600}], "allowrestnum": 1,"onrestnum": 0,"waitrestnum": 1}}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying the State and Skills of a Specified Agent Before Logging In

Interface Description

This interface is used by an agent that does not log in to query the state and skill information about a specified agent.

Usage Description

1. Prerequisites
 - None
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/queryagentstatusandskill
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the result returned after a successful query, that is, the state and skill queue of an agent. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
skills	list	Indicates the skill queue configured for an agent. For the parameter description of skills , see Table 4 .
status	int	Indicates the state of an agent. See Table 1 .

Table 4 Parameter description of skills

Parameter	Data Type	Description
name	string	Indicates the name of a skill.
id	int	Indicates the ID of a skill.
mediatype	int	Media Types
serviceType	int	Indicates the ID of a service type.
realFlag	int	Indicates whether the queue is a real queue or virtual queue.
shortening	string	This parameter is not used.

Interface Example

Example Type	Reference Format
Example of a request packet	<code>GET /agentgateway/resource/agentgroup/1010/queryagentstatusandskill HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</code>
Example of a response packet	<code>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "skills": [{ "id": "10", "mediaType": "4", "serviceType": "6", "realFlag": "1", "name": "callback", "shortening": "" }, { "id": "11", "mediaType": "1", "serviceType": "5", "realFlag": "1", "name": "textchat", "shortening": "" }, { "id": "9", "mediaType": "5", "serviceType": "6", "realFlag": "1", "name": "voice", "shortening": "" }] }, "status": "1" }</code>

Triggered Event

- None

Error Code

- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying Information About Specified Agents in Batches

Interface Description

This interface is used by an agent that has logged in to query information about specified agents in batches. The agent information obtained does not include skill information.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/agentinfofonoskills
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
agentlist	list	Yes	Indicates the list of agent work IDs. The array contains a maximum of 500 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, an information list of specified agents. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
workno	string	Indicates the work ID of an agent.
name	string	Indicates the name of an agent.
status	int	Indicates the state of an agent. See Table 2 .
ctiStatus	int	Indicates the platform state of an agent. See Table 2 .
groupid	int	Indicates the ID of an agent group.
groupname	string	This parameter is not used.
skilllist	list	This parameter is not used.
mediatype	string	This parameter is not used.
phonenum	string	This parameter is not used.
vdnid	int	Indicates the ID of the home VDN.
currentstatetime	long	Indicates the duration of the current status, in seconds.

Parameter	Data Type	Description
logindate	long	Indicates the time when the agent signs in to the system.
callids	list	Indicates the list of call IDs. A maximum number of two call IDs are returned for an agent. 4294967295-XXX indicates no call.
inMultimediaConf	int	Indicates whether an agent is in a multimedia conference. 0 : no 1 : yes
currentStateReason	int	Indicates the reason code of the current status. You can customize the rest reason code or busy reason code. The value 65535 indicates that the no reason code is set.)

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/agentgroup/1010/agentinfonoskills HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"agentlist": [20011, 20012]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0", "result": [{"workno": "20011", "name": "20011", "status": "5", "ctiStatus": "5", "groupid": 1, "groupname": null, "skilllist": [], "mediatype": "FFF", "vdnid": 6, "phonenum": null, "currentstatetime": 100, "logindate": 1501125758000, "callids": [{"1501127920-0", "1501127996-2"}], "inMultimediaConf": 0, "currentStateReason": 0}, {"workno": "20012", "name": "20012", "status": "0", "ctiStatus": "0", "groupid": 1, "groupname": null, "skilllist": [], "mediatype": "FFF", "vdnid": 6, "phonenum": null, "currentstatetime": 2860, "logindate": 4294967295000, "callids": [{"4294967295-4294967295", "4294967295-4294967295"}], "inMultimediaConf": 0, "currentStateReason": 65535}]}</pre>

Triggered Event

- None

Error Code

- 100-001
- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Performing a Fuzzy Query of Online Agents by Using a Keyword

Interface Description

After the agent has logged in, perform a fuzzy query of online agents by using a keyword such as a work ID or agent name.

NOTE

The interface needs to query the skills of each agent, so there is a performance bottleneck. If there are more than 100 agents, do not use the interface.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/onlineagentonvndnbykeyword/{keyword}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
keyword	int	Yes	Indicates the agent ID or agent name to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, a list of specified agents. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
workno	string	Indicates the work ID of an agent.
name	string	Indicates the name of an agent.
status	int	Indicates the state of an agent. See Table 1 .
ctiStatus	int	Indicates the platform state of an agent. See Table 2 .
groupid	int	Indicates the ID of an agent group.
groupname	string	Indicates the name of an agent group.
skilllist	list	Indicates the agent skill list. For the parameter description of skilllist , see Table 4 .
mediatype	string	Indicates the media type of the agent.
vdnid	int	Indicates the ID of the home VDN.

Parameter	Data Type	Description
phonenumber	string	Indicates the phone number of an agent.
currentstatetime	long	Indicates the duration of the current status, in seconds.
logindate	long	Indicates the login time (timestamp, in milliseconds).
inMultimediaConf	int	Indicates whether an agent is in a multimedia conference. 0 : no 1 : yes
currentStateReason	int	Indicates the reason about entering into the current state.

Table 4 Parameter description of skilllist

Parameter	Data Type	Description
name	string	Indicates the name of a skill.
id	int	Indicates the ID of a skill.
mediatype	int	Media Types

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/onlineagentonvndnbykeyword/10 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0", "result": [{"workno": "110", "name": "Agent", "status": "3", "ctiStatus": "7", "groupid": "0", "groupname": ""}, {"skilllist": [{"name": "Text Chat", "id": "2", "mediatype": "1"}, {"name": "Click to Dial", "id": "3", "mediatype": "2"}], "mediatype": "TYPE1", "vdnid": "1", "phonenumber": "70050", "currentstatetime": "50052", "logindate": "1462774621000", "inMultimediaConf": "0", "currentStateReason": "0"}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Querying the Work ID of an Agent Based on a Phone Number

Interface Description

This interface is used by an agent that has logged in to query the work ID based on a phone number.

Usage Description

1. Prerequisites
The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/queryworknobynumber?phoneNumber={phoneNumber}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
phoneNumber	string	Yes	Indicates the phone number. The value contains a maximum of 24 characters.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
agent	int	Indicates the work ID of an agent. If the work ID of the agent corresponding to the phone number does not exist, the value is set to -1.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/queryworknobynumber?phoneNumber=70020 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"agent":121}}</pre>

Triggered Event

- None

Error Code

- 000-002

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Batch Querying IP addresses of Agents

Interface Description

This interface is used by an agent that has logged in to batch query IP addresses of agents.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentgroup/{agentid}/queryagentip
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request body			
agentlist	array	Yes	Indicates the list of agent work IDs. The array contains a maximum of 500 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	array	For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
phones	array	Indicates the array of agent IP addresses. 255.255.255.255 indicates that the work ID of an agent does not exist or the agent has not logged in.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/agentgroup/1010/queryagentip HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000 {"agentlist": [20011, 20012]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0", "result": {"phones": ["127.0.0.1", "255.255.255.255"]}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying the Work ID Using the Third-Party Account

Interface Description

After logging in, an agent can query the work ID of another agent using the third-party account.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	https://ip:port/agentgateway/resource/agentgroup/{agentid}/worknobythirdaccount?thirdAccount={thirdAccount}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
thirdAccount	string	Yes	Indicates the third-party account, which is mandatory and cannot exceed 40 characters.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	For the parameter description of result , see Table 3 .

Table 3 Parameter description of **result**

Parameter	Data Type	Description
workno	int	Indicates the work ID of the target agent.
name	string	Indicates the user name of the target agent.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/worknobythirdaccount?thirdAccount=feng HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0", "result": {"workno": "109", "name": ""}}</pre>

Triggered Event

- None

Error Code

- 000-002

- 100-006
- 100-007

Parent topic: [Agent Group: agentgroup](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Checking Whether an Agent Has the Permission to Download Files Based on the Agent ID

Interface Description

This interface is used to check whether an agent has the permission to download files based on the agent ID.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	https://ip:port/agentgateway/resource/agentgroup/{agentid}/isdownloadrecord
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	string	0: The agent does not have the download permission. 1: The agent has the download permission.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentgroup/1010/isdownloadrecord HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":0}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 900-002

Parent topic: [Agent Group: agentgroup](#)

Call Data: calldata

[Call-Associated Data](#)

[Held Calls](#)

[Querying Call Information](#)

[Querying Call Information Before Answering a Call](#)

[Querying Call Information About the Home VDN](#)

[Querying Information About All Call IDs](#)

[Querying Call Information by Call ID](#)

[Querying Call IDs of a Specified Agent](#)

[Querying the Number of Current Calls of an Agent](#)

[Querying All Call Information of a Specified Agent](#)

[Querying Current Call Statistics Information About an Agent](#)

[Querying Information About Queuing Calls in a Specified Skill Queue](#)

[Querying Whether the Agent Is Processing or Is to Process a Call](#)

[Querying Information About Queuing Calls in a Specified IVR System](#)

[Querying Information About Queuing Calls in a Private Queue](#)

[Querying Phone Number Information About Parties Making Calls on a Specified Agent](#)

[Querying the Number of Calls in a Specified IVR System](#)

[Querying Whether an Agent Has the Permission to Release a Specified Call](#)

[Querying the Geographical Location Based on the Calling Number](#)

[Updating the Geographical Location Based on the Calling Number](#)

[Querying MSD Data by Call ID](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Call-Associated Data

[Configuring Call-Associated Data](#)

[Configuring Call-Associated Data \(Expanded\)](#)

[Configuring Call-Associated Data \(Bean Expansion Interface\)](#)

[Querying Call-Associated Data \(Bean Expansion Interface\)](#)

[Querying Call-Associated Data](#)

Parent topic: [Call Data: calldata](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Configuring Call-Associated Data

NOTE

The call-associated data of this interface is transmitted over URL packets, resulting in security risks. As a result, this interface is discarded since IPCC V200R001C60. An interface for setting the call-associated data (extended) is used to replace this interface. However, this interface is still valid actually to support sites that adopt earlier versions.

Interface Description

This interface is used by an agent that is in a conversation after signing in to configure call-associated data.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in a conversation.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}?calldata={calldata}&callid={callid}
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
calldata	string	Yes	Indicates the call-associated data (containing a maximum of 6000 bytes).
callid	long	Yes	Indicates the ID of a call.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/calldata/1010/?calldata=vip&callid=1501127996-2 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007
- 400-001

Parent topic: [Call-Associated Data](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Configuring Call-Associated Data (Expanded)

Interface Description

This interface is used by an agent that is in a conversation after signing in to configure call-associated data (expanded).

NOTE

This interface applies only to voice calls.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in a conversation.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/setcalldataex
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
callid	string	No	Indicates the ID of a call.
calldata	string	No	Indicates the call-associated data. The value contains a maximum of 16000 bytes.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/calldata/1010/setcalldataex HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000 {"callid": "1456229294-1191", "calldata": "1233"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007
- 400-001

Parent topic: [Call-Associated Data](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Configuring Call-Associated Data (Bean Expansion Interface)

Interface Description

This interface is used by an agent that is in conversation after signing in to configure call-associated data (bean expansion interface).

NOTE

This interface applies only to voice calls.

Usage Description

- Prerequisites
 - The agent has logged in.
 - The agent is in a conversation.
- Precautions

None
- Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/setcallbusinessdata
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
callId	string	Yes	Indicates the ID of a call.
callBusinessData	list	Yes	Indicates a list of call-associated data objects. For the parameter description of callBusinessData , see Table 2 . The array contains a maximum of 200 IDs.

Table 2 Parameter description of **callBusinessData**

Parameter	Data Type	Mandatory (Yes/No)	Description
key	string	Yes	Indicates the key of call-associated data.
value	string	Yes	Indicates the value of call-associated data.
isWriteBill	int	No	Indicates whether the key/value pair is saved to the database. (0 : no; 1 : yes; -1 : invalid). The default value is 0 .

Rules:

- The total number of keys/values does not exceed 200.
- The total number of archived keys/values does not exceed 10.
- The length of a key/value is smaller than 512 bytes.
- The overall length of archived keys/values is smaller than 1024 bytes.
- The overall length of keys is smaller than 2048 bytes.
- The overall length of keys/values is smaller than 10k bytes.
- A key starts with a letter, contains only letters, numbers, and underlines, and does not exceed 64 bytes.
- A value cannot contain **&}** or **&|**.

Response Message

Table 3 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		

Parameter	Data Type	Description
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/calldata/1010/setcallbusinessdata HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"callId":"1456229294-1191","callBusinessData":[{"key":"a1","value":"1123","isWriteBill":1}, {"key":"a2","value":"2222","isWriteBill":1}]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Call-Associated Data](#)

Querying Call-Associated Data (Bean Expansion Interface)

Interface Description

This interface is used by an agent that is in conversation after signing in to query call-associated data (bean expansion interface).

NOTE

This interface applies only to voice calls.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in a conversation.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/getcallbusinessdata
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
callId	string	Yes	Indicates the ID of a call.
callBusinessDataKey	list	Yes	Indicates a list of call-associated data keys.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates a list of call-associated data objects returned after a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callId	string	Indicates the ID of a call.
callBusinessData	list	Indicates a list of call-associated data objects. For the parameter description of callBusinessData , see Table 4 .

Table 4 Parameter description of callBusinessData

Parameter	Data Type	Description
key	string	Indicates the key of call-associated data.
value	string	Indicates the value of call-associated data.

Parameter	Data Type	Description
isWriteBill	int	Indicates whether the key/value pair is saved to the database. (0: no; 1: yes; -1: invalid).

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/calldata/1010/getcallbusinessdata HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"callId":"1456229294-1191","callBusinessDataKey":["a1","a2"]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"callId": "1456229294-1191","callBusinessData":{"key": "a1","value": "1123","isWriteBill": 1}, {"key": "a2","value": "2222","isWriteBill": 1}}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Call-Associated Data](#)

Querying Call-Associated Data

Interface Description

This interface is used by an agent that has logged in to query the call-associated data.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in a conversation.
2. Precautions
 - None
3. Use restrictions
 - Text chats are not supported.

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/appdata
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	string	Indicates the call-associated data returned after a successful query. No result is returned if the query fails.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/calldata/1010/appdata HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0", "result": "1234"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Call-Associated Data](#)

Held Calls

[Querying the List of Held Calls](#)

[Querying the List of Held Calls of a Specified Agent \(Expanded\)](#)

[Querying the Number of Held Calls of a Specified Agent](#)

Parent topic: [Call Data: calldata](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying the List of Held Calls

Interface Description

This interface is used by an agent that has logged in to query the list of held calls.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/holdlist
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Indicates the return result of a successful query, that is, a list of held calls. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callfeature	int	Indicates the type of a call. See Call Types .
callid	string	Indicates the ID of a call.
caller	int	Indicates the calling number.
called	int	Indicates the called number.
callskill	string	Indicates the description of a call skill.
callskillid	int	This parameter is not used.
orgcallednum	string	This parameter is not used.
calldata	string	This parameter is not used.
begintime	long	This parameter is not used.
endtime	long	This parameter is not used.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/holdlist HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":0,"result": [{"callfeature":7,"callid":"1501127996-2","caller":"10086","called":"70943","callskill":"voice","callskillid":0, "orgicallednum":"","calldata":null,"begintime":null,"endtime":null},{ "callfeature":7,"callid":"1501127920-0", "caller":"10086","called":"70941","callskill":"","callskillid":0,"orgicallednum":"","calldata":null, "begintime":null,"endtime":null}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 300-001
- 400-003

Parent topic: [Held Calls](#)

Querying the List of Held Calls of a Specified Agent (Expanded)

NOTE

This interface supports only the query of held call lists of agents that log in to the Agent Gateway server which the inspector signs in.

Interface Description

This interface is used by an inspector that has logged in to query the held call list of a specified agent (expanded).

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/holdlistex/{workno}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of the agent that has logged in.
workno	int	Yes	Indicates the work ID of the agent to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Indicates the return result of a successful query, that is, a list of held calls. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callfeature	int	Indicates the type of a call. See Call Types .
callid	string	Indicates the ID of a call.
caller	int	Indicates the calling number.
called	int	Indicates the called number.
callskill	string	Indicates the description of a call skill.
callskillid	int	This parameter is not used.
orgcallednum	string	This parameter is not used.
calldata	string	This parameter is not used.
begintime	long	This parameter is not used.

Parameter	Data Type	Description
endtime	long	This parameter is not used.

Interface Example

Example Type	Reference Format
Example of a request packet	<code>GET /agentgateway/resource/calldata/1010/holdlistex/10086 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</code>
Example of a response packet	<code>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{ "callfeature": "7", "callid": "1501127996-2", "caller": "10086", "called": "70943", "callskill": "voice", "callskillid": "0", "orgicallednum": "", "calldata": null, "begintime": null, "endtime": null, "callfeature": "7", "callid": "1501127920-0", "caller": "10086", "called": "70941", "callskill": "", "callskillid": "0", "orgicallednum": "", "calldata": null, "begintime": null, "endtime": null }] }</code>

Triggered Event

- None

Error Code

- 100-006
- 300-001
- 400-003

Parent topic: [Held Calls](#)

Querying the Number of Held Calls of a Specified Agent

Interface Description

This interface is used by an agent that has logged in to query the number of held calls of a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/agentholdnum/{workno}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
workno	int	Yes	Indicates the work ID of the agent to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Indicates the return result of a successful query, that is, the number of held calls of an agent.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/agentholdnum/10086 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": 1}</pre>

Triggered Event

- None

Error Code

- 100-006

Parent topic: [Held Calls](#)

Querying Call Information

Interface Description

This interface is used by an agent that has logged in to query the call information.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/callinfo?isNoContainLastCall={isNoContainLastCall}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
isNoContainLastCall	boolean	Yes	Indicates that when the current agent has no calls, whether to query the last call information
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Indicates the call information returned after a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callfeature	int	Indicates the type of a call. See Call Types .
callid	string	Indicates the ID of a call.
caller	int	Indicates the calling number.
called	int	Indicates the called number.
callskill	string	Indicates the description of a call skill.
callskillid	int	Indicates the ID of a call skill.
orgcallednum	string	This parameter is not used.
calldata	string	Indicates the call-associated data.
beginTime	long	Indicates the answering start time (timestamp, in milliseconds).
endTime	long	This parameter is not used.
userPriority	int	Indicates the customer level. The valid customer level codes range from 1 to 254. A larger code indicates a higher customer level and priority.
trunkNo	int	Indicates the trunk number.

Parameter	Data Type	Description
logontimes	int	Indicates the total queuing duration of the call, in seconds.
mediaAbility	int	Indicates the media capability. 1: audio; 2: video.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/callinfo?isNoContainLastCall=false HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"callfeature":0,"callid":"1476838963-224","caller":"70004","called":"60015","callskill":"voice","callskillid":20011, "orgicallednum":"","calldata":"","begintime":1476838963000,"endtime":null,"userPriority":0,"trunkNo":65535, "logontimes":0,"mediaAbility":1}}</pre>

Triggered Event

- None

Error Code

- 100-006

Parent topic: [Call Data: calldata](#)

Querying Call Information Before Answering a Call

Interface Description

This interface is used by an agent that has logged in to query the call information before answering a call.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/callinfobeforeanswer
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the call information returned after a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callfeature	int	Indicates the type of a call. See Call Types .
callid	string	Indicates the ID of a call.
caller	int	Indicates the calling number.
called	int	Indicates the called number.
callskill	string	Indicates the description of a call skill.
callskillid	int	Indicates the ID of a call skill.
orgcallednum	string	This parameter is not used.
calldata	string	Indicates the call-associated data.
begintime	long	Indicates the start time of answering a call.
endtime	long	This parameter is not used.
userPriority	int	Indicates the customer level. The valid customer level codes range from 1 to 254. A larger code indicates a higher customer level and priority.
trunkNo	int	Indicates the trunk number.
logontimes	int	Indicates the total queuing duration of the call, in seconds.

Parameter	Data Type	Description
mediaAbility	int	Indicates the media capability. 1: audio; 2: video.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/callinfobeforeanswer HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"callfeature":0,"callid":"1476838963-224","caller":"70004","called":"60015","callskill":"voice","callskillid":20011, "orgicallednum":"","calldata":"","beginTime":1476838963000,"endTime":null,"userPriority":0,"trunkNo":65535, "logontimes":0,"mediaAbility":1}}</pre>

Triggered Event

- None

Error Code

- 100-006

Parent topic: [Call Data: calldata](#)

Querying Call Information About the Home VDN

Interface Description

This interface is used by an agent that has logged in to query the call information about the home VDN.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/allcallinfoinvdn
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates a list of call information objects returned after a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
calltype	int	Indicates the type of a call. See Call Types .
callid	string	Indicates the ID of a call.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/allcallinfoinvdn HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"callid": "1456232265-1194","calltype": 6}]}</pre>

Triggered Event

- None

Error Code

- 100-006

- 100-007

Parent topic: [Call Data: calldata](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying Information About All Call IDs

Interface Description

This interface is used by an agent that has logged in to query the information about all call IDs.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/allcallid
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the call ID list returned after a successful query.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/allcallid HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0", "result": ["1456232265-1194"]}</pre>

Triggered Event

- None

Error Code

- 100-006

Parent topic: [Call Data: calldata](#)

Querying Call Information by Call ID

Interface Description

This interface is used by an agent that has logged in to query call information by call ID.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/callinfobycallid/{callid}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
callid	string	Yes	Indicates the ID of the call to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the call information returned after a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callfeature	int	Indicates the type of a call. See Call Types .
callid	string	Indicates the ID of a call.
caller	int	Indicates the calling number.
called	int	Indicates the called number.
callskill	string	Indicates the description of a call skill.
callskillid	int	Indicates the ID of a call skill.
orgcallednum	string	This parameter is not used.
calldata	string	Indicates the call-associated data.
begintime	long	Indicates the start time of answering a call.
endtime	long	This parameter is not used.
userPriority	int	Indicates the customer priority.
trunkNo	int	Indicates the trunk number.

Parameter	Data Type	Description
logontimes	int	Indicates the total queuing duration of the call, in seconds.
mediaAbility	int	Indicates the media capability. 1: audio; 2: video.

Interface Example

Example Type	Reference Format
Example of a request packet	<code>GET /agentgateway/resource/calldata/1010/callinfobycallid/1476070409-38 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</code>
Example of a response packet	<code>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"callfeature":0,"callid":"1476070409-38","caller":"70001","called":"10086","callskill":"voice_jst","callskillid":3, "orgicallednum":"12345678","calldata":"","begintime":1476070413000,"endtime":null,"userPriority":0,"trunkNo":65535, "logontimes":0,"mediaAbility":1}}</code>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Call Data: calldata](#)

Querying Call IDs of a Specified Agent

Interface Description

This interface is used by an agent that has logged in to query call IDs of a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/allcallinfoEx/{workno}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
workno	int	Yes	Indicates the work ID of the agent to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, a list of call IDs of a specified agent.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/allcallinfoEx/1012 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":["1456297722-1253","1456297463-1249"]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 100-011
- 900-002

Parent topic: [Call Data: calldata](#)

Querying the Number of Current Calls of an Agent

Interface Description

This interface is used by an agent that has logged in to query the number of current calls.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/callnums
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	string	Indicates the return result of a successful query, that is, the number of current calls of an agent.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/callnums HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0", "result": 1}</pre>

Triggered Event

- None

Error Code

- 100-006

Parent topic: [Call Data: calldata](#)

Querying All Call Information of a Specified Agent

Interface Description

This interface is used by an agent that has logged in to query all call information about a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent and the specified agent have logged in to the same agent server.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/allcallinfo/{workno}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
workno	int	Yes	Indicates the work ID of the agent to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates a list of all call information objects of an agent returned after a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callfeature	int	Indicates the type of a call. See Call Types .
callid	string	Indicates the ID of a call.
caller	int	Indicates the calling number.
called	int	Indicates the called number.
callskill	string	Indicates the description of a call skill.
callskillid	int	This parameter is not used.
orgcallednum	string	This parameter is not used.
calldata	string	This parameter is not used.
begintime	long	This parameter is not used.
endtime	long	This parameter is not used.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/allcallinfo/1012 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"callfeature": 0,"callid": "1456284702-1218","caller": "70082","called": "6048","callskill": "Voice_jinsitao","callskillid": 25,"orgicallednum": "", "calldata": null,"begintime": null, "endtime": null}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-002

Parent topic: [Call Data: calldata](#)

Querying Current Call Statistics Information About an Agent

Interface Description

This interface is used by an agent that has logged in to query the current call statistics information about an agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/statistics
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the current call statistics information about an agent returned after a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
talktime	long	Indicates the total call duration on the current day (in seconds).
answernums	int	Indicates the number of call answers on the current day.
noanswernums	int	Indicates the number of no answers after a long wait on the current day.
calloutnums	int	Indicates the number of outgoing calls on the current day.
intercallnums	int	Indicates the number of internal calls on the current day.
interhelpnums	int	Indicates the number of times of asking for internal help on the current day.
transfernums	int	Indicates the number of internal transfers.
transferoutnums	int	Indicates the number of transfers to external numbers.
transferivnums	int	Indicates the number of calls that are transferred to IVR on the current day.
redirectnums	int	Reserved.
keepnums	int	Indicates the number of times that the agent is on hold.
busynums	int	Indicates the number of times that the agent is in the busy state.
restnums	int	Indicates the number of times that the agent rests.

Parameter	Data Type	Description
restoutnums	int	Indicates the excess number of times that the agent takes rests.
resttime	long	Indicates the rest duration (in seconds).
restouttime	long	Indicates the duration exceeding the rest duration (in seconds).
agentrelease	int	Indicates the number of active releases.
busytime	long	Indicates the busy duration (in seconds).

Interface Example

Example Type	Reference Format
Example of a request packet	<code>GET /agentgateway/resource/calldata/1010/statistics HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</code>
Example of a response packet	<code>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "talktime": 4328, "answernums": 5, "noanswernums": 0, "calloutnums": 0, "intercallnums": 5, "interhelprnums": 0, "transfernums": 0, "transferoutnums": 0, "transferivrnums": 0, "redirectnums": 0, "keepnums": 0, "busynums": 0, "restnums": 0, "restoutnums": 0, "resttime": 0, "restouttime": 0, "agentrelease": 1, "busytime": 0 } }</code>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Call Data: calldata](#)

Querying Information About Queuing Calls in a Specified Skill Queue

Interface Description

This interface is used to query all calls queued in a specified public skill queue after agent sign-in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/waitcallinfo/{skillid}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
skillid	int	Yes	Indicates the ID of the skill queue to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates a list of queuing call information objects returned after a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callfeature	int	Indicates the type of a call. See Call Types .
callid	string	Indicates the ID of a call.
caller	int	Indicates the calling number.
called	int	Indicates the called number.
callskill	string	Indicates the description of a call skill.
callskillid	int	Indicates the ID of a call skill.
orgcallednum	string	This parameter is not used.
calldata	string	Indicates the call-associated data.
begintime	long	Indicates the time when the call starts to queue (timestamp, in milliseconds). Note: This parameter is valid only for voice and video services.
endtime	long	This parameter is not used.
userPriority	int	Indicates the customer level.

Parameter	Data Type	Description
trunkNo	int	Indicates the trunk number.
logontimes	int	Indicates the total queuing duration of the call, in seconds.
mediaAbility	int	Indicates the media capability. 1: audio; 2: video.

Interface Example

Example Type	Reference Format
Example of a request packet	<code>GET /agentgateway/resource/calldata/1010/waitcallinfo/5 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</code>
Example of a response packet	<code>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": [{"callfeature":0,"callid":"1476707884-279","caller":"70004","called":"60015","callskill":"voice","callskillid":1, "orgicallednum":"","calldata":"","begintime":1476707884000,"endtime":null,"userPriority":0,"mediaAbility":1}, {"callfeature":0,"callid":"1476707885-280","caller":"70003","called":"60015","callskill":"voice","callskillid":1, "orgicallednum":"","calldata":"","begintime":1476707885000,"endtime":null,"userPriority":0,"trunkNo":65535, "logontimes":0,"mediaAbility":1}]}</code>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Call Data: calldata](#)

Querying Whether the Agent Is Processing or Is to Process a Call

Interface Description

This interface is used by an agent that has logged in to query whether an agent is processing or is to process a call, for example, call ringing or in a conversation.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/isprocesscall
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	boolean	Indicates the return result, true or false , of a successful query.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/isprocesscall HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": true}</pre>

Triggered Event

- None

Error Code

- 100-006

Parent topic: [Call Data: calldata](#)

Querying Information About Queuing Calls in a Specified IVR System

Interface Description

This interface is used by an agent that has logged in to query the information about queuing calls in a specified IVR system.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/ivrcallinfo/{ivrid}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
ivrid	int	Yes	Indicates the ID of the IVR system to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates a list of queuing call information objects returned after a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callfeature	int	Indicates the type of a call. See Call Types .
callid	string	Indicates the ID of a call.
caller	int	Indicates the calling number.
called	int	Indicates the called number.
callskill	string	Indicates the description of a call skill.
callskillid	int	Indicates the ID of a call skill.
orgcallednum	string	This parameter is not used.
calldata	string	Indicates the call-associated data.
begintime	long	Indicates the answering start time (timestamp, in milliseconds).
endtime	long	This parameter is not used.
userPriority	int	Indicates the customer level.
trunkNo	int	Indicates the trunk number.

Parameter	Data Type	Description
logontimes	int	Indicates the total queuing duration of the call, in seconds.
mediaAbility	int	Indicates the media capability. 1: audio; 2: video.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/ivrcallinfo/4 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": [{"callfeature":0,"callid":"1476707884-279","caller":"70004","called":"60015","callskill":"voice","callskillid":1, "orgicallednum":"","calldata":"","begintime":1476707884000,"endtime":null,"userPriority":0,"mediaAbility":1}, {"callfeature":0,"callid":"1476707885-280","caller":"70003","called":"60015","callskill":"voice","callskillid":1, "orgicallednum":"","calldata":"","begintime":1476707885000,"endtime":null,"userPriority":0,"trunkNo":65535, "logontimes":0,"mediaAbility":1}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Call Data: calldata](#)

Querying Information About Queuing Calls in a Private Queue

Interface Description

This interface is used by an agent that has logged in to query the information about queuing calls in a private queue of an agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/privatecallinfo
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates a list of queuing call information objects returned after a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callfeature	int	Indicates the type of a call. See Call Types .
callid	string	Indicates the ID of a call.
caller	int	Indicates the calling number.
called	int	Indicates the called number.
callskill	string	Indicates the description of a call skill.
callskillid	int	This parameter is not used.
orgcallednum	string	This parameter is not used.
calldata	string	This parameter is not used.
begintime	long	This parameter is not used.
endtime	long	This parameter is not used.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/privatecallinfo HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"callfeature": 7, "callid": "1456295530-1236", "caller": "70093", "called": "6058","callskill": "Voice_jinsitao","callskillid": 0,"orgcallednum": null,"calldata": null,"begintime": null,"endtime": null}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Call Data: calldata](#)

Querying Phone Number Information About Parties Making Calls on a Specified Agent

Interface Description

This interface is used by an agent that has logged in to query information about all phone numbers of parties making calls on a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/remotenumbers
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, a list of phone numbers.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/remotenumbers HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":["70093","70092"]}</pre>

Triggered Event

- None

Error Code

- 100-006

Parent topic: [Call Data: calldata](#)

Querying the Number of Calls in a Specified IVR System

Interface Description

This interface is used by an agent that has logged in to query the number of calls in a specified IVR system.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/ivrccount/{ivrid}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
ivrid	int	Yes	Indicates the ID of the IVR system to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	int	Indicates the number of calls in a specified IVR system returned after a successful query.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/ivrccount/4 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": 0}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Call Data: calldata](#)

Querying Whether an Agent Has the Permission to Release a Specified Call

Interface Description

After **Agent Hung up Mode** of a skill queue is set to the value indicating that the call is re-queued after hang-up, this interface can be used to query whether an agent has the permission to release a specified call. If the agent does not have the permission, the call is re-queued after the agent releases the call.

Usage Description

- Prerequisites
 - The agent has logged in.
 - The call is available to the agent or is in the skill queue.
 - Agent Hung up Mode** is set to the value indicating that the call is re-queued after hang-up.
- Precautions
 - None
- Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/releaseauthoritybycallid/{callid}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
callid	long	Yes	Indicates the unique call ID.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
result	int	For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
isAgentReleaseAllowed	boolean	false : The agent does not have the permission to release the call. true : The agent has the permission to release the call.
callId	string	Indicates the unique call ID.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/releaseauthoritybycallid/1493792611-30 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"isAgentReleaseAllowed":false,"callId":"1493792611-30"}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Call Data: calldata](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying the Geographical Location Based on the Calling Number

Interface Description

This interface is used to query the location information of the calling party based on the calling number.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in an ongoing call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/locationbycaller/{caller}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
caller	string	Yes	Indicates the calling number, which is mandatory and consists of 1 to 24 digits.
Request Header			
Content-Type	string	No	The value is "application/json; charset=UTF-8".
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	For the description of the parameters in the result object, see Table 3 .

Table 3 Parameter description of **result**

Parameter	Data Type	Description
location	string	Indicates the location information. The maximum length is 2044 bytes.
lbsType	string	Indicates the location information format. The options are as follows: 0 : unknown; 1 : LbyV; 2 : LbyR.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/102/locationbycaller/86006 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"location":"<?xml version='1.0'?> <presence xmlns='urn:ietf:params:xml:ns:pidf'xmlns:dm='urn:ietf:params:xml:ns:pidf:data- model'xmlns:gp='urn:ietf:params:xml:ns:pidf:geopriv10'xmlns:gml='http://www.opengis.net/gml'xmlns:gs='http://www.opengis.net/pid flo/1.0'xmlns:cl='urn:ietf:params:xml:ns:pidf:geopriv10:civicAddr'xmlns:con='urn:ietf:params:xml:ns:geopriv:conf'entity='sip:+96 6583110341@ims.mnc004.mcc420.3gppnetwork.org'> ", "lbsType":"1"}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007
- 100-020

Parent topic: [Call Data: calldata](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Updating the Geographical Location Based on the Calling Number

Interface Description

This interface is used to update the location of the calling party based on the calling number.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The call is available to the agent or is in the skill queue.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/refreshlocationbycaller
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Indicates the message description.
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
caller	string	Yes	Indicates the calling number, which is mandatory and consists of 1 to 24 digits.
location	string	Yes	Indicates the location information. The maximum length is 2044 bytes.
lbsType	string	Yes	Indicates the location information format. The options are as follows: 0 : unknown; 1 : LbyV; 2 : LbyR. Currently, only the location information in the LbyV format can be updated.

Response Message

Table 2 Response message description

Parameter	Data Type	Indicates the message description.
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/refreshlocationbycaller HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- None

Error Code

- 000-002

- 100-006
- 100-007

Parent topic: [Call Data: calldata](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying MSD Data by Call ID

Interface Description

This interface is used by an agent that has logged in to query MSD data by call ID.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/calldata/{agentid}/msdbycallid/{callid}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
callid	string	Yes	Indicates the ID of the call to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the MSD data returned after a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
MSD	string	MSD data.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/calldata/1010/msdbycallid/1476070409-38 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"MSD":"datadata"}}</pre>

Triggered Event

- None

Error Code

- 200-028

Parent topic: [Call Data: calldata](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Agent Event: agentevent

AGENT POLL Mode

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

AGENT POLL Mode

[Obtaining the Events of a Single Agent in Polling Mode \(Normal\)](#)

Parent topic: [Agent Event: agentevent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Obtaining the Events of a Single Agent in Polling Mode (Normal)

Interface Description

This interface is used to obtain the events of a single agent in polling mode.

NOTE

If an agent has no event, the interface will return the response after 10 seconds. If the agent has events, the interface will return the response immediately. Modify configurations in the **agentgateway/WEB-INF/config/basic.properties** file as follows:

AGENT_POLL_WAIT_FLAG = ON // Indicates whether to wait. If the value is **ON** and the target agent has no event, the server returns a response after 10 seconds.

AGENT_POLL_WAIT_TIMES = 100 // If the target agent has no event, the interface waits for a maximum of 100 times.

AGENT_POLL_WAIT_INTERVAL = 100 // Indicates the waiting duration each time, in milliseconds.

Usage Description

1. Prerequisites

- This interface is designed for obtaining associated events of an agent that has logged in to a specific Agent Gateway. The events are obtained by polling in short HTTP connection mode.
- This mode allows users to obtain short-connection events of a single agent.
- Configuration in the **agentgateway/WEB-INF/config/basic.properties** file has been modified as follows:
EVENT_METHOD = AGENT_POLL
GET_EVENT_MODE = 1

2. Precautions

None

3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentevent/{agentid}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	list	Indicates the event object. For the parameter description of event , see Table 3 .

Table 3 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type. See Events .
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the content of an event. The definition varies with the event.

Interface Example

Example Type	Reference Format
Example of a request packet	GET /agentgateway/resource/agentevent/1010 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "event": { "eventType": "AgentOther_InService", "workNo": "291", "content": null } }

Triggered Event

- None

Error Code

- 000-001
- 100-006
- 000-003

Parent topic: [AGENT POLL Mode](#)

Query Monitoring: querymonitor

[Querying the Local System Time of the Main CCS Server](#)

[Querying the Server Version](#)

[Search System State Information](#)

[Querying Cluster Service Information](#)

[Querying the Service Cluster Information About a Specified Agent](#)

[Querying the Service Cluster Information About All Agents](#)

[Querying the Information About a Specified Service Cluster](#)

[Querying the Traffic Statistics Information About a Specified Skill Queue](#)

[Configuring the Effectiveness of the Agent Handshake Timer](#)

[Setting the Number of Instant Calls That an Agent can Handle Simultaneously](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying the Local System Time of the Main CCS Server

Interface Description

This interface is used by an agent that has logged in to query the local system time of the main CCS server.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/querymonitor/{agentid}/servertime
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Indicates the local system time of the CCS server returned after a successful query. Default time format: yyyy-MM-dd HH:mm:ss

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/querymonitor/1010/servertime HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": "2016-02-24 17:04:46"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Query Monitoring: querymonitor](#)

Querying the Server Version

Interface Description

This interface is used by an agent that has logged in to query the server version.

Usage Description

- Prerequisites
 - The agent has logged in.
- Precautions
 - None
- Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/querymonitor/{agentid}/systemversion
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
result	list	Indicates the return result of a successful query, that is, an information list of server versions. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
ip	string	Indicates the IP address of a server.
servertype	int	Indicates the server type.
version	int	Indicates the version information.
description	int	Indicates the description information about a server.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/querymonitor/1010/systemversion HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":0,"result":[{"ip": "10.177.120.250","servertype": 12, "description": "SERVER_TYPE_UIS_MAIN", "version": "ICDV300R006C85"}, {"ip": "10.177.120.250","servertype": 2, "description": "SERVER_TYPE_CS_MAIN", "version": "ICDV300R006C85"}, {"ip": "10.177.120.250","servertype": 6, "description": "SERVER_TYPE_WEBM_MAIN", "version": "ICDV300R006C85"}, {"ip": "10.177.120.250","servertype": 0, "description": "SERVER_TYPE_CCS_MAIN", "version": "ICDV300R006C85"}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Query Monitoring: querymonitor](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Search System State Information

Interface Description

This interface is used by an agent that has logged in to query the system state information.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/querymonitor/{agentid}/systemstate
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Indicates the return result of a successful query, that is, the system state information. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
busyagent	int	Indicates the number of agents that are busy.
idleagent	int	Indicates the number of agents that are idle.
callinqueuenum	int	Indicates the number of queuing users.
callnum	int	Indicates the current number of calls in the system.
skillnum	int	Indicates the number of skill queues of the home VDN of the agent.
talkingnum	int	Indicates the number of agents that are occupied by calls.
totalloginagent	int	Indicates the total number of agents that are logged in.
versioninfo	string	Indicates the version information about a server.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/querymonitor/1010/systemstate HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "busyagent": 0, "idleagent": 1, "callinqueuenum": 0, "callnum": 0, "skillnum": 71, "talkingnum": 0, "totalloginagent": 1, "versioninfo": "ICDV300R006C85" } }

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Query Monitoring: querymonitor](#)

Querying Cluster Service Information

NOTE

This interface is no longer in use because the cluster cache is not used.

Interface Description

This interface is used by an agent that has logged in to query the cluster service information.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/querymonitor/{agentid}/clusterinfo
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	array	Indicates the cluster service information returned after a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
clusterName	string	Indicates the name of a cluster.
agentNum	int	Indicates the number of agents.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/querymonitor/1010/clusterinfo HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"clusterName": "AgentGateway0","agentNum": 1}]}</pre>

Triggered Event

- None

Error Code

- 100-006

Parent topic: [Query Monitoring: querymonitor](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying the Service Cluster Information About a Specified Agent

NOTE

This interface is no longer in use because the cluster cache is not used.

Interface Description

This interface is used by an agent that has logged in to query the service cluster information about a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/querymonitor/{agentid}/agentclusterinfo/{workno}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
workno	int	Yes	Indicates the work ID of the agent to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	string	Indicates the cluster name returned after a successful query.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/querymonitor/1010/agentclusterinfo/1011 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result": "AgentGateway0"}</pre>

Triggered Event

- None

Error Code

- 100-006

Parent topic: [Query Monitoring: querymonitor](#)

Querying the Service Cluster Information About All Agents

NOTE

This interface is no longer in use because the cluster cache is not used.

Interface Description

This interface is used by an agent that has logged in to query the service cluster information about all agents.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/querymonitor/{agentid}/allagentclusterinfo
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates a list of cluster service information returned after a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
clusterName	string	Indicates the name of a cluster.
Agentname	string	Indicates the name of an agent.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/querymonitor/1010/allagentclusterinfo HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"clustername": "AgentGateway0","agentname": "49999"}]}</pre>

Triggered Event

- None

Error Code

- 100-006

Parent topic: [Query Monitoring: querymonitor](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying the Information About a Specified Service Cluster

NOTE

This interface is no longer in use because the cluster cache is not used.

Interface Description

This interface is used by an agent that has logged in to query the information about a specified service cluster.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/querymonitor/{agentid}/clusterinfobyname/{clustername}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
clustername	string	Yes	Indicates the name of the cluster service to be queried (The maximum length is 100).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query, that is, a list of agent IDs that belong to a specified cluster.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/querymonitor/1010/clusterinfobyname/AgentGateway0 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0", "result": ["49999"]}</pre>

Triggered Event

- None

Error Code

- 100-006

Parent topic: [Query Monitoring: querymonitor](#)

Querying the Traffic Statistics Information About a Specified Skill Queue

Interface Description

This interface is used by an inspector that has logged in to query the traffic statistics information about a specified skill queue.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/querymonitor/{agentid}/skillstatisticinfo/{skillid}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
skillid	int	Yes	Indicates the ID of the skill queue to be queried.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Indicates the return result of a successful query, that is, the traffic statistics information. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
agentIdleNums	int	Indicates the number of idle agents.
agentLoginNums	int	Indicates the number of agents that have logged in.
agentMaxIdleTime	int	Indicates the longest idle duration among all agents in the last five minutes (internal time interval of the CTI).
agentOccupyNums	int	Indicates the number of agents in the occupied state.
agentPreOccupyNums	int	Indicates the number of agents in the preoccupied state.
agentRestNums	int	Indicates the number of resting agents.
agentSetBusyNums	int	Indicates the number of agents in the busy state.
agentStudyNums	int	Indicates the number of agents in the study state.
agentTalkingNums	int	Indicates the number of talking agents.
agentWorkNums	int	Indicates the number of agents in the wrap-up state, including the agents in the adjusting state.
allCallNums	int	Indicates the number of calls.

Parameter	Data Type	Description
callWaitNums	int	Indicates the number of queuing calls (or waiting calls).
connectedCallNumIn20	int	Indicates the number of calls that are connected within 20s (internal time interval of the CTI).
evenCallTime	int	Indicates the average call duration in the last five minutes (internal time interval of the CTI). The unit is second.
evenWaitTime	int	Indicates the average call waiting time in the last five minutes (internal time interval of the CTI). The unit is second.
maxCallWaitTimes	int	Indicates the longest call waiting time in the last five minutes (internal time interval of the CTI). The unit is second.
processingCallNums	int	Indicates the number of calls that are being processed.
totalCallNums	int	Indicates the total number of calls that are processed.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/querymonitor/1010/skillstatisticinfo/5 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"agentIdleNums": 1,"agentLoginNums": 1,"agentMaxIdleTime": 18657,"agentOccupyNums": 0,"agentPreOccupyNums": 0,"agentRestNums": 0,"agentSetBusyNums": 0,"agentStudyNums": 0,"agentTalkingNums": 0,"agentWorkNums": 0,"allCallNums": 0,"callWaitNums": 0,"connectedCallNumIn20": 0,"evenCallTime": 0,"evenWaitTime": 0,"maxCallWaitTimes": 0,"processingCallNums": 0,"totalCallNums": 0}}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 900-002

Parent topic: [Query Monitoring: querymonitor](#)

Configuring the Effectiveness of the Agent Handshake Timer

Interface Description

This interface is used by an agent that has logged in to configure the effectiveness of the agent handshake timer.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/querymonitor/{agentid}/setagenttimeout/{flag}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
flag	string	Yes	Indicates the timer flag. (OFF indicates the timer is set to off and other values indicate the timer is set to on. The maximum length is 5 characters.)
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/querymonitor/1010/setagenttimeout/OFF HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006

Parent topic: [Query Monitoring: querymonitor](#)

Setting the Number of Instant Calls That an Agent can Handle Simultaneously

Interface Description

This interface is used by an agent that has logged in to set the number of instant calls that a specified agent can handle simultaneously. The configuration takes effect after the agent state changes.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/querymonitor/{agentid}/setmaxchatnum/{vdnid}/{chatnum}?agents={agents}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
vdnid	int	Yes	Indicates the VDN ID.
chatnum	int	Yes	Indicates the number of instant calls that an agent can handle simultaneously. The maximum value is 30 .
agents	string	Yes	Indicates the work ID of the target agent. (For multiple agents, separate them with a semicolon (;). The maximum length is 100 characters).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/querymonitor/1010/setmaxchatnum/1/10?agents=1012;1045;1083 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007

Real-Time Quality Control: [qualitycontrol](#)

[Inserting](#)

[Listening On](#)

[Intercepting](#)

[Starting Monitoring](#)

[Stopping Monitoring](#)

[Stopping Whispering](#)

[Requesting Whispering](#)

[Switching Among Whispering, Listening, and Inserting](#)

[Canceling Listening and Inserting](#)

[Indicating an Agent in Busy State Forcibly](#)

[Indicating an Agent in Idle State Forcibly](#)

[Forcibly Logging Out](#)

[Releasing a Call Forcibly](#)

[Screen Inspection](#)

[Querying Information About All Agents That Can Be Monitored](#)

[Adjusting the Skill Queue of a Specified Agent](#)

[Applying for Joining a Multimedia Conference](#)

[Obtaining the Recording Duration](#)

[Generating the Recording Download Path](#)

[Downloading a Recording File](#)

[Forcibly Showing Busy with a Reason Code](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Inserting

Interface Description

This interface is used by an inspector that has logged in to insert an agent for real-time quality control.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/addinsert/{workNo}?mediaType={mediaType}
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
workNo	int	Yes	Indicates the work ID of the agent to be inserted.
mediaType	string		Indicates the media type. Value 1 indicates text chat, and value 5 indicates voice call. This parameter is not required for voice call inspection, but is mandatory for text chat inspection.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/qualitycontrol/1019/addinsert/1012 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Remarks

NOTE

Inspectors in ACW state can perform the **Listen** operation but not the **Barge** operation.

Triggered Event

- None

Error Code

- 100-006

- 900-001
- 900-002
- 900-003
- 900-005

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Listening On

Interface Description

This interface is used by an inspector that has logged in to listen on a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://{ip}:{port}/agentgateway/resource/qualitycontrol/{agentid}/addsupervise/{workNo}?mediaType={mediaType}
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
workNo	int	Yes	Indicates the work ID of the agent to be listened.
mediaType	string		Indicates the media type. Value 1 indicates text chat, and value 5 indicates voice call. This parameter is not required for voice call inspection, but is mandatory for text chat inspection.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/qualitycontrol/1019/addsupervise/1012 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003
- 900-005

Intercepting

Interface Description

This interface is used by an inspector that has logged in to intercept a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/intercept/{workNo}?mediaType={mediaType}&callId={callId}
Request Method	PUT

Request Message

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
workNo	int	Yes	Indicates the work ID of the agent to be intercepted.
mediaType	string		Indicates the media type. Value 1 indicates text chat, and value 5 indicates voice call. This parameter is not required for voice call inspection, but is mandatory for text chat inspection.
callId	string		Indicates the call ID. This parameter is not required for voice call inspection, but is mandatory for text chat inspection.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 1 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/qualitycontrol/1019/intercept/1012 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003

Starting Monitoring

Interface Description

This interface is used by an inspector that has logged in to monitor a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/beginmonitor?agents={agents}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
agents	string	Yes	Indicates the work ID of the agent to be monitored. (For multiple agents, separate them with a semicolon ";". The maximum length is 100 characters.)
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/beginmonitor?agents=1010;1011;1012;1013 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003
- 900-004

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Stopping Monitoring

Interface Description

This interface is used by an inspector that has logged in to stop monitoring a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/endmonitor?agents={agents}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
agents	string	Yes	Indicates the work ID of the agent to be monitored. (For multiple agents, separate them with a semicolon ";". The maximum length is 100 characters.)
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/endmonitor?agents=1010;1011;1012;1013 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003
- 900-004

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Stopping Whispering

Interface Description

This interface is used by an inspector that has logged in to stop whispering.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/requeststopwhisperagent?whisperagentid={whisperagentid}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
whisperagentid	int	Yes	Indicates the work ID of the agent that the inspector is whispering to.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/requeststopwhisperagent?whisperagentid=1010 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003
- 900-004

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Requesting Whispering

Interface Description

This interface is used by an inspector that has logged in to request whispering. After the request is successful, the inspector can hear the talking of the agent and customer, but when the inspector is talking to the seat, the customer cannot hear the inspector.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/requestwhisperagent?whisperagentid={whisperagentid}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
whisperagentid	int	Yes	Indicates the work ID of the agent that the inspector is whispering to.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/requestwhisperagent?whisperagentid=1010 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003
- 900-004

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Switching Among Whispering, Listening, and Inserting

Interface Description

This interface is used by an inspector to switch among whispering, listening, and inserting.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/requestswitchinsertwhisperagent?whisperagentid={whisperagentid}&switchtype={switchtype}&mediaType={mediaType}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
whisperagentid	int	Yes	Indicates the work ID of the agent that the inspector is whispering to.
switchtype	int	Yes	Indicates the switching type. (0 indicates switching to listening; 1 indicates switching to inserting; and 2 indicates switching to whispering.)
mediaType	string		Indicates the media type. Value 1 indicates text chat, and value 5 indicates voice call. This parameter is not required for voice call inspection, but is mandatory for text chat inspection.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/requestswitchinsertwhisperagent?whisperagentid=1010&switchtype=2 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002

- 900-003
- 900-004

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Canceling Listening and Inserting

Interface Description

This interface is used by an inspector that has logged in to cancel listening and inserting on a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/{workNo}?mediaType={mediaType}
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of the inspector who has logged in.
workNo	int	Yes	Indicates the work ID of the specified agent.
mediaType	string		Indicates the media type. Value 1 indicates text chat, and value 5 indicates voice call. This parameter is not required for voice call inspection, but is mandatory for text chat inspection.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/qualitycontrol/1019/1011 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003

Indicating an Agent in Busy State Forcibly

Interface Description

This interface is used by an inspector that has logged in to indicate that a specified agent is in busy state forcibly.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/forcebusy/{workNo}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
workNo	int	Yes	Indicates the work ID of the specified agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/forcebusy/1010 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Indicating an Agent in Idle State Forcibly

Interface Description

This interface is used by an inspector that has logged in to indicate that a specified agent is in idle state forcibly.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/forceidle/{workNo}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
workNo	int	Yes	Indicates the work ID of the specified agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/forceidle/1010 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Forcibly Logging Out

Interface Description

This interface is used by an inspector that has logged in to log out a specified agent forcibly.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/forcelogout/{workNo}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
workNo	int	Yes	Indicates the work ID of the specified agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/forcelogout/1010 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Releasing a Call Forcibly

Interface Description

This interface is used by an inspector that has logged in to release a call forcibly.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/forcedropcall/{callid}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
callid	int	Yes	Indicates the ID of the specified call.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/forcedropcall/1501127996-2 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Screen Inspection

[Querying Inspection Tasks](#)

[Reporting the Port Number of Screen Recording](#)

[Start Screen Inspection](#)

[Stopping Screen Inspection](#)

[Starting and Stopping Screen Recording Playback](#)

[Deleting Real-Time Screen Inspection, Immediate Screen Recording, and Scheduled Screen Recording Tasks](#)

[Notifying the CCS of the Startup Result of a Screen Recording or Screen Inspection Task](#)

[Deleting an Inspection Task](#)

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying Inspection Tasks

Interface Description

This interface is used by an inspector that has logged in to query the inspection tasks.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/queryqctasks
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Indicates an information list of inspection tasks returned after a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
duration	long	Indicates the duration of a task.
state	int	Indicates the state of a task. (1 : Submitted; 2 : Active; 3 : Paused)
agentid	string	Indicates the work ID of the agent to be inspected.
agentname	string	Indicates the name of the agent to be inspected.
ccid	int	Indicates the contact center ID.
mediatype	int	Media Types
qcagentid	string	Indicates the work ID of an inspector.
qcagentname	string	Indicates the name of an inspector.
startdatetime	Date	Indicates the start time of a task.
statestr	string	Indicates the description of the task state.
taskdsn	int	Indicates the serial number of a task.
tasktypeid	int	Indicates the ID of a task type. (0 : Unknown; 1 : Monitoring; 2 : Screen recording playback; 3 : Voice playback; 4 : Real-time screen inspection; 5 : Screen recording; 6 : Automatic recording; 7 : Listening and inserting)

Parameter	Data Type	Description
tasktypedescription	string	Indicates the description of the task type.

Interface Example

Example Type	Reference Format
Example of a request packet	<code>GET /agentgateway/resource/qualitycontrol/1010/queryqctasks HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</code>
Example of a response packet	<code>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{ "duration": 2909, "state": 3, "agentid": "49999", "agentname": "49999", "ccid": 1, "mediatype": 5, "qcagentid": "111", "qcagentname": "111", "startdatetime": 1456337563000, "statestr": "Pause", "taskdsn": 6657, "tasktypeid": 7, "tasktypedescription": " QC_SUPERVISE_INSERT_EX" }] }</code>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003

Parent topic: [Screen Inspection](#)

Reporting the Port Number of Screen Recording

Interface Description

This interface is used by an agent that has logged in to report the screen recording port number of the agent whose screen is recorded.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/registerDataToServer?port={port}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
port	int	Yes	Indicates the port of recording control. The value ranges from 1 to 65535.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/registerDataToServer?port=8888 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-003

Parent topic: [Screen Inspection](#)

Start Screen Inspection

Interface Description

This interface is used by an inspector that has logged in to implement screen inspection on a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/startVideoMonitor
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
videoBeginTime	string	No	Indicates the start time of a scheduled screen recording. The value contains a maximum of 13 digits.
videoDuration	long	No	Indicates the duration of screen recording, in seconds. By default, the value is 0 .
videoOperationType	int	No	Indicates the type of screen inspection operation (0 : Real-time; 1 : Immediately; 2 : Scheduled). By default, the value is 1 .
isWorkInIdle	int	No	Indicates whether to perform screen recording when the agent is in idle state. (0 : No recording in idle state; 1 : Recording in idle state) By default, the value is 0 .
monitoredAgents	string	Yes	Indicates the work ID of the agent initiates automatic recording. For multiple agents, separate them with a semicolon ";". (For real-time screen inspection, only one agent is supported. The maximum length is 100.)

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the common inspection events. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
agentId	string	Indicates the work ID of an agent.
cause	string	Indicates the code of a failure cause.
causeDescription	string	Indicates the description of a failure.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/startVideoMonitor HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"videoBeginTime":"1456382859642","videoDuration":100000,"videoOperationType":1,"isWorkInIdle":0,"monitoredAgents":"49999"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"49999":{"agentId":"49999","cause":"900-008","causeDescription":"CTI cause 18.No corresponding right"}}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 900-001
- 900-002
- 900-003

Parent topic: [Screen Inspection](#)

Stopping Screen Inspection

Interface Description

This interface is used by an inspector that has logged in to stop screen inspection on a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/stopVideoMonitor
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
videoBeginTime	string	No	Indicates the start time of a scheduled screen recording. The value contains a maximum of 13 digits.
videoDuration	long	No	Indicates the duration of screen recording, in seconds. By default, the value is 0 .
videoOperationType	int	No	Indicates the type of screen inspection operation (0 : Real-time; 1 : Immediately; 2 : Scheduled). By default, the value is 1 .
isWorkInIdle	int	No	Indicates whether to perform screen recording when the agent is in idle state. (0 : No recording in idle state; 1 : Recording in idle state) By default, the value is 0 .
monitoredAgents	string	Yes	Indicates the work ID of the agent initiates automatic recording. For multiple agents, separate them with a semicolon ";". (For real-time screen inspection, only one agent is supported. The maximum length is 100.)

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the common inspection events. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
agentId	string	Indicates the work ID of an agent.
cause	string	Indicates the code of a failure cause.
causeDescription	string	Indicates the description of a failure.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/stopVideoMonitor HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"videoBeginTime":"1456382859642","videoDuration":100000,"videoOperationType":1,"isWorkInIdle":0,"monitoredAgents":"49999"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"49999":{"agentId":"49999","cause":"900-008","causeDescription":"CTI cause 2.Task ID error"}}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 900-001
- 900-002
- 900-003

Parent topic: [Screen Inspection](#)

Starting and Stopping Screen Recording Playback

Interface Description

This interface is used by an inspector that has logged in to play or stop playing screen recording of a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/startOrStopVideoPlay?monitoragent={monitoragent}&isstart={isstart}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
monitoragent	int	Yes	Indicates the work ID of the specified agent.
isstart	boolean	Yes	Indicates whether to start or stop screen recording playback (true indicates starting and false indicates stopping).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/startOrStopVideoPlay/?monitoragent=1012&isstart=true HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 900-001
- 900-002
- 900-003

Deleting Real-Time Screen Inspection, Immediate Screen Recording, and Scheduled Screen Recording Tasks

Interface Description

This interface is used by an inspector that has logged in to delete real-time screen inspection, immediate screen recording, and scheduled screen recording tasks of a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/deleteVideoTask?monitoragent={monitoragent}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
monitoragent	int	Yes	Indicates the work ID of the specified agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/deleteVideoTask?monitoragent=1012 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 900-001
- 900-002
- 900-003

Parent topic: [Screen Inspection](#)

Notifying the CCS of the Startup Result of a Screen Recording or Screen Inspection Task

Interface Description

This interface is used by an inspector that has logged in to notify the CCS of the startup result of a screen recording or screen inspection task.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/startVideoOperation?monitoragent={monitoragent}&result={result}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
monitoragent	int	Yes	Indicates the work ID of the specified agent.
result	int	Yes	Indicates the startup result. 0 : Succeed. Other values: Fail
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/startVideoOperation?monitoragent=1012&result=0 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 900-001
- 900-002
- 900-003

Parent topic: [Screen Inspection](#)

Deleting an Inspection Task

Interface Description

This interface is used by an inspector that has logged in to delete an inspection task.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/deleteqctask?taskdsn={taskdsn}&begintime={begintime}
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
taskdsn	int	Yes	Indicates the specified task number
begintime	string	Yes	Indicates the task start time. The value contains a maximum of 13 digits.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/qualitycontrol/1019/deleteqctask?taskdsn=5&begintime=100 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003
- 900-009

Parent topic: [Screen Inspection](#)

Querying Information About All Agents That Can Be Monitored

Interface Description

This interface is used by an inspector that has logged in to query information about all agents that can be monitored.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/allagent
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates an information list of inspected agents returned after a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
workNo	int	Indicates the work ID of an agent.
name	string	Indicates the name of the agent.
agentOpStatus	int	Indicates the operating status of an agent. See Operating Status of Agents .
agentOpDescription	string	Indicates the description of the operating status of an agent.
recorded	boolean	Indicates whether the agent is recorded.
monitored	boolean	Indicates whether the agent is monitored.
liveVideo	boolean	Indicates whether screen inspection is performed on the agent.
superviseInsert	boolean	Indicates whether the agent is listened or inserted.
liveVideoConfig	int	Indicates the screen inspection configuration for the agent. (0 : Off; 1 : On; 2 : Customized by the agent; 3 : Unknown)
liveVideoInitd	int	Indicates whether the initialization of screen inspection is complete. (0 : Not initialized; 1 : Initialized; 2 : Unknown)
superInsertMode	boolean	Indicates whether the agent is monitored or barged in. false : monitoring; true : inserting

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/qualitycontrol/1010/allagent HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"workNo": 161,"name": "161","agentOpStatus": 2,"agentOpDescription": "OPS_IDLE","recorded": false,"monitored": false,"liveVideo": false,"superviseInsert": false,"liveVideoConfig": 0,"liveVideoInitd": 0,"superInsertMode": false}, {"workNo": 49999,"name": "49999","agentOpStatus": 27,"agentOpDescription": "OPS_WORK","recorded": false,"monitored": false,"liveVideo": false,"superviseInsert": true,"liveVideoConfig": 0,"liveVideoInitd": 0,"superInsertMode": false}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Adjusting the Skill Queue of a Specified Agent

Interface Description

This interface is used by an inspector that has logged in to adjust the skill queue of a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/adjustskill
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
workNo	string	No	Indicates the work ID of the specified agent.
skills	array	No	Indicates the array of skill queue IDs. The array contains a maximum of 20 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/adjustskill HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"workNo":"49999","skills":[10,25]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-001
- 100-006
- 900-001
- 900-002

- 900-003

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Applying for Joining a Multimedia Conference

Interface Description

This interface is used by an inspection agent that has logged in to apply to join a multimedia conference of a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
 - The specified agent is in a multimedia conference.
 - The inspection agent is not in a multimedia conference.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/requestmultimediaconf/{workno}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
workno	int	Yes	Indicates a specified agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/requestmultimediaconf/1012 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

After successfully applying to join a conference, the inspection agent receives [AgentEvent_JoinConf \(Notification of a Multimedia Conference Message\)](#), and joins the media conference using the conference information in this event.

Error Code

- 000-002
- 100-006
- 100-007
- 700-003

Obtaining the Recording Duration

Interface Description

This interface is used to obtain the recording duration.

NOTE

This interface is applicable only to the ICP scenarios. The UIDB needs to be set on the Agent Gateway, and the database must be an Oracle database. If this interface is used, records in the **TRECORDINFOXX** table cannot exceed 3 million because more records result in slower query.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/recordinfo?url={url}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
url	string	Yes	Indicates the recording file address.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

NOTE

An example format of {url} is V:\\1\\0\\20170824\\342\\1008365.V3. The value needs to be encoded by UriEncode.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	See Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
recordId	string	Indicates the recording file address.
fileName	string	Indicates the recording file address.
duration	int	Recording duration, in milliseconds.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/qualitycontrol/1010/recordinfo?url=V:\\1\\0\\20170824\\342\\1008365.V3 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1</pre>

Example Type	Reference Format
	Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": {"recordId": "V:\\1\\0\\20170824\\342\\1008365.V3", "fileName": "V:\\1\\0\\20170824\\342\\1008365.V3", "duration": 17000}}

Triggered Event

None

Error Code

- 000-002
- 100-006
- 103-025

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Generating the Recording Download Path

Interface Description

This interface is used to generate the path for downloading the specified recording file on the Agent Server.

NOTE

After obtaining the path, you must download the recording file within 15 minutes. Otherwise, you need to invoke the interface again to generate the download path.

Usage Description

- Prerequisites
 - The agent has logged in as an inspector.
 - The inspector's **Agent** role in the WAS has the offline playback permission.
- Precautions

None
- Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/localrecordpath?format={format}&recordId={recordId}&recordFileName={recordFileName}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
format	int	Yes	Indicates the recording format. The value can be 0 (ZIP) or 1 (WAV).
recordId	string	No	Indicates the recording address, which is received in a recording start event and in the format of V:/1/0/20170824/342/1008365.V3 .
recordFileName	string	No	Indicates the recording file name, which is received in a recording start event and in the format of V:/1/0/20170824/342/1008365.V3 .
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

NOTE

- The **{recordId}** and **{recordFileName}** parameters need to be coded by UriEncode.
- At least one of the **{recordId}** and **{recordFileName}** parameters is mandatory. When both parameters are set, the system uses the value of **{recordId}**.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
result	object	For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
localRecordPath	string	Indicates the recording download path on the Agent Server.
token	string	Indicates the recording download authentication token.

Interface Example

Example Type	Reference Format
Example of a request packet	GET /agentgateway/resource/qualitycontrol/1010/localrecordpath?format=1&recordId=V:1/0/20170824/342/1008365.v3 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "localRecordPath": "/agentrecordtemp/20170705/20011/hw20170705085504.wav", "token": "bAoKdMV6e5y2PvK844dPWBBj/tGitKz+hFe27BxAziw=" } } }

Triggered Event

None

Error Code

- 000-002
- 000-003
- 100-006
- 104-001
- 104-002
- 104-003
- 104-004
- 104-005
- 104-006
- 104-007
- 104-008
- 104-009

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Downloading a Recording File

Interface Description

This interface is used to download a recording file.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
 - The interface described in [Generating the Recording Download Path](#) has been invoked to generate the recording download path.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/recordfile?token={token}&localRecordPath={localRecordPath}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
token	string	Yes	Indicates the recording download authentication token.
localRecordPath	string	Yes	Indicates the recording download path.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

NOTE

The {token} and {localRecordPath} parameters need to be coded by UriEncode.

Response Message

Table 2 Response message description (download failure)

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	string	Reserved.

Table 3 Response message description (downloaded successfully)

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Content-Disposition	string	attachment;filename=hw20170705091532.zip
Response Body		
File Stream		

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/qualitycontrol/1010/recordfile? token=bAoKdMV6e5yZPvK844dPWBBj/tGitKz+hFe27BxAziw=&localRecordPath=/agentrecordtemp/20170705/20011/hw20170705085504.wav HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"retcode":"000-003","message":"no right to invite resouce","result":""}</pre>

Triggered Event

None

Error Code

- 000-003

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Forcibly Showing Busy with a Reason Code

Interface Description

This interface is used by an inspector that has logged in to indicate that a specified agent is in busy state forcibly.

Usage Description

1. Prerequisites
 - The agent has logged in, and the agent has the inspection permission.
 - The target agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/forcebusy/{workNo}?reason={reason}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of the inspector who has logged in.
reason	int	Yes	Indicates the busy reason code. The value is an integer ranging from 200 to 250.
workNo	int	Yes	Indicates the work ID of the specified agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1019/forcebusy/1010? reason=203 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"retcode": "0", "message": "", "result": {}}</pre>

Triggered Event

None

Error Code

- 000-002
- 100-006
- 900-001
- 900-002

- 900-003

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Multimedia Conference: [multimediaconf](#)

[Applying for a Multimedia Conference](#)

[Inviting an Agent to Join a Multimedia Conference](#)

[Reporting a Multimedia Conference Joining Result](#)

[Stopping a Multimedia Conference](#)

[Querying the Multimedia Conference Status](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Applying for a Multimedia Conference

Interface Description

This interface is used to create a multimedia conference.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/multimediaconf/{agentid}/requestconf
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
callid	string	No	Indicates the conference ID. The maximum length is 30 characters.
addressinfo	string	Yes	Indicates the information about conference participants. The conference participants can only be agents. The maximum length is 1024 characters. This parameter points to an AddressID structure string that includes information about multiple to-be-invited customers. Values in the AddressID structure field are separated using commas (,), structures are separated using semicolons (;), and the string is ended with a semicolon (;). The AddressIdInfo parameter specifies the type of to-be-invited participants and the corresponding phone number or work ID. This parameter may correspond to the AddressID values of multiple participants.  NOTE The strings corresponding to different participants are as follows: Identifier of the agent type: 9. For example, when the work ID is 103 and the VDN ID is 1, the string is presented as 9,1,103; Identifier of the phone number: 6. For example, when the phone number is 7060, the string is presented as 6,7060; Identifier of the IP address: 5. For example, when the IP address is 698002, the string is presented as 5,698002; Identifier of the path: 4. For example, when the path is 40, the string is presented as 4,40;

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/multimediaconf/1019/requestconf HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1</pre>

Example Type	Reference Format
	Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 { "callid": "1455885056-1095", "addressinfo": "9,1,110;" }
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0" }

Triggered Event

- [AgentEvent_JoinConf](#) (Notification of a Multimedia Conference Message)

Error Code

- 000-002
- 100-006
- 100-007
- 700-001
- 700-003
- 700-006

Parent topic: [Multimedia Conference: multimediaconf](#)

Inviting an Agent to Join a Multimedia Conference

Interface Description

This interface is used to invite participants to join a multimedia conference.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/multimediaconf/{agentid}/inviteconf
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
confid	int	Yes	Indicates the conference ID.
addressinfo	string	Yes	Indicates the information about conference participants. The conference participants can only be agents. The maximum length is 1024 characters. This parameter points to an AddressID structure string that includes information about multiple to-be-invited customers. Values in the AddressID structure field are separated using commas (,), structures are separated using semicolons (;), and the string is ended with a semicolon (;). The AddressIdInfo parameter specifies the type of to-be-invited participants and the corresponding phone number or work ID. This parameter may correspond to the AddressID values of multiple participants.  NOTE The strings corresponding to different participants are as follows: Identifier of the agent type: 9. For example, when the work ID is 103 and the VDN ID is 1, the string is presented as 9,1,103; Identifier of the phone number: 6. For example, when the phone number is 7060, the string is presented as 6,7060; Identifier of the IP address: 5. For example, when the IP address is 698002, the string is presented as 5,698002; Identifier of the path: 4. For example, when the path is 40, the string is presented as 4,40;

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/multimediaconf/1010/inviteconf HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1</pre>

Example Type	Reference Format
	Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 { "confid": "13107206", "addressinfo": "9,1,110;" }
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0" }

Triggered Event

- [AgentEvent_OnMultimediaConfState](#) (Notification of the Multimedia Conference Status)
- [AgentEvent_JoinConf](#) (Notification of a Multimedia Conference Message)

Error Code

- 000-002
- 100-006
- 100-007
- 700-001
- 700-004

Parent topic: [Multimedia Conference: multimediaconf](#)

Reporting a Multimedia Conference Joining Result

Interface Description

This interface is used to report the multimedia conference joining result to the platform.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/multimediaconf/{agentid}/joinconfresult
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
confid	int	Yes	Indicates the conference ID.
confresult	int	Yes	Indicates the multimedia conference joining result of client. The value is of an int type and cannot be empty. The options are as follows: 0 : Succeed Other values: Fail
cause	int	No	Indicates the failure cause code (customized). The value is of an int type and can be empty when the joining result is successful.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/multimediaconf/1019/joinconfresult HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 { "confid": "13107206", "confresult": 0, "cause": }</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0"}</pre>

Triggered Event

- [AgentEvent_OnMultimediaConfState \(Notification of the Multimedia Conference Status\)](#)

Error Code

- 100-006
- 100-007

Parent topic: [Multimedia Conference: multimediaconf](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Stopping a Multimedia Conference

Interface Description

This interface is used to stop a multimedia conference.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/multimediaconf/{agentid}/stopconf
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
confid	int	Yes	Indicates the conference ID.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/multimediaconf/1019/stopconf HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"confid":"13107206"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- [AgentEvent_OnStopMultimediaConf \(Multimedia Conference Stopped\)](#)

Error Code

- 100-006
- 100-007
- 700-005

Parent topic: [Multimedia Conference: multimediaconf](#)

Querying the Multimedia Conference Status

Interface Description

This interface is used to query the multimedia conference status of a specified agent.

Usage Description

- Prerequisites
 - The agent has logged in.
- Precautions
 - None
- Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/multimediaconf/{agentid}/getconfstate
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
addressinfo	string	Yes	Indicates the information about conference participants. The conference participants can only be agents. The maximum length is 1024 characters. This parameter points to an AddressID structure string that includes information about multiple to-be-invited customers. Values in the AddressID structure field are separated using commas (,), structures are separated using semicolons (;), and the string is ended with a semicolon (;). The AddressIdInfo parameter specifies the type of to-be-invited participants and the corresponding phone number or work ID. This parameter may correspond to the AddressID values of multiple participants.  NOTE The strings corresponding to different participants are as follows: Identifier of the agent type: 9. For example, when the work ID is 103 and the VDN ID is 1, the string is presented as 9,1,103;. Identifier of the phone number: 6. For example, when the phone number is 7060, the string is presented as 6,7060;. Identifier of the IP address: 5. For example, when the IP address is 698002, the string is presented as 5,698002;. Identifier of the path: 4. For example, when the path is 40, the string is presented as 4,40;.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
result	string	Indicates the returned status information about multimedia conference participants. The information is in a string format as follows: usType, vdnID, workNo: ucConfState; . For example, when agents 102 and 103 are in the conference, and agent 104 is not in the conference, the returned result is 9,1,102:1;9,1,203:1;9,1,104:0;. If the returned value is an empty string, the interface fails to be invoked.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/multimediaconf/1019/getconfstate HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 { "addressinfo":"9,1,110;" }</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {message=, retcode=0, result=9,1,115:1;}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007
- 700-001
- 700-002

Parent topic: [Multimedia Conference: multimediaconf](#)

Conference Call: agentconf

[Applying for a Conference Call](#)

[Answering a Conference Call](#)

[Rejecting a Conference Call](#)

[Exiting a Conference Call](#)

[Releasing a Conference Call](#)

[Placing a Participant on Hold](#)

[Unholding a Participant](#)

[Applying for Conference Extension by a Conference Chair](#)

[Transferring the Conference Chair Rights](#)

[Batch Inviting Participants](#)

[Batch Deleting Participants](#)

[Modifying a Participant Attribute](#)

[Playing Announcement for a Conference Call](#)

[Stopping Announcement for a Conference Call](#)

[Playing Announcement for a Conference Call Channel](#)

[Stopping Playing Announcement for a Conference Call Channel](#)

[Changing the Number of Conference Participants](#)

[Batch Querying Conference Information](#)

[Querying a Call ID of a Participant](#)

[Querying the Conference ID of an Ongoing Conference Call on the VDN](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Applying for a Conference Call

Interface Description

This interface is used by an agent to apply for a conference call. After this interface is successfully invoked, the agent waits for a subsequent asynchronous event. After the application is successful, the agent that applies for the conference call becomes the conference chair. The agent receives the [AgentConf_SelfJoinResult \(Agent Joined a Conference Call\)](#) event, indicates that the agent can join the conference but needs to wait for the [AgentConf_RequestSuccess \(Successfully Applying for a Conference Call\)](#) event before performing the conference chair operations. Before receiving the [AgentConf_RequestSuccess \(Successfully Applying for a Conference Call\)](#) event, the platform directly returns a failure message if the agent invokes the interface related to the conference.

NOTICE

- If the current agent is in the idle or call state, the call in the call state must be stable. Otherwise, the conference call application fails. For example, if announcement playing, muting, call holding, or blocked transfer is performed, the conference call application fails.
- If two agents exist in the three-party call, the called agent cannot initiate the conference call.
- The participants can only be agents or phone numbers.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/requestagentconf
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
memberNum	int	Yes	Indicates the number of participants in a conference. The value ranges from 1 to 120 .
confCallerNo	String	No	Indicates the calling number displayed in an outgoing call. It supports a maximum of 24 bytes. When the value is not specified, the platform uses the system calling number in the basic information of the VDN configuration console by default.
time	int	No	Indicates the conference call application duration. The unit is minute. The value ranges from 4 to 1440 . The default value is 60 .
promptTime	int	No	Indicates the duration prompted before a conference call ends. It is optional. The unit is minute. The value ranges from 3 to 1440 . The default value is 3 . If the value of this parameter is equal to or larger than the value of time , the value is the value of time minus 1.
beepTone	boolean	No	Indicates whether to play the beep tone when a user joins or exits a conference call. The default value is false .
playMode	int	No	Indicates the announcement mode. 1 : Play the VP beep tone. 2 : Play the specified file tone. The default value is 1 .
voicePath	String	No	Indicates the absolute path of the beep tone code or file. When beepTone is set to True , this parameter is mandatory. When beepTone is set to False , this parameter is invalid. The maximum length is 127. The file can be a local file of the VP console or a network file that can be accessed by the VP console.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/agentconf/1019/requestagentconf HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"memberNum" : 1, "confCallerNo" : "10086", "time" : 60, "promptTime" : 3, "beepTone" : true, "playMode" : 1, "voicePath" : "66"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- If a conference call is successfully applied for, the agent receives the following events:
 - [AgentState_Busy \(Talking\)](#)
 - [AgentOther_PhoneAlerting \(Phone in Ringing State\)](#)
 - [AgentOther_PhoneOffhook \(Phone in Off-Hook State\)](#)
 - [AgentConf_SelfJoinResult \(Agent Joined a Conference Call\)](#)
 - [AgentConf_RequestSuccess \(Successfully Applying for a Conference Call\)](#)
- If a conference call fails to be applied for, the agent receives the following event:
 - [AgentConf_RequestFailed \(Applying for a Conference Call Failed\)](#)

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Conference Call: agentconf](#)

Answering a Conference Call

Interface Description

This interface is used by an agent to make a response after receiving the [AgentConf_Ringing_\(Ringing of a Conference Call\)](#).

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has received the [AgentConf_Ringing_\(Ringing of a Conference Call\)](#) event.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/answeragentconf
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/agentconf/1019/answeragentconf HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- [AgentConf_SelfJoinResult_\(Agent Joined a Conference Call\)](#)

NOTE

Other participants receive the [AgentConf_ParticipantChanged_\(Participant Changed\)](#) event.

Error Code

- 000-002
- 100-006
- 100-007
- 101-001

Rejecting a Conference Call

Interface Description

This interface is used by an agent to reject a conference call after receiving the [AgentConf_Ringing \(Ringing of a Conference Call\)](#) event.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has received the [AgentConf_Ringing \(Ringing of a Conference Call\)](#) event.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/rejectagentconf
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/agentconf/1019/rejectagentconf HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- [AgentOther_PhoneRelease \(Phone in On-Hook State\)](#)

NOTE

Other participants receive the [AgentConf_ParticipantChanged \(Participant Changed\)](#) event.

Error Code

- 000-002
- 100-006
- 100-007
- 101-001

Exiting a Conference Call

Interface Description

This interface is used by an agent to exit a conference call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has joined a conference call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/requestleaveagentconf
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/agentconf/1019/requestleaveagentconf HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- [AgentOther_PhoneRelease \(Phone in On-Hook State\)](#)
- [AgentConf_SelfLeaveResult \(Agent Leaved a Conference Call\)](#)

NOTE

Other participants receive the [AgentConf_ParticipantChanged \(Participant Changed\)](#) event.

Error Code

- 000-002
- 100-006
- 100-007

- 101-001

Parent topic: [Conference Call: agentconf](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Releasing a Conference Call

Interface Description

This interface is used by an agent to release the entire conference. The conference chair and all participants are deleted. Only the conference chair has the rights to release a conference.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is a conference chair.
 - The conference call has been successfully applied.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/releaseagentconf
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/agentconf/1019/releaseagentconf HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- [AgentOther_PhoneRelease](#) (Phone in On-Hook State)
- [AgentConf_SelfLeaveResult](#) (Agent Leaved a Conference Call)

Error Code

- 000-002
- 100-006
- 100-007
- 101-001
- 101-002

Placing a Participant on Hold

Interface Description

This interface is used by an agent to hold a participant. Only the conference chair has the rights to hold a participant.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is a conference chair.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/holdparticipant
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
addressType	String	Yes	Indicates the address type. 6 : access code and phone number of an agent 9 : work ID of an agent
address	String	Yes	Indicates the address ID. It supports a maximum of 24 bytes.
playMode	int	Yes	Indicates the announcement mode. 1 : Play the VP beep tone. 2 : Play the specified file tone. 4 : Play the SIG tone. The default value is 1.
voicePath	String	Yes	Indicates the absolute path of the beep tone code or file. It supports a maximum of 127 characters. The file can be a local file of the VP console or a network file that can be accessed by the VP console.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/agentconf/1019/holdparticipant HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000 {"address": "70005", "addressType": "6", "playMode": 1, "voicePath": "66"}</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0" }

Triggered Event

- [AgentConf ParticipantChanged \(Participant Changed\)](#)

Error Code

- 000-002
- 100-006
- 100-007
- 101-001
- 101-002

Parent topic: [Conference Call: agentconf](#)

Unholding a Participant

Interface Description

This interface is used by an agent to unhold a participant on hold. Only the conference chair has the rights to unhold a participant.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is a conference chair.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/unholdparticipant
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
addressType	String	Yes	Indicates the address type. 6 : access code and phone number of an agent 9 : work ID of an agent
address	String	Yes	Indicates the address ID. It supports a maximum of 24 bytes.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/agentconf/1019/unholdparticipant HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"address" : "70005", "addressType" : "6"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- [AgentConf_ParticipantChanged \(Participant Changed\)](#)

Error Code

- 000-002

- 100-006
- 100-007
- 101-001
- 101-002

Parent topic: [Conference Call: agentconf](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Applying for Conference Extension by a Conference Chair

Interface Description

This interface is used by a conference chair to extend conference call duration. The total conference call duration cannot exceed 1440 minutes.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is a conference chair.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/prolongtime?prolongTime={prolongTime}
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
prolongTime	int	Yes	Extended conference duration. The value ranges from 1 to 1440, in minutes.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	See Table 3 .

Table 3 Extended duration

Parameter	Data Type	Description
appliedTime	int	Extended duration. Unit: minute Value range: 1-1440 The duration specified by appliedTime may be shorter than the duration specified by prolongTime because the time specified by prolongTime plus the used conference time may be longer than 1440 minutes.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/agentconf/1019/prolongtime?prolongTime=100 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"appliedTime":50}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007
- 101-001
- 101-002

Parent topic: [Conference Call: agentconf](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Transferring the Conference Chair Rights

Interface Description

This interface is used by a conference chair to transfer the conference chair rights to another agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is a conference chair.
 - The target agent has joined the conference.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/applytoshippresident?destWorkNo={destWorkNo}
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
destWorkNo	int	Yes	Indicates the work ID of the target agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/agentconf/1019/applytoshippresident?destWorkNo=1020 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- [AgentConf_ParticipantChanged \(Participant Changed\)](#).

NOTE

The target agent receives the [AgentConf_PresidentChanged \(Conference Chair Changed\)](#) event.

Error Code

- 000-002
- 100-006

- 100-007
- 101-001
- 101-002

Parent topic: [Conference Call: agentconf](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Batch Inviting Participants

Interface Description

This interface is used by a conference chair to batch invite participants.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is a conference chair.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/batchaddparticipant
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
addresses	array	Yes	Indicates information about batch invited participants. The maximum length is 120 characters. For the parameter description, see Table 2 .
beepTone	boolean	Yes	Indicates whether to play greeting to a user when a user joins a conference call. The default value is false .
playMode	int	No	Indicates the announcement mode. 1 : Play the VP beep tone. 2 : Play the specified file tone. The default value is 1 .
voicePath	String	No	Indicates the absolute path of the beep tone code or file. When beepTone is set to True , this parameter is mandatory. When beepTone is set to False , this parameter is invalid. The file can be a local file of the VP console or a network file that can be accessed by the VP console. It supports a maximum of 127 characters.
caller	String	No	Indicates the calling number. It supports a maximum of 24 characters.

Table 2 Participants

Parameter	Data Type	Mandatory (Yes/No)	Description
addressType	String	Yes	Indicates the address type. 6 : phone number 9 : work ID of an agent 25 : radio trunking group number
address	String	Yes	Indicates the address ID. It supports a maximum of 24 characters.
deviceCallType	int	No	Indicates a user-defined device call type. The default value is 0 . The value range is from 0 to 255 .
deviceType	int	No	Indicates a user-defined device type. The default value is 0 . The value range is from 0 to 255 .
isForDispatch	boolean	No	Indicates integrated incident reception and dispatch. The default value is false . When isForDispatch is set to true , addresses can contain only one participant object. This object is an integrated incident reception and dispatch object. In addition, the beepTone parameter does not take effect. That is, the system does

Parameter	Data Type	Mandatory (Yes/No)	Description
			not play a greeting when an integrated incident reception and dispatch object joins a conference. One conference allows only one integrated incident reception and dispatch object, and the object cannot perform operations such as call hold, announcement playing through channels, and attribute modification.

Response Message

Table 3 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/agentconf/1019/batchaddparticipant HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"addresses":[{"address": "70005", "addressType": "6", "deviceCallType": 1, "deviceType": 66}], "beepTone": true, "playMode": 1, "voicePath": "66", "caller":""}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- [AgentConf_ParticipantChanged \(Participant Changed\)](#)

Error Code

- 000-002
- 100-006
- 100-007
- 101-001
- 101-002

Parent topic: [Conference Call: agentconf](#)

Batch Deleting Participants

Interface Description

This interface is used by a conference chair to delete participants in batches.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is a conference chair.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/batchremoveparticipant
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
addresses	array	Yes	Indicates information about batch deleted participants. The maximum length is 120 characters. For the parameter description, see Table 2 .

Table 2 AgentConfAddressExParam objects

Parameter	Data Type	Mandatory (Yes/No)	Description
addressType	String	Yes	Indicates the address type. 6 : phone number 9 : work ID of an agent 25 : radio trunking group number
address	String	Yes	Indicates the address ID. It supports a maximum of 24 characters.

Response Message

Table 3 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	See Table 4 .

Table 4 List of non-existed participants

Parameter	Data Type	Description
noExistParticipants	array	See Table 5 .

Table 5 Parameter description of participants

Parameter	Data Type	Description
addressType	string	Indicates the address type.
address	string	Indicates the address ID.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/agentconf/1019/batchremoveparticipant HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"addresses":[{"address" : "70005", "addressType" : "6"}]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0", "result": {"noExistParticipants": [{"addressType": 6, "address": "70005"}]}}</pre>

Triggered Event

- [AgentConf_ParticipantChanged \(Participant Changed\)](#)

Error Code

- 000-002
- 100-006
- 100-007
- 101-001
- 101-002

Parent topic: [Conference Call: agentconf](#)

Modifying a Participant Attribute

Interface Description

This interface is used by a conference chair to modify the channel attribute of a participant. Only the conference chair has the rights to modify the channel attribute of a participant.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is a conference chair.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/changeparticipantmode
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
attribute	int	Yes	Indicates the attribute of a participant. 1: A participant can only listen to the conference call instead of making a speech. 2: A participant can only make a speech instead of listening to the conference call. 3: A participant can both listen to the conference call and make a speech. 4: A participant cannot listen to the conference call or make a speech.
addressType	String	Yes	Indicates the address type. 6: phone number 9: work ID of an agent
address	String	Yes	Indicates the address ID. It supports a maximum of 24 bytes.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/agentconf/1019/changeparticipantmode HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"attribute" : 1, "address" : "70005", "addressType" : "6"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- If a participant attribute value is changed to **1** or **3**, the agent receives the following event:

[AgentConf_ParticipantChanged \(Participant Changed\)](#)

- If a participant attribute value is changed to **2** or **4**, the agent does not receive any event.

Error Code

- 000-002
- 100-006
- 100-007
- 101-001
- 101-002

Parent topic: [Conference Call: agentconf](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Playing Announcement for a Conference Call

Interface Description

This interface is used by a conference chair to play announcement for a conference call. Only the conference chair has the rights to play announcement for conference calls.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is a conference chair.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/playvoicetoconf
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
playType	int	Yes	Indicates the announcement type. 0 : Play the conference foreground music. 1 : Play the conference background music.
playMode	int	Yes	Indicates the announcement mode. 1 : Play the VP beep tone. 2 : Play the specified file tone. 4 : Play the SIG tone.
voicePath	String	Yes	Indicates the absolute path of the beep tone code or file. The file can be a local file of the VP console or a network file that can be accessed by the VP console. It supports a maximum of 127 characters.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	This parameter is returned only when the call fails. For the parameter description of result, see Table 3 .

Table 3 Announcement failure causes

Parameter	Data Type	Description
errorReason	int	Indicates the transparently transmitted failure cause code returned by the automatic call distributor when the announcement fails.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre> PUT /agentgateway/resource/agentconf/1019/playvoicetoconf HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"playType" : 0, "playMode" : 1, "voicePath" : "66"}</pre>
Example of a response packet	<pre> HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "General Error", "retcode": "100-007", "result": {"errorReason": 1}}</pre>

Triggered Event

- [AgentConf_StopVoice \(Conference Announcement Ended\)](#)

Error Code

- 000-002
- 100-006
- 100-007
- 101-001
- 101-002

Parent topic: [Conference Call: agentconf](#)

Stopping Announcement for a Conference Call

Interface Description

This interface is used by a conference chair to stop announcement for a conference call. Only the conference chair has the rights to stop announcement for conference calls.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is a conference chair.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/stopvoicetoconf
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	This parameter is returned only when the call fails. For the parameter description of result , see Table 3 .

Table 3 Announcement stopping failure causes

Parameter	Data Type	Description
errorReason	int	Indicates the transparently transmitted failure cause code returned by the automatic call distributor when the announcement fails to be stopped.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/agentconf/1019/stopvoicetoconf HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "\\byte-sequence\\ isn't right.", "retcode": "100-007", "result": {"errorReason": 21248}}</pre>

Triggered Event

None

Error Code

- 000-002

- 100-006
- 100-007
- 101-001
- 101-002

Parent topic: [Conference Call: agentconf](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Playing Announcement for a Conference Call Channel

Interface Description

This interface is used by a conference chair to play announcement for a conference call channel. Only the conference chair has the rights to play announcement for conference call channels.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is a conference chair.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/playvoicetoparticipant
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
addressType	String	Yes	Indicates the address type. 6: phone number 9: work ID of an agent
address	String	Yes	Indicates the address ID. It supports a maximum of 24 bytes.
playMode	int	Yes	Indicates the announcement mode. 1: Play the VP beep tone. 2: Play the specified file tone. 4: Play the SIG tone. The default value is 1.
voicePath	voicePath	Yes	Indicates the absolute path of the beep tone code or file. It supports a maximum of 127 characters. The file can be a local file of the VP console or a network file that can be accessed by the VP console.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	This parameter is returned only when the call fails. For the parameter description of result, see Table 3 .

Table 3 Announcement failure causes

Parameter	Data Type	Description
errorReason	int	Indicates the transparently transmitted failure cause code returned by the automatic call distributor when the announcement fails.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/agentconf/1019/playvoicetoparticipant HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"addressType" : "6", "address" : "70005", "playMode" : 1, "voicePath" : "66"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "General Error", "retcode": "100-007", "result": {"errorReason": 1}}</pre>

Triggered Event

- [AgentConf_StopParticipantVoice \(Conference Channel Announcement Ended\)](#)

Error Code

- 000-002
- 100-006
- 100-007
- 101-001
- 101-002

Parent topic: [Conference Call: agentconf](#)

Stopping Playing Announcement for a Conference Call Channel

Interface Description

This interface is used by a conference chair to stop playing announcement for a conference call channel. Only the conference chair has the rights to stop playing announcement for conference call channels.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is a conference chair.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/stopvoicetoparticipant
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
addressType	String	Yes	Indicates the address type. 6 : phone number 9 : work ID of an agent
address	String	Yes	Indicates the address ID. It supports a maximum of 24 bytes.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	This parameter is returned only when the call fails. For the parameter description of result , see Table 3 .

Table 3 Announcement stopping failure causes

Parameter	Data Type	Description
errorReason	int	Indicates the transparently transmitted failure cause code returned by the automatic call distributor when the announcement fails to be stopped.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/agentconf/1019/stopvoicetoparticipant HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"addressType": "6", "address": "70005"}</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "\"byte-sequence\" isn't right.", "retcode": "100-007", "result": { "errorReason": "21248" } }

Triggered Event

None

Error Code

- 000-002
- 100-006
- 100-007
- 101-001
- 101-002

Parent topic: [Conference Call: agentconf](#)

Changing the Number of Conference Participants

Interface Description

This interface is used to change the number of conference participants.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/modifyconfresource
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
modifyType	int	Yes	Indicates the type of a change application. 0 : Increase 1 : Reduce The default value is 0 .
modifyNum	int	Yes	Indicates the number to be changed. The value range is from 2 to 118 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/agentconf/1019/modifyconfresource HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"modifyType": 0, "modifyNum": 118}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

None

Error Code

- 000-002

- 100-006
- 100-007
- 101-001
- 101-002

Parent topic: [Conference Call: agentconf](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Batch Querying Conference Information

Interface Description

This interface is used to batch query conference information.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/queryconfinfos
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
confIds	array	Yes	Indicates the list of conference IDs. The maximum length is 20 characters.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	array	See Table 3 .

Table 3 Conference information

Parameter	Data Type	Description
confId	long	Indicates the conference ID.
confState	int	Indicates the conference status. 0 : normal conference call 1 : announcement of a conference site
startTime	long	Indicates the conference start time (timestamp, in milliseconds).
applyConfTime	int	Indicates the applied duration of a conference. The unit is minutes.
confHaveBeenTime	int	Indicates the elapsed time of a conference, in minutes.
addresses	array	Indicates the list of participants. For details, see Table 4 .

Table 4 Participant information

Parameter	Data Type	Description
-----------	-----------	-------------

Parameter	Data Type	Description
addressType	String	Indicates the address type. 6 : phone number 9 : work ID of an agent
address	String	Indicates the address ID.
deviceCallType	int	Indicates a user-defined device call type.
deviceType	int	Indicates a user-defined device type.
channelAttrib	int	Indicates a conference attribute. 1 : Listen only 2 : Speak only 3 : Listen and speak
channelState	int	Indicates the conference channel state. 0 : in a normal conference call 1 : placed on hold 2 : announcement
role	int	Indicates a conference role. 0 : participant 1 : conference chair
enterTime	long	Indicates the time when a participant joins a conference (timestamp, in milliseconds).
confHaveBeenTime	int	Indicates the elapsed time of a conference, in minutes.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/agentconf/1019/queryconfinfos HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"confIds" : [1029888,1029889]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"confs":[{"confId":1029888,"confState":0,"startTime":1475745454000,"applyConfTime":60,"confHaveBeenTime":29, "addresses":[{"addressType":"6","address":"70005","deviceCallType":0,"deviceType":0,"channelAttrib":3,"channelState":0, "role":0,"enterTime":1475745464000},{addressType":"9","address":"153","deviceCallType":0,"deviceType":6,"channelAttrib":3, "channelState":0,"role":1,"enterTime":1475745454000}]}]}</pre>

Triggered Event

None

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Conference Call: agentconf](#)

Querying a Call ID of a Participant

Interface Description

This interface is used to query the call ID of a participant in a conference call.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/querycallidonparticipant
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
confId	long	Yes	Indicates the conference ID.
addressType	String	Yes	Indicates the address type. 6 : phone number 9 : work ID of an agent
address	String	Yes	Indicates the address ID. It supports a maximum of 24 bytes.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	See Table 3 .

Table 3 Call ID information

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/agentconf/1019/querycallidonparticipant HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000 {"confId" : "1029888", "address" : "70005", "addressType" : "6"}</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "callId": "1475745462-63" } }

Triggered Event

None

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Conference Call: agentconf](#)

Querying the Conference ID of an Ongoing Conference Call on the VDN

Interface Description

This interface is used to query the conference id of an ongoing conference call on the VDN.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentconf/{agentid}/queryallconfids
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	See Table 3 .

Table 3 List of conference IDs

Parameter	Data Type	Description
confids	array	Indicates the list of conference IDs.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentconf/1019/queryallconfids HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"confIds":[1029888]}}</pre>

Triggered Event

None

Error Code

- 000-002
- 100-006
- 100-007

Emailcall: emailcall

[Answering a Call](#)

[Ending a Call](#)

[Replying to an Email Call](#)

[Sending an Email](#)

[Querying the Email Configuration of an Agent](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Answering a Call

Interface Description

This interface is used by an agent to answer a call when receiving the [AgentMail_Ringing_\(Ringling of an Email Call\)](#) event. The email call does not support call rejection. It is recommended that the agent invoke this interface to automatically answer a call after receiving the [AgentMail_Ringing_\(Ringling of an Email Call\)](#) event in secondary development.

Usage Description

- Prerequisites
 - The agent has logged in.
 - The agent has been configured with an email skill queue.
 - The agent has signed in the MailM server.
- Precautions
 - None
- Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/emailcall/{agentid}/answer?callId={callId}
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
callId	long	Yes	Indicates the ID of an email call to be answered.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/emailcall/1019/answer?callId=1456401416-3 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- After an email call is successfully answered, the agent receives the following events:

[AgentMail_Connected_\(Email Call Setup\)](#)

[AgentMail_Received_\(Email Received\)](#)

- If an email call is not answered for a long period of time, the agent receives the following event:

[AgentMail_NoAnswer_\(No Answer to an Email Call\)](#)

Error Code

- 100-006
- 100-007
- 200-026

Parent topic: [Emailcall: emailcall](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Ending a Call

Interface Description

This interface is used by an agent to end an email call after receiving the [AgentMail_Connected \(Email Call Setup\)](#) event if the agent has replied to the email or is not willing to reply to the email.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The email call has been established.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/emailcall/{agentid}/drop?callId={callId}
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
callId	long	Yes	Indicates the ID of an email call to be ended.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/emailcall/1019/drop?callId=1456401416-3 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- [AgentMail_Disconnected \(Email Call Released\)](#)

Error Code

- 100-006
- 100-007
- 200-026

Parent topic: [Emailcall: emailcall](#)

Replying to an Email Call

Interface Description

This interface is used by an agent to reply to an email call after receiving the [AgentMail_Received \(Email Received\)](#) event. If the agent does not reply to the email call for a long period of time, the agent receives the [AgentMail_Remind \(Email Reminder\)](#) event that reminds the agent to reply to the email call.

Usage Description

- Prerequisites
 - The agent has logged in.
- Precautions
 - None
- Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/emailcall/{agentid}/replymail?callId={callId}
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
callId	long	Yes	Indicates the ID of an email call to be replied.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/emailcall/1019/replymail?callId=1456401416-3 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

None

Error Code

- 100-006
- 100-007
- 200-026

Parent topic: [Emailcall: emailcall](#)

Sending an Email

Interface Description

This interface is used by an agent to proactively send an email.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has signed in the MailM server.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/emailcall/{agentid}/sendmail
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
skillId	int	Yes	Indicates the skill ID of an outbound email.
mailIndex	int	Yes	Indicates the index of an outbound email.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	See Table 3 .

Table 3 Call information

Parameter	Data Type	Description
callId	string	Indicates the ID of an email call.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/emailcall/1019/sendmail HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"skillId": 4, "mailIndex": 121}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"callId":"1476412139-33554747"}}</pre>

Triggered Event

- After an outbound email is successfully sent, the agent receives the following events:

[AgentMail_Connected \(Email Call Setup\)](#)

[AgentMail_Disconnected \(Email Call Released\)](#)

- After an outbound email fails to be sent, the agent receives the following event:

[AgentMail_CallOutFailed \(Outgoing Email Failed\)](#)

Error Code

- 100-006
- 100-007

Parent topic: [Emailcall: emailcall](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying the Email Configuration of an Agent

Interface Description

This interface is used to query the email configuration of an agent.



WARNING

The login password of a private mailbox configured by an agent is returned using this interface. Therefore, there are security risks, and you need to use this interface with caution in secondary development.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/emailcall/{agentid}/getmailcfg
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	See Table 3 .

Table 3 Mailbox information

Parameter	Data Type	Description
pop3Server	string	Indicates the POP3 information of a mailbox.
smtpServer	string	Indicates the SMTP information of a mailbox.
recvEmailAddr	string	Indicates the private email address used by an agent to receive emails.
sendEmailAddr	string	Indicates the private email address used by an agent to send emails.
recvEmailUserName	string	Indicates the user name of a private email used by an agent to receive emails.
recvEmailPassword	string	Indicates the password of a private email used by an agent to receive emails.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/emailcall/1019/getmailcfg HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1</pre>

Example Type	Reference Format
	Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "pop3Server": "10.177.120.247:SSL1:SPA0", "smtpServer": "10.177.120.247:SSL1:SPA0", "recvEmailAddr": "receiver@cc.com", "sendEmailAddr": "sender@cc.com", "recvEmailUserName": "receiver", "recvEmailPassword": "Huawei@123" } }

Triggered Event

None

Error Code

- 100-006
- 100-007

Parent topic: [Emailcall: emailcall](#)

ECC Interfaces: eccconfig

NOTE

ECC interfaces apply only to the ICP scenario. They are internal interfaces of the ICP SDK and cannot be used in the IPCC scenario.

- [Adding a Phone Number to the Blacklist](#)
- [Querying a Phone Number in the Blacklist](#)
- [Querying All Phone Numbers in the Blacklist](#)
- [Deleting a Phone Number from the Blacklist](#)
- [Deleting All Phone Numbers from the Blacklist](#)
- [Reading Configuration Information Based on configId](#)
- [Adding a Phone Number to the Redlist](#)
- [Querying a Phone Number in the Redlist](#)
- [Querying All Phone Numbers in the Redlist](#)
- [Deleting a Phone Number from the Redlist](#)
- [Deleting All Phone Numbers from the Redlist](#)
- [Querying the Number of Abandoned Calls](#)
- [Querying Abandoned Call Records](#)
- [Querying Prank Call Records](#)

Parent topic: [Interfaces](#)

Adding a Phone Number to the Blacklist

Interface Description

This interface is used by an agent to add a phone number to the blacklist after sign-in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/blacklist
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
phoneNumber	string	Yes	Indicates the phone number. The value contains a maximum of 24 characters, including digits and the following special characters: * # - /
lockTime	long	Yes	Indicates the duration for locking a phone number. The value ranges from 5 to 999999999, in seconds.
filterMode	string	Yes	Indicates the blacklist mode. 1: rejection 2: downgrade Only the preceding two options are available.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/eccconfig/1019/blacklist HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"phoneNumber":"6676766","lockTime":"5","filterMode":"2"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 103-001
- 103-002

Parent topic: [ECC Interfaces: eccconfig](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying a Phone Number in the Blacklist

Interface Description

This interface is used by an agent to query a phone number in the blacklist after login.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/blacklist?phoneNumber={phoneNumber}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
phoneNumber	string	Yes	Indicates the phone number. The value contains a maximum of 24 characters, including digits and the following special characters: * # - /
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
id	string	Reserved.
phoneNumber	string	Indicates a phone number.
filterMode	string	Indicates the blacklist mode. 1: rejection 2: downgrade
createdBy	string	Indicates the work ID of the creator.
createDate	long	Indicates the creation time (timestamp, in milliseconds).
duration	long	Indicates the locking duration, in seconds.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/eccconfig/1019/blacklist?phoneNumber=110 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1</pre>

Example Type	Reference Format
	Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{ "id": null, "phoneNumber": "123456", "filterMode": 2, "createdBy": "49001", "createDate": 1501084329000, "duration": 5 }] }

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 103-004

Parent topic: [ECC Interfaces: eccconfig](#)

Querying All Phone Numbers in the Blacklist

Prerequisites

- The agent has logged in.

Interface Description

This interface is used by an agent to query all phone numbers in the blacklist to check whether the blacklist contains invalid data after login.

Usage Description

- Prerequisites
 - The agent has logged in.
- Precautions
None
- Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/allblacklist?isContainInvalid={isContainInvalid}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
isContainInvalid	boolean	Yes	Indicates whether the blacklist contains invalid data (the value is true or false).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
result	list	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
id	string	Reserved.
phoneNumber	string	Indicates a phone number.
filterMode	string	Indicates the blacklist mode. 1 : rejection 2 : downgrade
createdBy	string	Indicates the work ID of the creator.
createDate	long	Indicates the creation time (timestamp, in milliseconds).
duration	long	Indicates the locking duration, in seconds.

Interface Example

Example Type	Reference Format
Example of a request packet	<code>GET /agentgateway/resource/ecccconfig/1019/allblacklist?isContainInvalid=true HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</code>
Example of a response packet	<code>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{ "id": null, "phoneNumber": "123456", "filterMode": 2, "createdBy": "49001", "createDate": 1501084329000, "duration": 5 }] }</code>

Triggered Event

- None

Error Code

- 100-006
- 103-004

Parent topic: [ECC Interfaces: eccconfig](#)

Deleting a Phone Number from the Blacklist

Interface Description

This interface is used by an agent to delete a phone number from the blacklist after login.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/blacklist?phoneNumber={phoneNumber}
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
phoneNumber	string	Yes	Indicates the phone number. The value contains a maximum of 24 characters, including digits and the following special characters: * # - /
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/eccconfig/1019/blacklist?phoneNumber=110 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result": {}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 200-026

Parent topic: [ECC Interfaces: eccconfig](#)

Deleting All Phone Numbers from the Blacklist

Interface Description

This interface is used by an agent to delete all phone numbers from the blacklist after login.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/allblacklist
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/eccconfig/1019/allblacklist HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- None

Error Code

- 100-006
- 103-006

Parent topic: [ECC Interfaces: eccconfig](#)

Reading Configuration Information Based on configId

Interface Description

This interface is used by an agent to read configuration information based on **configId**.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/config?configId={configId}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
configId	string	Yes	Indicates the name of a configuration item (the value contains a maximum of 36 characters and cannot be empty).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
configvalue	int	Indicates the configuration information.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/eccconfig/1019/config?configId= HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"configvalue":49001}]}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 103-020

Parent topic: [ECC Interfaces: eccconfig](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Adding a Phone Number to the Redlist

Interface Description

This interface is used by an agent to add a phone number to the redlist after sign-in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/redlist
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
phoneNumber	string	Yes	Indicates the phone number. The value contains a maximum of 24 characters, including digits and the following special characters: * # - /
custLevel	long	Yes	Indicates the priority. The value ranges from 1 to 14.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/eccconfig/1019/redlist HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"phoneNumber":"13145","custLevel":"5"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006

- 103-007
- 103-008

Parent topic: [ECC Interfaces: eccconfig](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying a Phone Number in the Redlist

Interface Description

This interface is used by an agent to query a phone number in the redlist after sign-in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/redlist?phoneNumber={phoneNumber}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
phoneNumber	string	Yes	Indicates the phone number. The value contains a maximum of 24 characters, including digits and the following special characters: * # - /
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
phoneNumber	string	Indicates a phone number.
custLevel	string	Indicates the priority.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/eccconfig/1019/redlist?phoneNumber=110 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"phoneNumber":"123456","custLevel":5}]}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 103-010

Parent topic: [ECC Interfaces: eccconfig](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying All Phone Numbers in the Redlist

Interface Description

This interface is used by an agent to query all phone numbers in the redlist after login.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/allredlist
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
phoneNumber	string	Indicates a phone number.
custLevel	string	Indicates the priority.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/eccconfig/1019/allredlist HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"phoneNumber":"123456","custLevel":5},{ "phoneNumber":"13145","custLevel":1}]}</pre>

Triggered Event

- None

Error Code

- 100-006
- 103-009

Deleting a Phone Number from the Redlist

Interface Description

This interface is used by an agent to delete a phone number from the redlist after sign-in.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/redlist?phoneNumber={phoneNumber}
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
phoneNumber	string	Yes	Indicates the phone number. The value contains a maximum of 24 characters, including digits and the following special characters: * # - /
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/eccconfig/1019/redlist?phoneNumber=1010 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 103-013

Parent topic: [ECC Interfaces: eccconfig](#)

Deleting All Phone Numbers from the Redlist

Interface Description

This interface is used by an agent to delete all phone numbers from the redlist after login.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/allredlist
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/eccconfig/1019/allredlist HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

- None

Error Code

- 100-006
- 103-012

Parent topic: [ECC Interfaces: eccconfig](#)

Querying the Number of Abandoned Calls

Interface Description

This interface is used by an agent to query the number of abandoned calls after login. Only data in the recent week can be queried.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/lostcallscount?beginLostTime={beginLostTime}&endLostTime={endLostTime}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
beginLostTime	string	Yes	Indicates the query start time. The time is in the yyyy-MM-dd HH:mm:ss format and cannot be empty.
endLostTime	string	Yes	Indicates the query end time. The time is in the yyyy-MM-dd HH:mm:ss format and cannot be empty.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	int	Indicates the number of abandoned calls.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/eccconfig/1019/lostcallscount?beginLostTime=2017-12-20 15:30:00&endLostTime=2017-12-20 15:35:00 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":0}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 103-021

Parent topic: [ECC Interfaces: eccconfig](#)

Querying Abandoned Call Records

Interface Description

This interface is used by an agent to query abandoned call records after sign-in. Only data in the recent week can be queried.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/lostcalls?startPosition={startPosition}&endPosition={endPosition}&beginLostTime={beginLostTime}&endLostTime={endLostTime}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
startPosition	int	Yes	Indicates the start position.
endPosition	int	Yes	Indicates the end position. The difference between the start position and the end position is the records to be queried.
beginLostTime	string	Yes	Indicates the query start time. The time is in the yyyy-MM-dd HH:mm:ss format and cannot be empty.
endLostTime	string	Yes	Indicates the query end time. The time is in the yyyy-MM-dd HH:mm:ss format and cannot be empty.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.
caller	string	Indicates the calling party.
callee	string	Indicates the called party.
beginTime	long	Indicates the call start time (timestamp, in milliseconds).
lostTime	long	Indicates the call release time (timestamp, in milliseconds).

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/ecccconfig/1019/lostcalls?startPosition=1&endPosition=2&beginLostTime=2017-12-20 15:30:00&endLostTime=2017-12-20 15:35:00 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"callId":"1505876960-15","caller":"70943","callee":"610412","beginTime":1505877001000,"lostTime":1505877001000}]}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 103-022

Parent topic: [ECC Interfaces: ecccconfig](#)

Querying Prank Call Records

Interface Description

This interface is used by an agent to query prank call records based on the phone number.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/maliciouscalls?phoneNumber={phoneNumber}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
phoneNumber	string	Yes	Indicates the phone number. The value contains a maximum of 24 characters, including digits and the following special characters: * # - /
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.
caller	string	Indicates the calling party.
callee	string	Indicates the called party.
callTime	long	Indicates the call start time (timestamp, in milliseconds).

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/eccconfig/1019/maliciouscalls?phoneNumber=110 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"callId":"1505875507-9","caller":"70942","callee":"610412","callTime":1505875548000}]}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 103-023

Parent topic: [ECC Interfaces: eccconfig](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Third-Party Control: thirdcontrol

[Instructing an Agent to Make an Outbound Call](#)

[Instructing an Agent to Answer a Call](#)

[Instructing an Agent to Set the Status](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Instructing an Agent to Make an Outbound Call

Interface Description

A third-party server initiates an outbound calling request to a specified agent through the bridge interface.

Usage Description

1. Prerequisites
 - The bridge account has logged in and has the inspection right.
2. Precautions
 - Successful bridge interface invoking only indicates that the request is sent successfully. You can check whether the operation is finally successful on the ICP SDK client.
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/thirdcontrol/{agentid}/callout/{destagentid}
Request Method	PUT

Request Message

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
destagentid	int	Yes	Indicates the work ID of the target agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
caller	string	No	Indicates the calling number. The value is a number of 0-24 digits. This parameter can be left empty. If it is empty, the default calling number of the platform is used.
called	string	Yes	Indicates the called number. This parameter is mandatory. It contains 1 to 24 digits and special characters * or #.
skillid	int	No	Indicates the ID of a skill. The value is a number and can be left empty. When the parameter is left empty, the default skill ID configured on the platform is used.
callappdata	string	Yes	Indicates the channel-associated data. The value contains a maximum of 512 characters.
mediaability	int	No	Indicates the media capability. The default value is 0. The options are as follows: 0: voice; 1: video; 2: default capability, negotiated by the agent's and user's phones

Response Message

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/thirdcontrol/135/callout/140 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json Host: 192.168.0.0:8000 {"caller":"40038","called":"111111","skillid":25,"callappdata":"111111111111","mediaability":1}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

After this interface is invoked, the call event will be triggered and sent to the specified agent.

Error Code

- 100-006: The current agent does not log in.
- 100-018: The target agent does not log in.
- 000-003: No right to invoke this interface. The inspection right is required.

Parent topic: [Third-Party Control: thirdcontrol](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Instructing an Agent to Answer a Call

Interface Description

A third-party server initiates a call answering request to a specified agent through the bridge interface.

Usage Description

1. Prerequisites
 - The bridge account has logged in and has the inspection right.
2. Precautions
 - Successful bridge interface invoking only indicates that the request is sent successfully. You can check whether the operation is finally successful on the ICP SDK client.
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/thirdcontrol/{agentid}/callanswer/{destagentid}
Request Method	PUT

Request Message

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of the current agent.
destagentid	int	Yes	Indicates the work ID of the target agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/thirdcontrol/110/callanswer/107 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

After this interface is invoked, the call answer event will be triggered.

Error Code

- 100-006: The current agent does not log in.
- 100-018: The target agent does not log in.
- 000-003: No right to invoke this interface. The inspection right is required.

Parent topic: [Third-Party Control: thirdcontrol](#)

Instructing an Agent to Set the Status

Interface Description

A third-party server initiates a status setting request to a specified agent through the bridge interface.

Usage Description

1. Prerequisites
 - The bridge account has logged in and has the inspection right.
2. Precautions
 - Successful bridge interface invoking only indicates that the request is sent successfully. You can check whether the operation is finally successful on the ICP SDK client.
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/thirdcontrol/{agentid}/setstatus/{destagentid}
Request Method	PUT

Request Message

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of the current agent.
destagentid	int	Yes	Indicates the work ID of the target agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
agentStatus	string	Yes	Indicates the agent status. 1. AgentState_Idle 2. AgentState_Busy

Response Message

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/thirdcontrol/110/setstatus/107 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":{}}</pre>

Triggered Event

After this interface is invoked, the status setting event will be triggered.

Error Code

- 100-006: The current agent does not log in.
- 100-018: The target agent does not log in.
- 000-003: No right to invoke this interface. The inspection right is required.

Events

[Events Related to Agent States](#)

[Events Related to Voice Call](#)

[Events Related to Outgoing Call](#)

[Events Related to Recording Playback](#)

[Events Related to Text Chat](#)

[Events Related to Real-time Quality Control](#)

[Events Related to RMS](#)

[Events Related to Physical Phone](#)

[Events Related to Multimedia Conference](#)

[Events Related to Phone Linkage](#)

[Conference Call Events](#)

[Email Events](#)

[Other Agent-Related Events](#)

Parent topic: [Basic Interfaces and Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Events Related to Agent States

[AgentState_Busy](#) (Talking)
[AgentState_Work](#) (Working)
[AgentState_Ready](#) (Idle)
[AgentState_SetNotReady_Success](#) (Indicating [Busy](#) Successfully)
[AgentState_CancelNotReady_Success](#) (Quitting the [Busy State](#) Successfully)
[AgentState_Force_SetNotReady](#) (Forcing To Enter the [Busy State](#) Successfully)
[AgentState_SetRest_Success](#) (Requesting [Rest](#) Successfully)
[AgentState_CancelRest_Success](#) (Quitting the [Resting State](#) Successfully)
[AgentState_Rest_Timeout](#) (Rest Timeout Reminder)
[AgentState_SetWork_Success](#) (Turning to the [Working State](#))
[AgentState_CancelWork_Success](#) (Quitting the [Working State](#))

Parent topic: [Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

AgentState_Busy (Talking)

Event Description

This event indicates that an agent is making a call.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"AgentState_Busy","workNo":"1010","content":null}}</pre>

Parent topic: [Events Related to Agent States](#)

AgentState_Work (Working)

Event Description

This event indicates that an agent enters the work state.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"AgentState_Work","workNo":"1010","content":null}}</pre>

Parent topic: [Events Related to Agent States](#)

AgentState_Ready (Idle)

Event Description

This event indicates that an agent becomes idle.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentState_Ready","workNo":"49997","content":null}}</pre>
----------------------------	--

Parent topic: [Events Related to Agent States](#)

AgentState_SetNotReady_Success (Indicating Busy Successfully)

Event Description

This event indicates that an agent enters the busy state successfully.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentState_SetNotReady_Success","workNo":"49997","content":null}}</pre>
----------------------------	--

Parent topic: [Events Related to Agent States](#)

AgentState_CancelNotReady_Success (Quitting the Busy State Successfully)

Event Description

This event indicates that an agent quits the busy state successfully.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentState_CancelNotReady_Success", "workNo": "49997", "content": null}}</pre>
----------------------------	--

Parent topic: [Events Related to Agent States](#)

AgentState_Force_SetNotReady (Forcing To Enter the Busy State Successfully)

Event Description

This event indicates that an agent is forced to enter the busy state successfully.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentState_Force_SetNotReady","workNo":"49997","content":null}}</pre>
----------------------------	--

Parent topic: [Events Related to Agent States](#)

AgentState_SetRest_Success (Requesting Rest Successfully)

Event Description

This event indicates that an agent's rest request is approved.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentState_SetRest_Success","workNo":"49997","content":null}}</pre>
----------------------------	--

Parent topic: [Events Related to Agent States](#)

AgentState_CancelRest_Success (Quitting the Resting State Successfully)

Event Description

This event indicates that an agent quits the resting state successfully.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentState_CancelRest_Success","workNo":"49997","content":null}}</pre>
----------------------------	---

Parent topic: [Events Related to Agent States](#)

AgentState_Rest_Timeout (Rest Timeout Reminder)

Event Description

This event indicates that the system notifies the agent that rest times out. (This event does not indicate that the agent exits theReststate.)

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentState_Rest_Timeout","workNo":"49997","content":null}}</pre>
----------------------------	---

Parent topic: [Events Related to Agent States](#)

AgentState_SetWork_Success (Turning to the Working State)

Event Description

This event indicates that an agent successfully requests to turn to the Working state.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentState_SetWork_Success","workNo":"49997","content":null}}</pre>
----------------------------	--

Parent topic: [Events Related to Agent States](#)

AgentState_CancelWork_Success (Quitting the Working State)

Event Description

This event indicates that an agent successfully requests to quit the Working state.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentState_CancelWork_Success","workNo":"49997","content":null}}</pre>
----------------------------	---

Parent topic: [Events Related to Agent States](#)

Events Related to Voice Call

[AgentEvent_Talking](#) (Turning to the Talking State)
[AgentEvent_Dialing](#) (Turning to Dialing State (for SAP))
[AgentEvent_Customer_Alerting](#) (Customer Ringing)
[AgentEvent_Hold](#) (Holding a Call Successfully)
[AgentEvent_Conference](#) (Entering Three-Party Conversation Successfully)
[AgentEvent_Call_Out_Fail](#) (Making an Outgoing Call Unsuccessfully)
[AgentEvent_Inside_Call_Fail](#) (Making an Internal Call Unsuccessfully)
[AgentEvent_No_Answer](#) (No Answer from an Agent for a Long Time)
[AgentEvent_Call_Release](#) (Agent Exiting a Call)
[AgentEvent_Customer_Release](#) (User Exiting a Call)
[AgentEvent_Auto_Answer](#) (Automatic Answering a Call)
[AgentEvent_Ringing](#) (Incoming Call Reminder)
[AgentEvent_Connect_Fail](#) (Failure to Connect to an Agent)
[AgentEvent_Consult_Fail](#) (Failure to Ask for Help)
[AgentEvent_SipInfo](#) (Receiving a SipInfo Message)
[AgentEvent_AbandonCall](#) (Notifying an Abandoned Call)
[AgentEvent_SuccTransResult](#) (Notifying the Success Transfer Result)
[AgentEvent_ReleaseRequest](#) (Request Release Events)
[AgentEvent_ReleaseResponse](#) (Response to Releasing A Call)
[AgentEvent_No_Answer_From_Cti](#) (No Reply From an Agent for a Long Time)
[AgentEvent_Incoming_CallInfo](#) (Incoming Call Notification Event)
[AgentEvent_TransOutResult](#) (Notifying the Transfer-Out Result)
[AgentEvent_Asr_Notify](#) (Real-Time Speech-to-Text Notification)
[OUTBOUND_DETECT_EVENT](#) (Outgoing Call Event with a Failure Cause Code)
[AgentEvent_Third_Control](#) (Third-Party Control Event)
[AgentEvent_Inside_Call_Queue_Fail](#) (Transferring a call to a skill queue fails)

Parent topic: [Events](#)

AgentEvent_Talking (Turning to the Talking State)

Event Description

This event indicates that the voice call of an agent enters the talking state.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
called	string	Indicates the called number.
caller	string	Indicates the calling number.
callid	string	Indicates the unique call ID.
type	string	Indicates the media type of a call, either an assistant call or a main call.
feature	string	Indicates the type of a call. See Table 1 .
mediaAbility	string	Indicates the media capability, where 1 indicates audio, 2 indicates video, and 3 indicates audio and video.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_Talking", "workNo": "49999", "content": {"caller": "10086", "callid": "1456401416-3", "called": "70092", "feature": "7", "type": "main", "mediaAbility": "1"}}</pre>
----------------------------	--

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Dialing (Turning to Dialing State (for SAP))

Event Description

This event indicates that an agent enters the dialing state.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callid	string	Indicates the unique call ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_Dialing", "workNo": "49999", "content": {"callid": "1456401416-4"}}</pre>
----------------------------	--

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Customer_Alerting (Customer Ringing)

Event Description

This event indicates that the phone of the customer associated with the agent is ringing.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
otherPhoneWorkno	string	Indicates the work ID of the agent whose phone is ringing.
otherPhone	string	Indicates the phone number of the party who phone is ringing or the work ID of the agent whose phone is ringing.
callid	string	Indicates the unique call ID.
type	string	Indicates the media type of a call, either an assistant call or a main call.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_Customer_Alerting","workNo":"49999","content":{"callid":"1456401416-3","otherPhoneWorkno":"","otherPhone":"70092","type":"main"}}</pre>
----------------------------	---

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Hold (Holding a Call Successfully)

Event Description

This event indicates that an agent holds a call successfully.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the unique call ID (CallId).

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_Hold", "workNo": "49999", "content": "1456402370-7"}}</pre>
----------------------------	--

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Conference (Entering Three-Party Conversation Successfully)

Event Description

This event indicates that the agent enters three-party conversation successfully.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail.
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
partner	string	Indicates the work ID or phone number of an agent.
callid	string	Indicates the unique call ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_Conference", "workNo": "49999", "content": {"callid": "1456403570-17", "partner": "49997,70093"}}</pre>
----------------------------	---

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Call_Out_Fail (Making an Outgoing Call Unsuccessfully)

Event Description

This event indicates that the agent's outgoing call fails. This may occur when the called number is incorrect.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the unique call ID (CallId).

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_Call_Out_Fail", "workNo": "49999", "content": "1456402370-7"}}</pre>
----------------------------	---

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Inside_Call_Fail (Making an Internal Call Unsuccessfully)

Event Description

This event indicates that the internal call initiated by the agent fails.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the unique call ID (CallId).

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_Inside_Call_Fail","workNo":"49999","content":{"1456402370-7"}}</pre>
----------------------------	--

Parent topic: [Events Related to Voice Call](#)

AgentEvent_No_Answer (No Answer from an Agent for a Long Time)

Event Description

This event indicates that the agent does not answer a call for a long time and the system notifies the agent that the call is hung up.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the unique call ID (CallId).

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_No_Answer", "workNo": "49999", "content": "1456402370-7"}}</pre>
----------------------------	---

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Call_Release (Agent Exiting a Call)

Event Description

This event indicates that an agent exits a call with the specified **callId**.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the unique call ID (CallId).

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_Call_Release", "workNo": "49999", "content": "1456402370-7"}}</pre>
----------------------------	--

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Customer_Release (User Exiting a Call)

Event Description

This event indicates that a user exits a call with the specified **callId**.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
number	string	Indicates the phone number of the party who releases the call.
callId	string	Indicates the unique call ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_Customer_Release", "workNo": "49999", "content": {"callId": "1456404171-43", "number": "70093"}}</pre>
----------------------------	--

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Auto_Answer (Automatic Answering a Call)

Event Description

This event indicates that the agent automatically answers a call.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
called	string	Indicates the called number.
caller	string	Indicates the calling number.
callid	string	Indicates the unique call ID.
type	string	Indicates the media type of a call, either an assistant call or a main call.
feature	string	Indicates the type of a call. See Table 1 .
mediaAbility	string	Indicates the media capability, where 1 indicates audio, 2 indicates video, and 3 indicates audio and video.
transfer	string	Reserved.
transfrom	string	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_Auto_Answer","workNo":"49999","content":{"caller":"70093","transfer":"no","callid":"1456404171-43","transfrom":"","called":"6048","type":"main","mediaAbility":"1","feature":"0"}}</pre>
----------------------------	--

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Ringing (Incoming Call Reminder)

Event Description

This event indicates that the agent is asked to manually answer a call.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
called	string	Indicates the called number.
caller	string	Indicates the calling number.
callid	string	Indicates the unique call ID.
type	string	Indicates the media type of a call, either an assistant call or a main call.
feature	string	Indicates the type of a call. See Table 1 .
mediaAbility	string	Indicates the media capability, where 1 indicates audio, 2 indicates video, and 3 indicates audio and video.
transfer	string	Reserved.
transfrom	string	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_Ringing","workNo":"49999","content":{"caller":"70093","transfer":"no","callid":"1456404171-43","transfrom":"","called":"6048","type":"main","mediaAbility":"1","feature":"0"}}</pre>
----------------------------	--

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Connect_Fail (Failure to Connect to an Agent)

Event Description

This event indicates that connecting to the agent fails.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the unique call ID (CallId).

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_Connect_Fail", "workNo": "49999", "content": "1456402370-7"}}</pre>
----------------------------	--

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Consult_Fail (Failure to Ask for Help)

Event Description

This event indicates that the agent cannot ask for help.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	string	Indicates the unique call IF in the text format.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_Consult_Fail","workNo":"49999","content":"1456404043-39"}}</pre>
----------------------------	--

Parent topic: [Events Related to Voice Call](#)

AgentEvent_SipInfo (Receiving a SipInfo Message)

Event Description

This event indicates that an agent receives a SipInfo message from the peer during a call.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
dataType	int	Indicates the type of the SipInfo message content. 0 : DTMF digits 1 : Text
callId	string	Indicates the unique call ID.
sipInfo	string	Indicates the content of the SipInfo message.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_SipInfo","workNo":"20011","content":{"dataType":1,"callId":"1476357284-365","sipInfo":"121212121212f"}}</pre>
----------------------------	---

Parent topic: [Events Related to Voice Call](#)

AgentEvent_AbandonCall (Notifying an Abandoned Call)

Event Description

This event indicates that a user is released before a call is established if the virtual queuing function for abandoned calls is configured in a skill queue.

NOTE

This event is applicable only to the ECC scenario.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
caller	string	Indicates the calling number.
callData	string	Indicates the call-associated data.
callId	string	Indicates the unique call ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_AbandonCall", "workNo": "20011", "content": {"caller": "70006", "callData": null, "callId": "1477393438-167"}}</pre>
----------------------------	---

Parent topic: [Events Related to Voice Call](#)

AgentEvent_SuccTransResult (Notifying the Success Transfer Result)

Event Description

This event indicates that an agent successfully invokes the transfer interface for success transfer in the voice or text transfer scenario. The event is not supported for an external call transfer.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.
result	int	Indicates the success transfer result. 0 : Succeed. Other values: Fail.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_SuccTransResult","workNo":"20011","content":{"result":1,"callId":"1477467960-16777237"}}}</pre>
----------------------------	---

Parent topic: [Events Related to Voice Call](#)

AgentEvent_ReleaseRequest (Request Release Events)

Event Description

This event indicates that the call is released on the agent side. The call is hung up either by the customer or the agent or is released due to platform reasons.

NOTE

This event is applicable only to the ECC scenario.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_ReleaseRequest","workNo":"20011","content":{"callId":"1477467960-16777237"}}</pre>
----------------------------	--

Parent topic: [Events Related to Voice Call](#)

AgentEvent_ReleaseResponse (Response to Releasing A Call)

Event Description

This event indicates that the call is released.

NOTE

This event is applicable only to the ECC scenario.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_ReleaseResponse", "workNo": "20011", "content": {}}}</pre>
----------------------------	--

Parent topic: [Events Related to Voice Call](#)

AgentEvent_No_Answer_From_Cti (No Reply From an Agent for a Long Time)

Event Description

This event indicates that the agent does not respond to the information sent by the platform for a long time.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_No_Answer_From_Cti","workNo":"20011","content":{}}}</pre>
----------------------------	---

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Incoming_CallInfo (Incoming Call Notification Event)

Event Description

The event is triggered when an agent receives an incoming call from a user (including rerouted calls). The event is not triggered when an agent receives an internal call from the other agent, or a call that is transferred from the other agent, or a call that is invited to join a conference.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.
caller	string	Indicates the calling number.
called	string	Indicates the called number.
skillId	int	Indicates the ID of a skill queue.
skillName	string	Indicates the description of a skill queue.
mediaType	int	Indicates the media type. See Media Types .
lastReleaseAgentId	int	Indicates the ID of the last agent who releases the call. The value 65535 indicates that no agent releases the call.
releaseAndReQueueCallFlag	int	Indicates whether the current call is a rerouting call that is released by an agent. The value 0 indicates no and 1 indicates yes.
releaseAndReQueueCount	int	Indicates that rerouting times about the call is released by an agent. Only includes when the call is released by the agent after answering, the call will be rerouted by the system. Excluding when the call is rejected by the agent after ringing, the call will be rerouted by the system.
callerIMSI	string	Indicates the caller imsi.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_Incoming_CallInfo","workNo":"20011","content":{"caller":"70943","skillName":"voice_jst","lastReleaseAgentId":65535,"releaseAndReQueueCallFlag":0,"releaseAndReQueueCount":0,"called":"600153","skillId":6,"callId":"1493793040-36","mediaType":5}}}</pre>
----------------------------	---

Parent topic: [Events Related to Voice Call](#)

AgentEvent_TransOutResult (Notifying the Transfer-Out Result)

Event Description

This event indicates that an agent successfully invokes the transfer interface for transferring a call to external phone number. The event is not supported for transferring a call to external phone number in released transfer mode.

NOTE

If an agent hangs up the physical phone during transfer, the event will not be triggered.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.
result	int	Indicates the success transfer result. 0: Succeed. Other values: Fail.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_TransOutResult", "workNo": "20011", "content": {"result": 0, "callId": "1494571919-0"}}}</pre>
----------------------------	---

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Asr_Notify (Real-Time Speech-to-Text Notification)

Event Description

This event is triggered to send speech-to-text status notifications (including speech start, intermediate event, and speech end) and upload speech-to-text content for agents enabling the speech-to-text function.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
talkerPhoneDn	int	Indicates the phone number of the user when the value of talkerType is 2 .
curUserDn	int	Indicates the phone number of the user who is in a call with the agent. If a call is between two agents, the number is empty.
curCallId	string	Indicates the unique call ID.
agentAsrResult	string	Indicates the recognized text result. See Table 4 .
talkerType	int	Indicates the type of the speaker. 255 : invalid value; 1 : agent; 2 : user.
cclId	int	Indicates the contact center ID.
talkerAgentId	int	Indicates the agent ID when the value of the talkerType field is 1 .
vdnId	int	Indicates the VDN ID.
asrUserCase	int	Indicates the cause code of the recognition result, that is, the status of the current notification. The options are as follows: 61 : The recognition starts. 62 : The recognition is ongoing. 63 : The recognition ends. 33 : The user does not speak within the timeout interval. 30 : An ASR error occurs (for example, because the speech is too long, ASR rejects the request, ASR starts recognition too early, the speaker speaks too fast, ASR recognizes too slowly, or the recognized content is empty.)
initialAgentId	int	Indicates the controller agent ID.

Table 4 agentAsrResult parameters

Parameter	Data Type	Description
confidence	int	Indicates the accuracy of the recognition result. The value ranges from 0 to 100.
encUserData	int	Indicates whether to encrypt the recognition result. The options are as follows: • 0: not encrypted • 1: encrypted Encryption is currently unsupported.
asrEncodeType	int	Indicates the coding type. 0 : UTF-8; 1 : GB2312.
asrContent	String	The NLResult field indicates the content of the recognition result. The time field indicates the relative time from the recognition beginning to the current recognition, in units of ms.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_Asr_Notify","workNo":"102","content":{"talkerPhoneDn":"9420001", "curUserDn":"9420001","curCallId":"1520406120-7738","agentAsrResult":{"asrContent":"","nlresult speech-to-text content=Speech recognition; time=12340 13090>}},"confidence":100,"asrEncodeType":1,"encUserData":0},"talkerType":2,"cclId":1,"talkerAgentId":0, "vdnId":1,"asrUserCase":62,"initialAgentId":102}}</pre>
----------------------------	---

OUTBOUND_DETECT_EVENT (Outgoing Call Event with a Failure Cause Code)

Event Description

This event indicates that an outgoing call fails and contains a failure cause code.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
detect	string	Indicates the failure cause code.
desc	string	Indicates the cause description.
callId	string	Indicates the unique call ID.

Table 4 List of failure cause codes

Code	Description
1153	The agent releases the call.
1163	The called number does not exist.
1164	The called party is busy.
1165	The mobile phone is powered off.
1166	The mobile phone is not in the service area.
1168	The called party does not answer the call.
1169	The called party rejects the call.
Other	Internal error code.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"OUTBOUND_DETECT_EVENT","workNo":"402","content":{"detect":1153,"desc":"The telephone agent hangs up.","callId":"1524283342-561"}}}</pre>
----------------------------	---

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Third_Control (Third-Party Control Event)

Event Description

This is a third-party control event of an agent.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see the following table.

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of event

Parameter	Data Type	Description
thirdControlType	string	Indicates the third-party control type. For details, see Table 4 . Only when the type is ThirdControl_Callout , the following parameters are included (except agentstatus).
agentstatus	string	Indicates the agent status: This parameter is available only when thirdControlType is set to ThirdControl_SetStatus . - AgentState_Idle - AgentState_Busy
caller	string	Indicates the calling number. The value is a number of 0-24 digits. This parameter can be left empty. If it is empty, the default calling number of the platform is used.
called	string	Indicates the called number. This parameter is mandatory. It contains 1 to 24 digits and special characters * or #.
skillid	int	Indicates the ID of a skill. The value is a number and can be left empty. When the parameter is left empty, the default skill ID configured on the platform is used.
callappdata	string	Indicates the channel-associated data. This parameter can be left empty or contains a maximum of 512 bytes.
mediaability	int	Indicates the media capability. The default value is 0. The options are as follows: 0: voice; 1: video; 2: default capability, negotiated by the agent's and user's phones

Table 4 thirdControlType parameters

ThirdControl_Callout	Third-Party Control
ThirdControl_CallAnswer	Call answering through third-party control
ThirdControl_SetStatus	Agent status setting through third-party control

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event": {"eventType":"AgentEvent_Third_Control","workNo":"102","content":{"thirdControlType":"ThirdControl_CallAnswer"}} HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event": {"eventType":"AgentEvent_Third_Control","workNo":"102","content": {"thirdControlType":"ThirdControl_Callout","caller":"40038","called":"40040","skillid":25,"callappdata":"","mediaability":1}}}</pre>
----------------------------	---

Parent topic: [Events Related to Voice Call](#)

AgentEvent_Inside_Call_Queue_Fail (Transferring a call to a skill queue fails)

Event Description

Failed to transfer an internal call to a skill queue.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	string	Indicates the unique call ID (CallId).

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "event": {"eventType": "AgentEvent_Inside_Call_Queue_Fail", "workNo": "1003", "content": "1537017373-111"}, "retcode": "0"}</pre>
----------------------------	---

Parent topic: [Events Related to Voice Call](#)

Events Related to Outgoing Call

- [AgentEvent_Release_Preview \(Previewed Outgoing Call Released\)](#)
- [AgentEvent_Agent_Occupied \(Agent Preoccupied\)](#)
- [AgentEvent_Preview \(Previewed Outgoing Call Initiated\)](#)

Parent topic: [Events](#)

AgentEvent_Release_Preview (Previewed Outgoing Call Released)

Event Description

This event indicates that the previewed outgoing call is released.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_Release_Preview","workNo":"49999","content":null}}</pre>
----------------------------	--

Parent topic: [Events Related to Outgoing Call](#)

AgentEvent_Agent_Occupied (Agent Preoccupied)

Event Description

This event indicates that the agent is preoccupied.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_Agent_Occupied", "workNo": "49999", "content": null}}</pre>
----------------------------	--

Parent topic: [Events Related to Outgoing Call](#)

AgentEvent_Preview (Previewed Outgoing Call Initiated)

Event Description

This event indicates that the agent receives a previewed outgoing call initiating event.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
controlid	string	Indicates the control block ID of the previewed outgoing call.
dialeddigits	string	Indicates the called number of the previewed outgoing call.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_Preview","workNo":"49999","content":{"controlid":"1456404043","dialeddigits":""}}}</pre>
----------------------------	--

Parent topic: [Events Related to Outgoing Call](#)

Events Related to Recording Playback

[AgentMediaEvent_Play_\(Recording Playback Started\)](#)
[AgentMediaEvent_Play_Succ_\(Recording Playback Succeeded\)](#)
[AgentMediaEvent_Play_Fail_\(Recording Playback Failed\)](#)
[AgentMediaEvent_StopPlayDone_\(Recording Playback Stopped\)](#)
[AgentMediaEvent_PausePlayDone_\(Recording Playback Paused\)](#)
[AgentMediaEvent_ResumePlayDone_\(Recording Playback Resumed\)](#)
[AgentMediaEvent_JumpPlayDone_\(Recording Playback Fast-Forwarded\)](#)
[AgentMediaEvent_Record_\(Recording Started\)](#)
[AgentMediaEvent_Record_Fail_\(Recording Start Failed\)](#)
[AgentMediaEvent_PauseRecordDone_\(Recording Paused\)](#)
[AgentMediaEvent_ResumeRecordDone_\(Recording Resumed\)](#)
[AgentMediaEvent_StopRecordDone_\(Recording Stopped\)](#)
[AgentMediaEvent_StartRecordScreen_Succ_\(Starting Screen Recording Succeeded\)](#)
[AgentMediaEvent_StartRecordScreen_Fail_\(Starting Screen Recording Failed\)](#)
[AgentMediaEvent_StopRecordScreen_Succ_\(Stopping Screen Recording Succeeded\)](#)
[AgentMediaEvent_StopRecordScreen_Fail_\(Stopping Screen Recording Failed\)](#)

Parent topic: [Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

AgentMediaEvent_Play (Recording Playback Started)

Event Description

This event indicates that recording playback is started.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentMediaEvent_Play","workNo":"49999","content":null}}</pre>
----------------------------	--

Parent topic: [Events Related to Recording Playback](#)

AgentMediaEvent_Play_Succ (Recording Playback Succeeded)

Event Description

This event indicates that recording playback is successful.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentMediaEvent_Play_Succ", "workNo": "49999", "content": null}}</pre>
----------------------------	--

Parent topic: [Events Related to Recording Playback](#)

AgentMediaEvent_Play_Fail (Recording Playback Failed)

Event Description

This event indicates that recording playback has failed.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentMediaEvent_Play_Fail", "workNo": "49999", "content": null}}</pre>
----------------------------	--

Parent topic: [Events Related to Recording Playback](#)

AgentMediaEvent_StopPlayDone (Recording Playback Stopped)

Event Description

This event indicates that recording playback is stopped.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
cause	int	Indicates the cause for stopping the recording playback 0: normally stopped after playback 1: proactively stopped by an agent 2: stopped due to recording playback failure

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentMediaEvent_StopPlayDone","workNo":"49999","content":{"cause":0}}</pre>
----------------------------	--

Parent topic: [Events Related to Recording Playback](#)

AgentMediaEvent_PausePlayDone (Recording Playback Paused)

Event Description

This event indicates that recording playback is paused.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentMediaEvent_PausePlayDone", "workNo": "49999", "content": null}}</pre>
----------------------------	--

Parent topic: [Events Related to Recording Playback](#)

AgentMediaEvent_ResumePlayDone (Recording Playback Resumed)

Event Description

This event indicates that recording playback is resumed.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentMediaEvent_ResumePlayDone", "workNo": "49999", "content": null}}</pre>
----------------------------	---

Parent topic: [Events Related to Recording Playback](#)

AgentMediaEvent_JumpPlayDone (Recording Playback Fast-Forwarded)

Event Description

This event indicates that recording playback is fast-forwarded.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentMediaEvent_JumpPlayDone", "workNo": "49999", "content": null}}</pre>
----------------------------	---

Parent topic: [Events Related to Recording Playback](#)

AgentMediaEvent_Record (Recording Started)

Event Description

This event indicates that recording for the agent is started.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
taskId	int	Indicates the ID of a recording task within the platform.
caller	string	Indicates the calling number.
recordID	string	Indicates the serial number of a recording.
called	string	Indicates the called number.
locationId	string	Indicates the ID of a central node corresponding to a recording.
fileName	string	Indicates the recording file address.
callId	string	Indicates the unique call ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentMediaEvent_Record", "workNo": "20011", "content": {"taskId": 5206, "caller": "70006", "recordID": "Yc1v6a20011d20161025t1902050", "called": "60015", "locationId": "256", "fileName": "Y:/6/0/20161025/20011/1902050.V3", "callId": "1477393325-164"}}</pre>
----------------------------	---

Parent topic: [Events Related to Recording Playback](#)

AgentMediaEvent_Record_Fail (Recording Start Failed)

Event Description

This event indicates that starting recording for the agent has failed.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Table 3 Parameter description of content

Parameter	Data Type	Description
taskId	int	Indicates the ID of a recording task within the platform.
caller	string	Indicates the calling number.
recordID	string	Indicates the serial number of a recording.
called	string	Indicates the called number.
locationId	int	Indicates the ID of a central node corresponding to a recording.
fileName	string	Indicates the recording file address.
callId	string	Indicates the unique call ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentMediaEvent_Record_Fail", "workNo": "20011", "content": {"taskId": 5255, "caller": "70006", "recordID": "Cc1v6a20011d20161025t1930326", "called": "60015", "locationId": "65535", "fileName": "C:/6/0/20161025/20011/1930326.V3", "callId": "1477395030-183"}}}}</pre>
----------------------------	---

Parent topic: [Events Related to Recording Playback](#)

AgentMediaEvent_PauseRecordDone (Recording Paused)

Event Description

This event indicates that recording for the agent is paused.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentMediaEvent_PauseRecordDone", "workNo": "49999", "content": null}}</pre>
----------------------------	--

Parent topic: [Events Related to Recording Playback](#)

AgentMediaEvent_ResumeRecordDone (Recording Resumed)

Event Description

This event indicates that recording for the agent is resumed.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentMediaEvent_ResumeRecordDone","workNo":"49999","content":null}}</pre>
----------------------------	--

Parent topic: [Events Related to Recording Playback](#)

AgentMediaEvent_StopRecordDone (Recording Stopped)

Event Description

This event indicates that recording for the agent is stopped.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
taskId	int	Indicates the ID of a recording task within the platform.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentMediaEvent_StopRecordDone", "workNo": "20011", "content": {"taskId": 5204}}}</pre>
----------------------------	---

Parent topic: [Events Related to Recording Playback](#)

AgentMediaEvent_StartRecordScreen_Succ (Starting Screen Recording Succeeded)

Event Description

This event indicates that screen recording is successfully started.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Table 3 Parameter description of content

Parameter	Data Type	Description
locationId	string	Indicates the ID of a central node corresponding to a recording.
fileName	string	Indicates the recording file address.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentMediaEvent_StartRecordScreen_Succ", "workNo": "300", "content": {"locationId": "-1", "fileName": "ftp://192.168.1.10/sftp/2/1/300/20160623/095145"}}}</pre>
----------------------------	---

Parent topic: [Events Related to Recording Playback](#)

AgentMediaEvent_StartRecordScreen_Fail (Starting Screen Recording Failed)

Event Description

This event indicates that screen recording fails to be started.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentMediaEvent_StartRecordScreen_Fail", "workNo": "300", "content": null}}</pre>
----------------------------	--

Parent topic: [Events Related to Recording Playback](#)

AgentMediaEvent_StopRecordScreen_Succ (Stopping Screen Recording Succeeded)

Event Description

This event indicates that screen recording of the current agent is successfully stopped.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentMediaEvent_StopRecordScreen_Succ", "workNo": "300", "content": null}}</pre>
----------------------------	--

Parent topic: [Events Related to Recording Playback](#)

AgentMediaEvent_StopRecordScreen_Fail (Stopping Screen Recording Failed)

Event Description

This event indicates that screen recording fails to be stopped.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentMediaEvent_StopRecordScreen_Fail", "workNo": "300", "content": null}}</pre>
----------------------------	---

Parent topic: [Events Related to Recording Playback](#)

Events Related to Text Chat

[AgentChat_Ring](#).(Ringing Before a Text Chat)
[AgentChat_Connected](#) (Text Chat Session Connected)
[AgentChat_Disconnected](#) (Text Chat Session Disconnected)
[AgentChat_DataRecvcd](#) (Obtaining Messages During a Text Chat)
[AgentChat_DataRecvcdEx](#) (Obtaining a Reply Message in a Text Chat)
[AgentChat_TransferStart](#) (Text Chat Call Transfer Started)
[AgentChat_TransferFailed](#) (Text Chat Call Transfer Failed)
[AgentChat_CallOutCreated](#) (Internal Text Chat Call Created)
[AgentChat_CalloutFailed](#) (Internal Text Chat Call Failed)
[AgentChat_Swapcd](#) (Notification of Invalid Text Chats (Server Switchover))
[AgentChat_WithoutCallConfirm](#) (Supplementary Reply Message)
[AgentChat_NoRealTimeCall](#) (Non-real-time Call Content Notification)
[AgentChat_PostDataSuccess](#) (Successfully Sending the Text Chat Content)
[AgentChat_PostDataFailed](#) (Sending the Text Chat Content Failed)

Parent topic: [Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

AgentChat_Ring (Ringing Before a Text Chat)

Event Description

This event indicates that the agent receives the AgentChat_Ring event. After the call center allocates a text chat to an agent, the agent receives this event.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3

Table 3 Parameter description of content

Parameter	Data Type	Description
caller	string	Indicates the calling number (or work ID of the calling agent for an internal text chat call).
isInnerCall	boolean	Indicates whether it is an internal text chat call.
called	string	Indicates the called number (or access code for a web user call, or work ID of the called agent for an internal text chat call).
callId	string	Indicates the unique call ID.
uvid	int	Indicates the customer access ID.
displayName	string	Indicates the displayed name of the user.
realCaller	string	Indicates the real calling party information.
userInfo	string	Indicates user information.
subMediaType	int	Indicates the sub media type.
attachData	string	Indicates the call-associated data.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentChat_Ring", "workNo": "49997", "content": {"caller": "test", "isInnerCall": false, "called": "600141", "uvid": 1254357, "realCaller": "jst", "userInfo": "null", "displayName": "jst", "callId": "1503470711-16777219", "subMediaType": 255, "attachData": ""}}}</pre>
----------------------------	---

Parent topic: [Events Related to Text Chat](#)

AgentChat_Connected (Text Chat Session Connected)

Event Description

This event indicates that the text chat session is connected. After the agent invokes the answer interface, a text chat session is connected and the agent receives this event.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
caller	string	Indicates the calling number (or work ID of the calling agent for an internal text chat call).
isInnerCall	boolean	Indicates whether it is an internal text chat call.
callId	string	Indicates the unique call ID.
called	string	Indicates the called number (or access code for a web user call, or work ID of the called agent for an internal text chat call).
uvid	int	Indicates the customer access ID.
attachData	string	Indicates the call-associated data.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentChat_Connected", "workNo": "49997", "content": {"caller": "49999", "isInnerCall": true, "called": "49997", "uvid": 1015460, "callId": "1456448988-16777216", "attachData": ""}}}</pre>
----------------------------	--

Parent topic: [Events Related to Text Chat](#)

AgentChat_Disconnected (Text Chat Session Disconnected)

Event Description

This event indicates that the text chat session is disconnected. When the text chat session ends, the agent receives this event.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentChat_Disconnected","workNo":"292","content":{"callId":"1438661103-16849130"}}</pre>
----------------------------	---

Parent topic: [Events Related to Text Chat](#)

AgentChat_DataRecved (Obtaining Messages During a Text Chat)

Event Description

The agent receives this event when the peer end sends a text message.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.
sender	string	Indicates the sender of the message.
isInnerCall	boolean	Indicates whether it is an internal text chat call.
chatContent	string	Indicates the sent content.
chatContentType	string	Indicates the content type, where 0 indicates text and 1 indicates file.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentChat_DataRecved", "workNo": "292", "content": {"sender": "test01", "isInnerCall": false, "chatContent": "test", "callId": "1438662114-16849136", "chatContentType": "0"}}</pre>
----------------------------	--

Parent topic: [Events Related to Text Chat](#)

AgentChat_DataRecvedEx (Obtaining a Reply Message in a Text Chat)

Event Description

This event indicates that a party in a text chat sends a message. Upon receiving this event, the agent calls the confirmation interface to confirm the receiving of a message.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.
sender	string	Indicates the sender of the message.
isInnerCall	boolean	Indicates whether it is an internal text chat call.
chatContent	string	Indicates the sent content.
chatContentType	string	Indicates the content type, where 0 indicates text and 1 indicates file.
chatId	string	Indicates the message ID.
sessionId	int	Indicates the ID of the sender in the CTI.
senderTime	string	Message sending time (timestamp).

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentChat_DataRecvedEx","workNo":"20011","content":{"sender":"1212","senderTime":"1481248826530","isInnerCall":false,"sessionId":100003,"chatContent":"\\u0031\\u0032\\u0031\\u0032\\u0031\\u0032","callId":"1476952781-16777221","chatId":482067725,"chatContentType":"0"}}}</pre>
----------------------------	--

Parent topic: [Events Related to Text Chat](#)

AgentChat_TransferStart (Text Chat Call Transfer Started)

Event Description

The agent receives this event after the text chat call is transferred at the agent's request. The agent will receive an event indicating that the call ends.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentChat_TransferStart","workNo":"292","content":{"callId":"1438662254-16849138"}}}</pre>
----------------------------	---

Parent topic: [Events Related to Text Chat](#)

AgentChat_TransferFailed (Text Chat Call Transfer Failed)

Event Description

This event indicates that text chat call transfer failed. The agent receives this event when the text chat call transfer requested by the agent fails (for example, the user is busy).

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentChat_TransferFailed","workNo":"291","content":{"callId":"1438662254-16849138"}}}</pre>
----------------------------	--

Parent topic: [Events Related to Text Chat](#)

AgentChat_CallOutCreated (Internal Text Chat Call Created)

Event Description

This event indicates that the internal text chat call is created. The agent who initiates the internal text chat call receives this event after the other agent receives the AgentChat_Ring event.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.
caller	string	Indicates the calling party.
called	string	Indicates the work ID of the called agent.
isInnerCall	boolean	Indicates whether it is an internal text chat call.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event": {"eventType":"AgentChat_CallOutCreated","workNo":"291","content":{"caller":"291","isInnerCall":true,"called":"292","callId":"1441182380-16777222"}}</pre>
----------------------------	---

Parent topic: [Events Related to Text Chat](#)

AgentChat_CalloutFailed (Internal Text Chat Call Failed)

Event Description

This event indicates that initiating an internal text chat call failed. After an agent initiates an internal text chat request to another agent, if the internal chat fails (for example, because the peer agent is busy), the agent receives the event.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentChat_CalloutFailed","workNo":"291","content":{"callId":"1438662583-16849139"}}</pre>
----------------------------	--

Parent topic: [Events Related to Text Chat](#)

AgentChat_Swaped (Notification of Invalid Text Chats (Server Switchover))

Event Description

This event indicates that in case of a server switchover, the system notifies the client that all the text chat calls related to the specified work ID become invalid.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{ {"content":null, "eventType":"AgentChat_Swaped ", "workNo":"2571"}}}</pre>
----------------------------	---

Parent topic: [Events Related to Text Chat](#)

AgentChat_WithoutCallConfirm (Supplementary Reply Message)

Event Description

This event indicates that a user reports the processing result after receiving the supplementary reply message from the agent.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3

Table 3 Parameter description of content

Parameter	Data Type	Description
result	int	Indicates the processing result reported by the user.
confirmer	string	User
chatId	int	Indicates the ID of a supplementary reply message sent by the agent.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentChat_WithoutCallConfirm", "workNo": "20011", "content": {"result": 0, "confirmer": "1212", "chatId": 1}}}</pre>
----------------------------	---

Parent topic: [Events Related to Text Chat](#)

AgentChat_NoRealTimeCall (Non-real-time Call Content Notification)

Event Description

This event indicates that a user directly sends a message to the current agent.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
caller	string	Indicates the user who initiates a non-real-time call.
dataSeqNo	string	Indicates the number of the non-real-time call content.
callData	string	Indicates the content of the non-real-time call.
innerSid	int	Indicates the internal ID of the CTI.
mediaType	int	Media Types
subMediaType	int	Indicates the sub media type.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentChat_NoRealTimeCall", "workNo": "20011", "content": {"caller": "1212", "dataSeqNo": "1658583507", "callData": "\\u0061\\u0073\\u0064\\u0066\\u0061\\u0073\\u0064\\u0066\\u0061\\u0073\\u0064\\u0066", "innerSid": 392036552, "mediaType": 1, "subMediaType": 0}}}</pre>
----------------------------	--

Parent topic: [Events Related to Text Chat](#)

AgentChat_PostDataSuccess (Successfully Sending the Text Chat Content)

Event Description

This event indicates that a receiver confirms the receiving of a message from an agent.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
result	int	Indicates the self-defined message confirmation result.
confirmer	string	Indicates the user who confirms a message.
callId	string	Indicates the unique call ID.
chatId	int	ID of a message

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentChat_PostDataSuccess","workNo":"20011","content":{"result":0,"confirmer":"1212","callId":"1476952781-16777221","chatId":120}}}</pre>
----------------------------	--

Parent topic: [Events Related to Text Chat](#)

AgentChat_PostDataFailed (Sending the Text Chat Content Failed)

Event Description

This event indicates that a receiver does not receive a message from an agent within 12s.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.
chatId	int	Indicates the message ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentChat_PostDataFailed","workNo":"20011","content":{"callId":"1476952781-16777221","chatId":120}}}</pre>
----------------------------	---

Parent topic: [Events Related to Text Chat](#)

Events Related to Real-time Quality Control

[QC_AgentState_Notify_\(Agent Monitoring Notification Event\)](#)

Parent topic: [Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

QC_AgentState_Notify (Agent Monitoring Notification Event)

Event Description

This is an agent monitoring event.

NOTE

1. The QC_AgentState_ActiveEx event supports the call transfer feature.

In the call transfer scenario, the callinfo field in the event content carries the call transfer information.

- The feature does not support the call transfer IVR scenario.
- When the MRS experiences an abnormal restart or active/standby switchover, it may affect the call transfer field information in the callinfo.

For details about the event content, see the event example.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
agentname	string	Indicates the work ID or user name of the current agent.
monitoredagent	string	Indicates the work ID or user name of the monitored agent.
subtype	String	Indicates the status or operation of the monitored agent. For details, see Table 4 .

Table 4 subtype description

QC_AgentState_Busy	Event indicating that the monitored agent enters the busy state
QC_AgentState_Mute	Muting event of the monitored agent
QC_AgentState_Monitor	Monitoring event of the monitored agent
QC_AgentState_RecordBegin	Recording event of the monitored agent
QC_AgentState_RecordStop	Recording stop event of the monitored agent
QC_AgentState_LiveVideoBegin	Screen inspection event of the monitored agent
QC_AgentState_LiveVideoStop	Screen inspection stop event of the monitored agent
QC_AgentState_SuperviseInsert	Supervising or inserting event of the monitored agent
QC_AgentState_StopSuperviseInsert	Supervision or insertion stop event of the monitored agent
QC_AgentState_StopMonitor	Monitoring stop event of the monitored agent
QC_AgentState_MuteVideo	Video muting event of the monitored agent
QC_AgentState_MuteVideoAudio	Video and audio muting event of the monitored agent
QC_AgentState_PlayVoice	Recording playback event of the monitored agent
QC_AgentState_Active	Calling event of the monitored agent
QC_AgentState_ActiveEx	Calling extended event of the monitored agent
QC_AgentState_WaitAnswer	Event indicating that the monitored agent is waiting for call answering
QC_AgentState_WaitAlerting	Event indicating that the monitored agent is waiting for the called party's phone to ring
QC_AgentState_ThreeParty	Three-party conversation event of the monitored agent

QC_AgentState_Busy	Event indicating that the monitored agent enters the busy state
QC_AgentState_HungUp	Event indicating that the call of the monitored agent is hung up
QC_AgentState_MonitorSupervisorOther	Monitoring, supervision, insertion, or whispering event of the monitored agent
QC_AgentState_MonitorInsertCall	Listening or barge event of the monitored agent
QC_AgentState_Idle	Event indicating that the monitored agent enters the idle state
QC_AgentState_Work	Event indicating that the monitored agent enters the working state
QC_AgentState_Rest	Event indicating that the monitored agent enters the rest state
QC_AgentState_Login	Login event of the monitored agent
QC_AgentState_Logout	Logout event of the monitored agent
QC_AgentState_LongNoAnswer	Event indicating that the monitored agent does not answer a call within a long time
QC_AgentState_SMS	Event indicating that the monitored agent has an SMS notification event.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"content":{"callinfo":{"callid":"1715937349-286","callfeature":0,"caller":"85193173","called":"1001","mediatype":5,"submediatype":255,"calldata":"datastring","transtype":"1","transfrom":"2574","callerimsi":"","subtype":"QC_AgentState_ActiveEx","monitoredagent":"2573","agentname":"2573"},"eventtype":"QC_AgentState_Notify","workNo":"2571"}}</pre>
----------------------------	--

Parent topic: [Events Related to Real-time Quality Control](#)

Events Related to RMS

[CTI_START_CALL_EVENT \(Call Starting\)](#)

[CTI_STOP_CALL_EVENT \(Call Ending\)](#)

[CTI_AGENT_LOGIN_EVENT \(Login\)](#)

[CTI_AGENT_LOGOUT_EVENT \(Logout\)](#)

Parent topic: [Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

CTI_START_CALL_EVENT (Call Starting)

Event Description

This event indicates that the agent starts a call.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
AgentID	string	Indicates the work ID of an agent.
HwFileName	string	Indicates the recording file name.
Caller	string	Indicates the calling number.
Called	string	Indicates the called number.
CallID	string	Indicates the unique call ID.
InOut	string	Call Types
Tel	string	Indicates the phone number of an agent.
SubCCID	string	Indicates the contact center ID.
QueueID	string	Indicates the ID of a skill.
MSDData	string	Indicates the MSD data of the NG-eCall.
CallerIMSI	string	Indicates the caller imsi.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"eventType": "CTI_START_CALL_EVENT", "workNo": "291", "content": {"AgentID": "291", "Caller": "70090", "Called": "6048", "CallID": "1438662583-16849139", "InOut": "I", "Tel": "70091", "SubCCID": "1", "QueueID": "25", "HwFileName": "textfilename"}}</pre>
----------------------------	---

Parent topic: [Events Related to RMS](#)

CTI_STOP_CALL_EVENT (Call Ending)

Event Description

This event indicates that the call of the agent ends.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
AgentID	string	Indicates the work ID of an agent.
Tel	string	Indicates the phone number of an agent.
SubCCID	string	Indicates the contact center ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event": {"eventType":"CTI_STOP_CALL_EVENT","workNo":"291","content":{"SubCCID":"1","Tel":"70090","AgentID":"291"}}</pre>
----------------------------	--

Parent topic: [Events Related to RMS](#)

CTI_AGENT_LOGIN_EVENT (Login)

Event Description

This event indicates that an agent logs in.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
AgentID	string	Indicates the work ID of an agent.
AgentName	string	Indicates the name of an agent.
Tel	string	Indicates the phone number of an agent.
SubCCID	string	Indicates the contact center ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "CTI_AGENT_LOGIN_EVENT", "workNo": "291", "content": {"SubCCID": "1", "AgentName": "291", "Tel": "70090", "AgentID": "291"}}</pre>
----------------------------	---

Parent topic: [Events Related to RMS](#)

CTI_AGENT_LOGOUT_EVENT (Logout)

Event Description

This event indicates that an agent logs out.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event": {"eventType":"CTI_AGENT_LOGOUT_EVENT","workNo":"291","content":null}}</pre>
----------------------------	---

Parent topic: [Events Related to RMS](#)

Events Related to Physical Phone

[AgentOther_PhoneUnknown \(Phone Status Unknown\)](#)

[AgentOther_PhoneRelease \(Phone in On-Hook State\)](#)

[AgentOther_PhoneOffhook \(Phone in Off-Hook State\)](#)

[AgentOther_PhoneAlerting \(Phone in Ringing State\)](#)

[AgentOther_PhoneBusy \(Physical Phone of an Agent Busy\)](#)

Parent topic: [Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

AgentOhter_PhoneUnknow (Phone Status Unknown)

Event Description

This event indicates that the phone status of an agent is unknown.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentOther_PhoneUnknow", "workNo": "49999", "content": null}}</pre>
----------------------------	---

Parent topic: [Events Related to Physical Phone](#)

AgentOther_PhoneRelease (Phone in On-Hook State)

Event Description

This event indicates that the phone of an agent is in the on-hook state.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
phoneState	int	Indicates the release cause. 2 : hang-up by the agent. 3 : hang-up by the platform.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event": {"eventType":"AgentOther_PhoneRelease","workNo":"20012","content":{"phoneState":3}}}</pre>
----------------------------	--

Parent topic: [Events Related to Physical Phone](#)

AgentOther_PhoneOffhook (Phone in Off-Hook State)

Event Description

This event indicates that the phone of an agent is in the off-hook state.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentOther_PhoneOffhook","workNo":"49999","content":null}}</pre>
----------------------------	---

Parent topic: [Events Related to Physical Phone](#)

AgentOther_PhoneAlerting (Phone in Ringing State)

Event Description

This event indicates that the phone of an agent is ringing.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentOther_PhoneAlerting", "workNo": "4999", "content": null}}</pre>
----------------------------	--

Parent topic: [Events Related to Physical Phone](#)

AgentOther_PhoneBusy (Physical Phone of an Agent Busy)

Event Description

This event indicates that the agent cannot answer a call because the phone is not signed in or the agent rejects the call on the phone.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentOther_PhoneBusy", "workNo": "20011", "content": {}}}</pre>
----------------------------	---

Parent topic: [Events Related to Physical Phone](#)

Events Related to Multimedia Conference

[AgentEvent_JoinConf \(Notification of a Multimedia Conference Message\)](#)

[AgentEvent_OnMultimediaConfState \(Notification of the Multimedia Conference Status\)](#)

[AgentEvent_OnStopMultimediaConf \(Multimedia Conference Stopped\)](#)

Parent topic: [Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

AgentEvent_JoinConf (Notification of a Multimedia Conference Message)

Event Description

This is a conference message notification event occurred after the conference resources are successfully applied.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3

Table 3 Parameter description of content

Parameter	Data Type	Description
confid	int	Indicates the conference ID.
confinfo	string	Indicates the conference information.
vdnid	int	vdn id
addresstype	int	Indicates the address type. 6 : phone number 9 : work ID of an agent
address	string	Indicates the address ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"eventType": "AgentEvent_JoinConf", "workNo": "108", "content": {"vdnid": 1, "addresstype": 9, "confid": 13107206, "confinfo": "ConfID=13107206 UserID=108 UserType=2 HostKey=35866746902687318633182764881727 SiteID=6jfl SiteUrl=10.120.189.41:6888 MSServerIP=10.186.53.75:8080 MsNatMap={ConfPrivilege=3192956785292434, "address": "108", "jsonKey": ["vdnid", "addresstype", "confid", "confinfo", "address"]}, "jsonKey": ["eventType", "workNo", "content"]}}</pre>
----------------------------	--

Parent topic: [Events Related to Multimedia Conference](#)

AgentEvent_OnMultimediaConfState (Notification of the Multimedia Conference Status)

Event Description

This event indicates that the platform delivers a multimedia conference status notification to the requesting party.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
vdnid	int	Indicates the VDN ID.
addresstype	int	Indicates the address type. 6 : phone number 9 : work ID of an agent
cause	int	Indicates the failure cause. See Error Codes about Multimedia Conferences .
confid	int	Indicates the conference ID.
address	string	Indicates the address ID.
confstate	int	Indicates the conference status. 0 : not in conference; 1 : in conference

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event": {"eventType":"AgentEvent_OnMultimediaConfState","workNo":"108","content":{"vdnid":1,"addresstype":9,"cause":3617,"confid":-1, "address":"113","confstate":0,"jsonKey":{"vdnid","addresstype","cause","confid","address","confstate"}}, "jsonKey": ["eventType","workNo","content"]}}</pre>
----------------------------	--

Parent topic: [Events Related to Multimedia Conference](#)

AgentEvent_OnStopMultimediaConf (Multimedia Conference Stopped)

Event Description

- This is a multimedia conference stopping event delivered to the conference by the platform.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
confid	int	Indicates the conference ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_OnStopMultimediaConf", "workNo": "110", "content": {"confid": -1, "jsonKey": [{"confid"}], "jsonKey": [["eventType", "workNo", "content"]]</pre>
----------------------------	---

Parent topic: [Events Related to Multimedia Conference](#)

Events Related to Phone Linkage

[AgentEvent_linkageCapability \(Events Related to Phone Linkage Results\)](#)

[AgentEvent_linkagePhoneStatus \(Phone Status\)](#)

[AgentEvent_linkagePhoneMute \(Call Muted in the Phone Linkage State\)](#)

[AgentEvent_linkagePhoneUnMute \(Muted Call Unmuted in the Phone Linkage State\)](#)

[AgentEvent_linkagePhoneCallOut \(Outgoing Call Made in the Phone Linkage State\)](#)

[AgentEvent_linkagePhoneTransferOut \(Call Transferred in the Phone Linkage State\)](#)

[AgentEvent_linkagePhoneTransferOut_Result \(The Result Of Call Transferred in the Phone Linkage State\)](#)

Parent topic: [Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

AgentEvent_linkageCapability (Events Related to Phone Linkage Results)

Event Description

This event indicates whether the phone linkage of an agent is successful.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
result	int	Indicates the linkage result. 0 : Succeed. Other values: Fail.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_linkageCapability","workNo":"120","content":{"result":0}}}</pre>
----------------------------	--

Parent topic: [Events Related to Phone Linkage](#)

AgentEvent_linkagePhoneStatus (Phone Status)

Event Description

This event indicates the phone status of an agent.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
result	int	Indicates the phone status. For the parameter description of result , see Table 4 .

Table 4 Phone status

Value	Description
0	Off-hook
1	On-hook
2	In a call
3	Online
5	Ringing
6	IPCC line recovered

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_linkagePhoneStatus","workNo":"120","content":{"result":2}}}</pre>
----------------------------	---

Parent topic: [Events Related to Phone Linkage](#)

AgentEvent_linkagePhoneMute (Call Muted in the Phone Linkage State)

Event Description

This event indicates that a call is muted.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique ID of a muted call.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_linkagePhoneMute","workNo":"120","content":{"callId":"1474269843-24"}}</pre>
----------------------------	--

Parent topic: [Events Related to Phone Linkage](#)

AgentEvent_linkagePhoneUnMute (Muted Call Unmuted in the Phone Linkage State)

Event Description

This event indicates that a muted call is unmuted.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique ID of an unmuted call.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_linkagePhoneUnMute", "workNo": "120", "content": {"callId": "1474269843-24"}}</pre>
----------------------------	--

Parent topic: [Events Related to Phone Linkage](#)

AgentEvent_linkagePhoneCallOut (Outgoing Call Made in the Phone Linkage State)

Event Description

This event indicates that an agent makes an outgoing call in the phone linkage state.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
addrCalled	map	Indicates the called number. For the parameter description, see Table 4 .
addrCaller	map	Indicates the phone number of an agent. For the parameter description, see Table 5 .
skillId	int	Indicates the ID of a skill queue.
callId	string	Indicates a unique call ID (This call ID is not used because it is not the actual call ID returned for a call).

Table 4 Parameter description of addrCalled

Parameter	Data Type	Description
address	string	Indicates the address ID.
addressType	int	Indicates the address type. Currently, it can be set to 6 only, indicating a phone number.

Table 5 Parameter description of addrCaller

Parameter	Data Type	Description
address	string	Indicates the address ID.
addressType	int	Indicates the address type. Currently, it can be set to 6 only, indicating a phone number.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_linkagePhoneCallOut", "workNo": "120", "content": {"addrCalled": {"address": "70002", "addressType": 6}, "addrCaller": {"address": "70001", "addressType": 6}, "skillId": 0, "callId": "1475051437-34"}}</pre>
----------------------------	---

Parent topic: [Events Related to Phone Linkage](#)

AgentEvent_linkagePhoneTransferOut (Call Transferred in the Phone Linkage State)

Event Description

This event indicates that an agent transfers the current call in the phone linkage state.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3

Table 3 Parameter description of content

Parameter	Data Type	Description
addrOut	map	Indicates the phone number of a transferred call.
addrSelf	map	Indicates the phone number of an agent.

Table 4 Parameter description of addrOut

Parameter	Data Type	Description
address	string	Indicates the address ID.
addressType	int	Indicates the address type. Currently, it can be set to 6 only, indicating a phone number.

Table 5 Parameter description of addrSelf

Parameter	Data Type	Description
address	string	Indicates the address ID.
addressType	int	Indicates the address type. Currently, it can be set to 6 only, indicating a phone number.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_linkagePhoneTransferOut","workNo":"120","content":{"addrOut":{"address":"70002","addressType":6},"addrSelf":{"address":"70001","addressType":6}}}}</pre>
----------------------------	--

Parent topic: [Events Related to Phone Linkage](#)

AgentEvent_linkagePhoneTransferOut_Result (The Result Of Call Transferred in the Phone Linkage State)

Event Description

This event indicates the result that the agent transfers the current call in the phone linkage state.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
result	int	Indicates the transfer result. 0 : Succeed. Other values: Fail.
callId	string	Indicates a unique ID of a call transferred.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_linkagePhoneTransferOut_Result","workNo":"130","content":{"result":1138,"callId":"1481881644-21"}}}</pre>
----------------------------	---

Parent topic: [Events Related to Phone Linkage](#)

Conference Call Events

[AgentConf_RequestSuccess \(Successfully Applying for a Conference Call\)](#)
[AgentConf_RequestFailed \(Applying for a Conference Call Failed\)](#)
[AgentConf_SelfJoinResult \(Agent Joined a Conference Call\)](#)
[AgentConf_Timeout \(Conference Timeout Reminder\)](#)
[AgentConf_Ringing \(Ringing of a Conference Call\)](#)
[AgentConf_ParticipantChanged \(Participant Changed\)](#)
[AgentConf_SelfLeaveResult \(Agent Leaved a Conference Call\)](#)
[AgentConf_PresidentChanged \(Conference Chair Changed\)](#)
[AgentConf_StopVoice \(Conference Announcement Ended\)](#)
[AgentConf_StopParticipantVoice \(Conference Channel Announcement Ended\)](#)
[AgentConf_SipInfo \(Conference SipInfo Message\)](#)

Parent topic: [Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

AgentConf_RequestSuccess (Successfully Applying for a Conference Call)

Event Description

This event indicates that a conference call is successfully applied and a conference chair has joined the conference.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
confId	int	Indicates the conference ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentConf_RequestSuccess","workNo":"153","content":{"confId":1030400}}}</pre>
----------------------------	--

Parent topic: [Conference Call Events](#)

AgentConf_RequestFailed (Applying for a Conference Call Failed)

Event Description

This event indicates that applying for a conference call failed.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
cause	int	Indicates the code of a failure cause.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentConf_RequestFailed", "workNo": "153", "content": {"cause": 21234}}}</pre>
----------------------------	--

Parent topic: [Conference Call Events](#)

AgentConf_SelfJoinResult (Agent Joined a Conference Call)

Event Description

This event indicates that the current agent has joined the conference call.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
confId	int	Indicates the conference ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentConf_SelfJoinResult","workNo":"153","content":{"confId":1030400}}}</pre>
----------------------------	--

Parent topic: [Conference Call Events](#)

AgentConf_Timeout (Conference Timeout Reminder)

Event Description

This event is triggered when the remaining duration of a conference call reaches the time point for sending a reminder. The timer starts after the conference call is successfully applied.

The agent can determine whether to extend the conference call upon receiving this event. If not extended, the conference call ends when reaching the end time.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3

Table 3 Parameter description of content

Parameter	Data Type	Description
confId	int	Indicates the conference ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentConf_Timeout", "workNo": "153", "content": {"confId": 1030400}}}</pre>
----------------------------	---

Parent topic: [Conference Call Events](#)

AgentConf_Ringing (Ringing of a Conference Call)

Event Description

This event is received by an invited agent.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
confId	int	Indicates the conference ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentConf_Ringing","workNo":"153","content":{"confId":1030400}}}</pre>
----------------------------	---

Parent topic: [Conference Call Events](#)

AgentConf_ParticipantChanged (Participant Changed)

Event Description

This event is received by an invited agent.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
confId	int	Indicates the conference ID.
result	int	Indicates the change result. 0 : Succeed. Other values: Fail.
changeType	int	Indicates the change type. For the parameter description, see Table 4 .
changeReason	int	Indicates the change reason. It is valid only when ChangeType is set to 1 , and is meaningless when ChangeType is set to other values. For the parameter description, see Table 5 .
participant	string	Indicates the ID of a conference participant.
participantType	int	Indicates the type of a conference call participant 6 : phone number; 9 : work ID of an agent
deviceCallType	int	Indicates a user-defined device call type.
deviceType	int	Indicates a user-defined device type.

Table 4 Parameter description of changeType

Value	Description
0	Join a conference call.
1	Exit a conference call.
2	Change by a conference chair.
3	Prohibit the speech.
4	Restore the speech.
5	Hold a participant.
6	Unhold a participant.

Table 5 Parameter description of changeReason

Value	Description
0	A participant proactively exits a conference call.
1	The conference chair forcibly logs out a participant.
2	A participant hangs up the phone.
3	The conference call ends.
4	A participating agent logs out.
5	A participant is forcibly logged out of a conference call due to other reasons.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentConf_ParticipantChanged","workNo":"154","content":{"result":0,"changeReason":255,"changeType":3,"confId":1031168,"participant":"154","participantType":9,"deviceCallType":0,"deviceType":0}}}</pre>
----------------------------	---

Parent topic: [Conference Call Events](#)

AgentConf_SelfLeaveResult (Agent Leaved a Conference Call)

Event Description

This event indicates that an agent leaves a conference call.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
confId	int	Indicates the conference ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentConf_SelfLeaveResult", "workNo": "153", "content": {"confId": 1030400}}}</pre>
----------------------------	---

Parent topic: [Conference Call Events](#)

AgentConf_PresidentChanged (Conference Chair Changed)

Event Description

This event indicates that the current agent becomes a conference chair.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3

Table 3 Parameter description of content

Parameter	Data Type	Description
confId	int	Indicates the conference ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentConf_PresidentChanged", "workNo": "154", "content": {"confId": 1031168}}}</pre>
----------------------------	--

Parent topic: [Conference Call Events](#)

AgentConf_StopVoice (Conference Announcement Ended)

Event Description

This event indicates that the conference announcement ends.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
result	int	Indicates the result of ending conference announcement. 0 : Succeed. 1 : Fail.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentConf_StopVoice","workNo":"154","content":{"result":0}}}</pre>
----------------------------	---

Parent topic: [Conference Call Events](#)

AgentConf_StopParticipantVoice (Conference Channel Announcement Ended)

Event Description

This event indicates that the conference channel announcement ends.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
result	int	Indicates the result of ending conference announcement. 0 : Succeed. 1 : Fail.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentConf_StopParticipantVoice","workNo":"154","content":{"result":0}}}</pre>
----------------------------	--

Parent topic: [Conference Call Events](#)

AgentConf_SipInfo (Conference SipInfo Message)

Event Description

This event indicates that the conference chair has received the SipInfo message from a user.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
sender	string	Indicates the sender of the SipInfo message.
dataType	int	Indicates the type of the SipInfo message content. 0 : DTMF digits 1 : text
senderType	int	Indicates the sender type. 6 : phone number; 9 : work ID of an agent
callId	string	Indicates the call ID corresponding to a conference.
sipInfo	string	Indicates the content of the SipInfo message.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentConf_SipInfo","workNo":"20011","content":{"sender":"89600151","dataType":1,"senderType":6,"callId":"1476356760-361","sipInfo":"1212121212f"}}</pre>
----------------------------	---

Parent topic: [Conference Call Events](#)

Email Events

[AgentMail_Ringing \(Ringing of an Email Call\)](#)

[AgentMail_Connected \(Email Call Setup\)](#)

[AgentMail_Received \(Email Received\)](#)

[AgentMail_Disconnected \(Email Call Released\)](#)

[AgentMail_Remind \(Email Reminder\)](#)

[AgentMail_CallOutFailed \(Outgoing Email Failed\)](#)

[AgentMail_NoAnswer \(No Answer to an Email Call\)](#)

Parent topic: [Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

AgentMail_Ringing (Ringling of an Email Call)

Event Description

This event indicates that an email is distributed to the current agent.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
called	string	Indicates the access code of an email call.
mailcaller	string	Indicates the address of an email sender.
callId	string	Indicates the ID of an email call.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentMail_Ringing","workNo":"20011","content":{"called":"60010","mailcaller":"jinsitao@cc.com","callId":"1476344714-33554634"}}}</pre>
----------------------------	---

Parent topic: [Email Events](#)

AgentMail_Connected (Email Call Setup)

Event Description

This event indicates that an email call is successfully set up.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
type	int	Indicates the call type. 0 : incoming call. 1 : outgoing call.
callId	string	Indicates the ID of an email call.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentMail_Connected","workNo":"20011","content":{"type":0,"callId":"1476344714-33554634"}}}</pre>
----------------------------	--

Parent topic: [Email Events](#)

AgentMail_Received (Email Received)

Event Description

This event indicates that an email is received in a private inbox of an agent.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
time	long	Indicates the time when a call accesses the system (timestamp).
handle	int	Indicates the number of times that a call accesses a task.
dsn	int	Indicates the number of a task to which a call accesses.
callId	string	Indicates the ID of an email call.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentMail_Received","workNo":"20011","content":{"time":1476344714,"handle":0,"dsn":202,"callId":"1476344714-33554634"}}}</pre>
----------------------------	---

Parent topic: [Email Events](#)

AgentMail_Disconnected (Email Call Released)

Event Description

This event indicates that an email call is released.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
type	int	Indicates the call type. 0 : incoming call. 1 : outgoing call.
callId	string	Indicates the ID of an email call.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentMail_Disconnected","workNo":"20011","content":{"type":0,"callId":"1476344714-33554634"}}}</pre>
----------------------------	---

Parent topic: [Email Events](#)

AgentMail_Remind (Email Reminder)

Event Description

This event reminds an agent to process an email call.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the ID of an email call.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentMail_Remind","workNo":"20011","content":{"callId":"1476346761-33554636"}}</pre>
----------------------------	---

Parent topic: [Email Events](#)

AgentMail_CallOutFailed (Outgoing Email Failed)

Event Description

This event indicates that an outgoing email fails.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the ID of an email call.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentMail_CallOutFailed","workNo":"20011","content":{"callId":"1476346065-33554635"}}</pre>
----------------------------	--

Parent topic: [Email Events](#)

AgentMail_NoAnswer (No Answer to an Email Call)

Event Description

This event indicates that the agent does not answer an email call for a long period of time.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the ID of an email call.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentMail_NoAnswer","workNo":"20011","content":{"callId":"1476344714-33554634"}}</pre>
----------------------------	---

Parent topic: [Email Events](#)

Other Agent-Related Events

[AgentOther_InService \(Login Success\)](#)
[AgentOther_ShutdownService \(Logout Success\)](#)
[AgentOther_WasSwaped \(WAS Server Switchover\)](#)
[Agent_Recover \(Agent Recovered\)](#)
[AgentOther_Note \(Note Received\)](#)
[AgentOther_Bulletin \(Bulletin Received\)](#)
[AgentOther_All_Agent_Busy \(All Agents in Busy State\)](#)
[AgentOther_CallInPrivateQueue \(Call Entering a Private Queue\)](#)
[AgentOther_CallOutPrivateQueue \(Call Exiting a Private Queue\)](#)
[AgentOther_BeQcStart \(Inspection on an Agent Started\)](#)
[AgentOther_BeQcStop \(Inspection on an Agent Stopped\)](#)
[Agent_QueueMonitor_Detail \(Monitoring Queue Details\)](#)
[Agentevent_UserLocation_Notify \(Location Information Notification Event\)](#)
[AgentEvent_MSD_Notify \(MSD Data Notification Event\)](#)

Parent topic: [Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

AgentOther_InService (Login Success)

Event Description

This event indicates that an agent logs in successfully.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Set-GUID	string	Indicates the GUID returned after login, which is contained in all the subsequent request messages.
Set-Cookie	string	Indicates the cookie returned after login, which is contained in all the subsequent request messages.
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	list	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentOther_InService","workNo":"49999","content":null}}</pre>
----------------------------	--

Parent topic: [Other Agent-Related Events](#)

AgentOther_ShutdownService (Logout Success)

Event Description

This event indicates that an agent logs out successfully.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
loginTime	string	Indicates the time when the agent successfully logs in, returned by the login interface (timestamp, in milliseconds).

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentOther_ShutdownService","workNo":"49999","content":{"loginTime":"1471585949806"}}}</pre>
----------------------------	---

Parent topic: [Other Agent-Related Events](#)

AgentOther_WasSwaped (WAS Server Switchover)

Event Description

This event indicates that the home WAS server of an agent starts a switchover.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentOther_WasSwaped","workNo":"49999","content":null}}</pre>
----------------------------	--

Parent topic: [Other Agent-Related Events](#)

Agent_Recover (Agent Recovered)

Event Description

This event indicates that an agent recovers after the home WAS server of the agent performs a switchover.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"Agent_Recover","workNo":"49999","content":null}}</pre>
----------------------------	---

Parent topic: [Other Agent-Related Events](#)

AgentOther_Note (Note Received)

Event Description

This event indicates that the current agent receives a note.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3

Table 3 Parameter description of content

Parameter	Data Type	Description
sender	string	Indicates the sender of a note.
receivetime	string	Indicates the time when a note is received (timestamp, in milliseconds).
sendername	string	Indicates the sender name.
timestring	string	Indicates the time when a note is received, in the format yyyy-MM-dd HH:MM:SS.
context	string	Indicates the note content.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentOther_Note", "workNo": "20012", "content": {"sender": "20011", "receivetime": "1477290432230", "sendername": "20011", "timestring": "2016-10-24 06:27:12", "context": "1121212"}}</pre>
----------------------------	---

Parent topic: [Other Agent-Related Events](#)

AgentOther_Bulletin (Bulletin Received)

Event Description

This event indicates that the current agent receives a bulletin.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
sender	string	Indicates the sender of a bulletin.
receivetime	string	Indicates the time when a bulletin is received.
sendername	string	Indicates the sender name.
timestring	string	Indicates the time when a bulletin is received, in the format yyyy-MM-dd HH:MM:SS .
context	string	Indicates the bulletin content.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentOther_Bulletin", "workNo": "20012", "content": {"sender": "20011", "receivetime": "1477290874243", "sendername": "20011", "timestring": "2016-10-24 06:34:34", "context": "1121212"}}</pre>
----------------------------	---

Parent topic: [Other Agent-Related Events](#)

AgentOther_All_Agent_Busy (All Agents in Busy State)

Event Description

This event indicates that all agents are in the Busy state.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentOther_All_Agent_Busy","workNo":"49999","content":null}}</pre>
----------------------------	---

Parent topic: [Other Agent-Related Events](#)

AgentOther_CallInPrivateQueue (Call Entering a Private Queue)

Event Description

This event indicates that a call enters the private skill queue of an agent.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
called	string	Indicates the called number.
caller	string	Indicates the calling number.
callid	string	Indicates the unique call ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentOther_CallInPrivateQueue", "workNo": "49999", "content": {"callid": "1456404171-43", "called": "49999", "caller": "70093"}}</pre>
----------------------------	---

Parent topic: [Other Agent-Related Events](#)

AgentOther_CallOutPrivateQueue (Call Exiting a Private Queue)

Event Description

This event indicates that a call exits the private skill queue of an agent.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
called	string	Indicates the called number.
caller	string	Indicates the calling number.
callid	string	Indicates the unique call ID.
reason	string	Indicates the reason why a call leaves a private queue.
causeid	string	Indicates the ID of the reason.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentOther_CallOutPrivateQueue", "workNo": "49999", "content": {"callid": "1456404171-43", "called": "49999", "caller": "70093", "reason": "abcdefg", "causeid": "1"}}</pre>
----------------------------	---

Parent topic: [Other Agent-Related Events](#)

AgentOther_BeQcStart (Inspection on an Agent Started)

NOTE

This event is only applicable to the VTM scenario.

Event Description

This event indicates that the current agent is inspected by an inspector.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
qcAgentId	string	Indicates the work ID of an inspector.
qcType	int	Indicates the inspection type. 8 : Listen. 9 : Insert.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentOther_BeQcStart", "workNo": "20011", "content": {"qcAgentId": "20016", "qcType": 8}}}</pre>
----------------------------	--

Parent topic: [Other Agent-Related Events](#)

AgentOther_BeQcStop (Inspection on an Agent Stopped)

NOTE

This event is only applicable to the VTM scenario.

Event Description

This event indicates that an inspector stops the inspection on an agent.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
qcAgentId	string	Indicates the work ID of an inspector.
qcType	int	Indicates the inspection type. 8 : Listen. 9 : Insert.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentOther_BeQcStop", "workNo": "20011", "content": {"qcAgentId": "20016", "qcType": 0}}}</pre>
----------------------------	---

Parent topic: [Other Agent-Related Events](#)

Agent_QueueMonitor_Detail (Monitoring Queue Details)

Event Description

An agent monitors the queue of the added to which the agent belongs.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callid	string	Indicates the call ID.
queueid	string	Indicates the queue ID.
caller	string	Indicates the calling number.
called	string	Indicates the called number.
callstarttime	string	Indicates the call start time.
flag	string	Indicates whether the call is in or out of the queue. The value IN indicates in the queue and OUT indicates out of the queue.
renson	string	Indicates the reason why the call is in or out of the queue.
customerlevel	string	Indicates the customer level.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "event": {"eventType": "Agent_QueueMonitor_Detail", "workNo": "103", "content": {"callid": "1539840203-26", "queueid": "1", "caller": "70986", "flag": "IN", "called": "10080", "callstarttime": "2018-10-18 13:23:23", "renson": "0", "customerlevel": "0"}}, "retcode": "0"}</pre>
----------------------------	---

Parent topic: [Other Agent-Related Events](#)

Agentevent_UserLocation_Notify (Location Information Notification Event)

Event Description

This is a dedicated event of the ICP solution. This event is used to push incident reporter location information to a call taker. For the same call, this event may be triggered multiple times.

This event is triggered only when the AML or NG911 location function is deployed at a site. For details about the AML or NG911 location function, see the feature guide in the product documentation.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
caller	string	Indicates the incident reporter number. The value is a numeric string of 1 to 24 digits.
location	string	Indicates the geographical location of the user to be queried.
lbsType	string	Indicates the location information format. The options are as follows: 0: unknown; 1: LbyV; 2: LbyR; 3: AML.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","event":{"eventType":"AgentEvent_UserLocation_Notify","workNo":"105","content":{"caller":"8***6","location":"A\\ML=1112","lbsType":"3"}}, "retcode":"0"}</pre>

NOTE

This event is an internal event between the Agent Server and SMS adapter and cannot be used in other scenarios.

Parent topic: [Other Agent-Related Events](#)

AgentEvent_MSD_Notify (MSD Data Notification Event)

Event Description

This is a dedicated event of the ICP solution. This event is used to push the MSD data carried in the NG-eCall message during an emergency call.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
caller	string	Indicates the incident reporter number. The value is a numeric string of 1 to 24 digits.
callId	string	Indicates the unique call ID.
MSD	string	Indicates the MSD data.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "event": {"eventType": "AgentEvent_MSD_Notify", "workNo": "105", "content": {"caller": "8***6", "callId": "1539840203-26", "MSD": "datadata"}}, "retcode": "0"}</pre>

Parent topic: [Other Agent-Related Events](#)

Extended Interfaces and Events

[Interfaces](#)

[Events](#)

Parent topic: [Agent Server Interfaces \(RESTful\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Interfaces

[Online Agent: onlineagent](#)

[Voice Call: voicecall](#)

[Recording and Playback: recordplay](#)

[Real-Time Quality Control: qualitycontrol](#)

[Agent Event: agentevent](#)

[Configuration Parameter: queryconfig](#)

[Telepresence Call: vccall](#)

[ECC Interfaces: eccconfig](#)

Parent topic: [Extended Interfaces and Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Online Agent: [onlineagent](#)

[Logging In to the CCS Only](#)

[Forcibly Logging In to the CCS Only](#)

[Forcibly Logging In Without Binding the Agent Phone Number](#)

[Setting Self-Recording Function](#)

[Changing the Password](#)

[Setting Indication of Call Forwarding/Call Forwarding on Busy](#)

[Sending a Note](#)

[Binding an Agent Phone Number](#)

[Setting Whether to Answer Incoming Calls](#)

[Publishing a Bulletin](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Logging In to the CCS Only

NOTE

If an agent only logs in to the CCS but does not log in to the media server, the agent does not occupy license resources.

Interface Description

This interface is used to log in to the CCS without logging in to the media server.

Usage Description

1. Prerequisites
 - None
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/loginex
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
Request Body			
password	string	Yes	Indicates the password of an agent. The value contains a maximum of 32 characters.
phonenum	string	No	Indicates the phone number of an agent. The value contains a maximum of 24 characters.
autoanswer	boolean	No	Indicates whether automatic answering is enabled. The default value is true .
autoenteridle	boolean	No	Indicates whether to enter the idle state automatically. The default value is true .
releasephone	boolean	No	Indicates whether an agent enters the non-always-off-hook state after the agent hangs up. The default value is true .
agenttype	int	No	Indicates the type of an agent logged in. The default value is 4 . 4 : PC+phone agent 11 : PC+phone video agent
status	int	No	Indicates the status of an agent right after the agent is logged in. The default status is idle. 4 : idle 5 : work
ip	string	No	Indicates the IP address of an agent. The default value is 127.0.0.1 . (The value contains a maximum of 15 characters.)
pushUrl	string	No	Indicates the URL for receiving an event. The value contains a maximum of 512 characters. If pushUrl is set, the agent event is pushed to the specified URL. For details, see pushUrl Request .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Set-Cookie	string	Indicates the cookie returned after login, which is contained in all the subsequent request messages. NOTE: Modify the following configuration in the agentgateway/WEB-INF/config/basic.properties file: AGENT.COOKIES.WRITEBACK.FLAG = ON The value ON indicates that a cookie is returned; the value OFF indicates that no cookie is returned.
Response Body		

Parameter	Data Type	Description
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
result	Map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
vdnid	string	Indicates the VDN ID.
workno	string	Indicates the work ID of an agent.
mediatype	string	Indicates the media server to which an agent logs in, such as FFF (first character: CTI Server; second character: WebM; third character: MailM).
loginTime	string	Indicates the login time (timestamp, in milliseconds).
isForceChange	boolean	Indicates whether to force an agent to change the password. If the value is true , an agent must change the password after login.
serverName	string	Indicates the cluster name of the Agent Server to which an agent logs in.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/onlineagent/1010/loginex HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"password":"","phonenum":"40038","status":"4","releasephone":"false","agenttype":"4"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"vdnid":1,"workno":"294","mediatype":"FFF","loginTime":"1471585949806","isForceChange":"false","serverName":"AgentGateway"}}</pre>

Triggered Event

- [AgentOther_InService \(Login Success\)](#)
- [AgentState_Ready \(Idle\)](#)

Error Code

- 100-001
- 100-002
- 100-004
- 100-007
- 100-012
- 100-015
- 100-016
- 110-016
- 999-001

Parent topic: [Online Agent: onlineagent](#)

Forcibly Logging In to the CCS Only

NOTE

If an agent only logs in to the CCS but does not log in to the media server, the agent does not occupy license resources.

Interface Description

This interface is used to forcibly log in to the CCS without logging in to the media server.

Usage Description

1. Prerequisites
 - None
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/forceloginex
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
Request Body			
password	string	Yes	Indicates the password of an agent. The value contains a maximum of 32 characters.
phonenumber	string	No	Indicates the phone number of an agent. The value contains a maximum of 24 characters.
autoanswer	boolean	No	Indicates whether automatic answering is enabled. The default value is true .
autoenteridle	boolean	No	Indicates whether to enter the idle state automatically. The default value is true .
releasephone	boolean	No	Indicates whether an agent enters the non-always-off-hook state after the agent hangs up. The default value is true .
agenttype	int	No	Indicates the type of an agent logged in. The default value is 4 . 4: PC+phone agent 11: PC+phone video agent
status	int	No	Indicates the status of an agent right after the agent is logged in. The default status is idle. 4: idle 5: work
ip	string	No	Indicates the IP address of an agent. The default value is 127.0.0.1 . (The value contains a maximum of 15 characters.)
pushUrl	string	No	Indicates the URL for receiving an event. The value contains a maximum of 512 characters. If pushUrl is set, the agent event is pushed to the specified URL. See pushUrl Request .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Set-Cookie	string	Indicates the cookie returned after login, which is contained in all the subsequent request messages. Modify the following configuration in the agentgateway/WEB-INF/config/basic.properties file: AGENT.COOKIE.WRITEBACK.FLAG = ON The value ON indicates that a cookie is returned; the value OFF indicates that no cookie is returned.
Response Body		
message	string	Indicates the message description.

Parameter	Data Type	Description
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
vdnid	string	Indicates the VDN ID.
workno	string	Indicates the work ID of an agent.
mediatype	string	Indicates the media server to which an agent logs in, such as FFF (first character: CTI Server; second character: WebM; third character: MailM).
loginTime	string	Indicates the login time (timestamp, in milliseconds).
isForceChange	string	Indicates whether to force an agent to change the password. If the value is true , an agent must change the password after login.
serverName	string	Indicates the cluster name of the Agent Server to which an agent logs in.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/onlineagent/1010/forceloginex HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"password":"","phonenum":"","status":"4","releasephone":"false","agenttype":"4"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"vdnid":1,"workno":"291","mediatype":"FFF","loginTime":"1471585949806","isForceChange":"false","serverName":"AgentGateway"}}</pre>

Triggered Event

- [AgentOther_InService \(Login Success\)](#)
- [AgentState_Ready \(Idle\)](#)

Error Code

- 100-001
- 100-002
- 100-004
- 100-007
- 100-012
- 100-015
- 100-016
- 110-016
- 999-001

Parent topic: [Online Agent: onlineagent](#)

Forcibly Logging In Without Binding the Agent Phone Number

NOTE

If an agent only logs in to the CCS but does not log in to the media server, the agent does not occupy license resources.

Interface Description

This interface is used to forcibly log in an agent without binding the phone number.

Usage Description

1. Prerequisites
 - None
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/forceloginexwithoutphone
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
Request Body			
password	string	Yes	Indicates the password of an agent. The value contains a maximum of 32 characters.
phonenumber	string	No	Indicates the phone number of an agent. The value contains a maximum of 24 characters.
autoanswer	boolean	No	Indicates whether automatic answering is enabled. The default value is true .
autoenteridle	boolean	No	Indicates whether to enter the idle state automatically. The default value is true .
releasephone	boolean	No	Indicates whether an agent enters the non-always-off-hook state after the agent hangs up. The default value is true .
agenttype	int	No	Indicates the type of an agent logged in. The default value is 4 . 4 : PC+phone agent 11 : PC+phone video agent
status	int	No	Indicates the status of an agent right after the agent is logged in. The default status is idle. 4 : idle 5 : work
ip	string	No	Indicates the IP address of an agent. The default value is 127.0.0.1 . (The value contains a maximum of 15 characters.)
entryip	string	No	Indicates the IP address of the Agent Gateway that the agent client connects to.
pushUrl	string	No	Indicates the URL for receiving an event. The value contains a maximum of 512 characters. If pushUrl is set, the agent event is pushed to the specified URL. See pushUrl Request .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Set-Cookie	string	Indicates the cookie returned after login, which is contained in all the subsequent request messages. Modify the following configuration in the agentgateway/WEB-INF/config/basic.properties file: AGENT.COOKIE.WRITEBACK.FLAG = ON The value ON indicates that a cookie is returned; the value OFF indicates that no cookie is returned.
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows:

Parameter	Data Type	Description
		• 0: Succeed • Other values: Fail
result	Map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
vdnid	string	Indicates the VDN ID.
workno	string	Indicates the work ID of an agent.
mediatype	string	Indicates the media server to which an agent logs in, such as TTT (first character: CTI Server; second character: WebM; third character: MailM).
loginTime	string	Indicates the login time (timestamp, in milliseconds).
isForceChange	string	Indicates whether to force an agent to change the password. If the value is true , an agent must change the password after login.
serverName	string	Indicates the cluster name of the Agent Server to which an agent logs in.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/onlineagent/1010/forceloginexwithoutphone HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"password":"","phonenum":"","status":"4","releasephone":"false","agenttype":"4"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"vdnid":1,"workno":"291","mediatype":"FFF","loginTime":"1471585949806","isForceChange":"false","serverName":"AgentGateway"}}</pre>

Triggered Event

- [AgentOther_InService \(Login Success\)](#)
- [AgentState_Ready \(Idle\)](#)

Error Code

- 100-001
- 100-002
- 100-004
- 100-007
- 100-012
- 100-015
- 100-016
- 110-016
- 999-001

Parent topic: [Online Agent: onlineagent](#)

Setting Self-Recording Function

Interface Description

This interface is used to set whether the agent self-recording function is enabled.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/setselfrecord/{recordflag}/{recordbeforetalking}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
recordflag	int	Yes	Indicates whether the self-recording function is enabled (the value 1 indicates that the self-recording function is enabled and the value 0 indicates that the self-recording function is disabled).
recordbeforetalking	int	Yes	Indicates whether automatic recording starts before call pickup. 1 : Start automatic recording before call pickup. 0 : Start automatic recording after call pickup.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/onlineagent/{agentid}/setselfrecord/0/0 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007

Parent topic: [Online Agent: onlineagent](#)

Changing the Password

NOTE

The password parameter of this interface is transmitted over URL packets, resulting in security risks. As a result, this interface is discarded since IPCC V200R001C80. An interface for changing the password (extended) is used to replace this interface. However, this interface is still valid actually to support sites that adopt earlier versions.

Interface Description

This interface is used to change a password.

NOTE

1. The length of the new password must be from 8 to 32 characters.
2. The new password cannot contain more than 2 duplicate characters.
3. The new password cannot contain more than 3 consecutive characters in the work ID.
4. The new password contains more than 3 types in upper case letter, lower case letter, a number and special character.
5. The new password must be different from the last 5 passwords (It can be configured in the WAS).

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/modifyaccountpwd?oldpassword={oldpassword}&newpassword={newpassword}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
oldpassword	string	Yes	Indicates the original password. The value contains a maximum of 32 characters.
newpassword	string	Yes	Indicates the new password. The value contains a maximum of 32 characters.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/onlineagent/1010/modifyaccountpwd?oldpassword=xxxx&newpassword=xxxx HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0" }

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Online Agent: onlineagent](#)

Setting Indication of Call Forwarding/Call Forwarding on Busy

Interface Description

This interface is used to set the indicator of call forwarding or call forwarding on busy.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/setforwarding
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
destdevicetype	int	No	Indicates the destination device type. The options are 1 (queue), 2 (agent), and 3 (IVR). The default value is 2 .
destdevice	string	Yes	Indicates the destination device description. Queue: queue ID Agent: work ID IVR: process ID It can be blank.
opertype	int	No	Indicates the operation type. The default value is 1 , and the value range is from 0 to 2 (0: canceling call forwarding, 1: call forwarding, 2: call forwarding on busy). When this parameter is set to 0 , destdevicetype and destdevice can be empty.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/onlineagent/1010/setforwarding HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"destdevicetype":2,"destdevice":"agent:49999","opertype":0}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Online Agent: onlineagent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Sending a Note

NOTE

The note content parameter of this interface is transmitted over URL packets, resulting in security risks. As a result, this interface is discarded since IPCC V200R001C60. An interface for sending a note (extended) is used to replace this interface. However, this interface is still valid actually to support sites that adopt earlier versions.

Interface Description

This interface is no longer used and is replaced by the extended interface for sending notes.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - This interface is used in user login mode and supports user name sending.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/sendnotelet/{receiver}?content={content}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of the sender agent.
receiver	string	Yes	Indicates the work ID of the recipient agent. A maximum of 100 recipient agents are supported, with work IDs segmented by the semicolon (;). The value contains a maximum of 600 characters.
content	string	Yes	Indicates the note content. Length: 0 to 4096 bytes
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	array	Indicates the work ID of a recipient who fails to receive the note.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/onlineagent/1010/sendnotelet/1011;1012?content=xxxxx HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": []}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Online Agent: onlineagent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Binding an Agent Phone Number

NOTE

This interface is applicable only to SAP CRM connection.

Interface Description

This interface is used by an agent to bind a phone number.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - This interface is used in user login mode and supports user name sending.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/bindphone
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
phonenum	string	Yes	Indicates the phone number of an agent.
autoanswer	boolean	No	Indicates whether automatic answering is enabled. The default value is true .
autoenteridle	boolean	No	Indicates whether to enter the idle state automatically. The default value is true .
releasephone	boolean	No	Indicates whether an agent enters the non-always-off-hook state after the agent hangs up. The default value is false .
agenttype	int	No	Indicates the type of an agent logged in. The default value is 4 . 4 : PC+phone agent 11 : PC+phone video agent
status	int	No	Indicates the status of an agent right after the agent is logged in. The default status is idle. 4 : idle 5 : work

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the returned WAS VDN of an agent after successful binding.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/onlineagent/1010/bindphone HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1</pre>

Example Type	Reference Format
	Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 { "phonenum": "40038", "status": "4", "releasephone": "false", "agenttype": "4" }
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": 1 }

Triggered Event

- None

Error Code

- 100-001
- 100-007
- 100-011
- 100-013

Parent topic: [Online Agent: onlineagent](#)

Setting Whether to Answer Incoming Calls

Interface Description

This interface is used to set whether an agent answers incoming calls.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/settalkright?flag={flag}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
flag	int	Yes	Indicates whether an agent answers incoming calls (1: yes; 0: no).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/onlineagent/1010/settalkright?flag=0 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-007

Parent topic: [Online Agent: onlineagent](#)

Publishing a Bulletin

Interface Description

This interface is used by an agent to publish a bulletin.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/onlineagent/{agentid}/notifybulletin
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
targettype	int	Yes	Indicates the bulletin publishing type. 0 : agent group 1 : skill queue
bulletindata	string	Yes	Indicates the bulletin data. The value contains a maximum of 900 characters.
targetname	string	Yes	Indicates the name of an agent group or skill queue. The value contains a maximum of 100 characters.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/onlineagent/1010/notifybulletin HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"targettype":0,"bulletindata":"Bulletin data","targetname":"voice_class"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006

- 100-007

Parent topic: [Online Agent: onlineagent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Voice Call: voicecall

[Making a Previewed Outgoing Call](#)

[Reporting Sound](#)

[Performing Two-Stage Dialing](#)

[Requesting a Call](#)

[Freezing Image](#)

[Unfreezing Image](#)

[Releasing the Connection of a Specified Phone Number](#)

[Hanging Up](#)

[Dropping a Call \(for VTM\)](#)

[Sending the SiplInfo Message](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Making a Previewed Outgoing Call

Interface Description

This interface is used by an agent that has logged in to make a previewed outgoing call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is not answering any call (except a held call).
 - The agent receives an AgentEvent_Preview event.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/previewcallout
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
called	string	Yes	Indicates the called number. This parameter is mandatory. It contains 1 to 24 digits and special characters * or #.
callcontrolid	long	Yes	Indicates the control block ID. This parameter is mandatory for a previewed outgoing call manually initiated and is obtained from controlid in the attached information of the AgentEvent_Preview (Previewed Outgoing Call Initiated) event.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/voicecall/1010/previewcallout HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000 {"called": "40040", "callcontrolid": 1456404043}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0"}</pre>

Triggered Event

- If the interface is successfully invoked, the agent receives the following events:
 - [AgentOther_PhoneAlerting \(Phone in Ringing State\)](#)
 - [AgentOther_PhoneOffhook \(Phone in Off-Hook State\)](#)

[AgentState_Busy \(Talking\)](#)

[AgentEvent_Customer_Alerting \(Customer Ringing\)](#)

[AgentEvent_Talking \(Turning to the Talking State\)](#)

- If the interface fails to be invoked, the agent receives the following event:

[AgentEvent_Call_Out_Fail \(Making an Outgoing Call Unsuccessfully\)](#)

Error Code

- 100-006
- 100-007
- 200-001

Parent topic: [Voice Call: voicecall](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Reporting Sound

Interface Description

This interface is used by an agent to report sound during a call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has established a call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/reportsound
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
soundtype	int	No	Indicates the type of sound reporting. The value 0 indicates releasing the call after sound reporting and the value 1 indicates holding the call after sound reporting. The default value is 0 .
soundcode	int	No	Indicates the speech code. The value 0 indicates Mandarin, the value 1 indicates English, and the value 2 indicates dialect. The default value is 0 .
telnum	string	Yes	Indicates the number of the phone to which the sound is reported. The value is a string of 1-24 digits.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/reportsound HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000 {"soundtype":1,"soundcode":0,"telnum":"40038"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006

- 100-007
- 200-009

Parent topic: [Voice Call: voicecall](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Performing Two-Stage Dialing

NOTE

Because this interface does not support "#", it is discarded since IPCC V200R001C80. It can be replaced by the interface for two-stage dialing (extended). However, this interface is still valid actually to support sites that adopt earlier versions.

Interface Description

This interface is used by an agent to perform two-stage dialing during a call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has established a call.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/seconddial/{number}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
number	string	Yes	Indicates the number to be dialed for the second time. The value consists of 1 to 24 digits or asterisk (*).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/seconddial/139254687843 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 000-002

- 100-006
- 100-007

Parent topic: [Voice Call: voicecall](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Requesting a Call

NOTE

An agent cannot request a call when having a call placed on held.

Interface Description

This interface is used to request a call from the public or private call queue.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - Queuing calls exist in the public queue or private queue of the agent.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/requestcall/{callid}/{skilltype}?skillid={skillid}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
callid	string	Yes	Indicates the ID of the queuing call.
skilltype	int	Yes	Indicates the skill queue type (the value 0 indicates the public queue and the value 1 indicates the private queue).
skillid	string	Yes	Indicates the skill queue ID (valid only for the public queue).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/requestcall/ 1476070409-38/0?skillid=12 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- If the interface is successfully invoked, the agent receives the following events:
[AgentOther_PhoneAlerting \(Phone in Ringing State\)](#)

[AgentOther_PhoneOffhook \(Phone in Off-Hook State\)](#)

[AgentState_Busy \(Talking\)](#)

[AgentState_Work \(Working\)](#)

[AgentEvent_Customer_Alerting \(Customer Ringing\)](#)

[AgentEvent_Talking \(Turning to the Talking State\)](#)

- If the interface fails to be invoked, the agent receives the following event:

[AgentEvent_Call_Out_Fail \(Making an Outgoing Call Unsuccessfully\)](#)

Error Code

- 100-006
- 100-007

Parent topic: [Voice Call: voicecall](#)

Freezing Image

Interface Description

This interface is used by an agent to freeze the image of an ongoing call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in an ongoing video call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/beginmutevideo
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/beginmutevideo HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 200-019
- 200-020

Parent topic: [Voice Call: voicecall](#)

Unfreezing Image

Interface Description

This interface is used by an agent to unfreeze a frozen call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has frozen an ongoing video call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/endmutevideo
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/endmutevideo HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 200-021
- 200-022

Parent topic: [Voice Call: voicecall](#)

Releasing the Connection of a Specified Phone Number

Interface Description

This interface is used by an agent to release the connection of a specified phone number.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in an ongoing call.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/disconnect/{number}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
number	string	Yes	Indicates the number to be released (1-24 digits).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/voicecall/1010/disconnect/70223 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 200-023
- 200-024

Parent topic: [Voice Call: voicecall](#)

Hanging Up

Interface Description

This interface is used by an agent to hang up the phone that has an ongoing voice call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in an ongoing voice call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/releasephone
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/voicecall/1010/releasephone HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- [AgentEvent_Call_Release \(Agent Exiting a Call\)](#)
- [AgentEvent_Customer_Release \(User Exiting a Call\)](#)

Error Code

- 100-006
- 100-007
- 200-017

Parent topic: [Voice Call: voicecall](#)

Dropping a Call (for VTM)

Interface Description

This interface is used by an agent to drop an ongoing voice call (for VTM).

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in an ongoing voice call.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/voicecall/1010 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- [AgentEvent_Call_Release \(Agent Exiting a Call\)](#)
- [AgentEvent_Customer_Release \(User Exiting a Call\)](#)

Error Code

- 100-006
- 100-007
- 200-017

Parent topic: [Voice Call: voicecall](#)

Sending the SipInfo Message

Interface Description

This interface is used by an agent to send the SipInfo message to the peer.

NOTE

The SipInfo message cannot be sent during the internal call, three-party call, and three-party help call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is in an ongoing voice call.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/voicecall/{agentid}/sendsipinfo
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
callId	String	Yes	Indicates the unique call ID. It supports a maximum of 30 characters.
dataType	int	No	Indicates the content type. 0 : DTMF digits 1 : text The default value is 0 .
data	string	Yes	Indicates the sent content. It supports a maximum of 255 characters.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/voicecall/1010/sendsipinfo HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"callId":"1476069477-32", "dataType":0,"data":"12"}</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0" }

Triggered Event

None

Error Code

- 000-002
- 100-006
- 100-007

Parent topic: [Voice Call: voicecall](#)

Recording and Playback: recordplay

[Starting Recording](#)

[Starting Recording \(File Name Automatically Generated by the System\)](#)

[Pausing Recording](#)

[Resuming Recording](#)

[Stopping Recording](#)

[Starting Screen Recording](#)

[Stopping Screen Recording](#)

[Obtaining the Screen Recording Authentication Information](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Starting Recording

Interface Description

This interface is used to start recording for an agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/record?filename={filename}
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
filename	string	Yes	Indicates the recording drive letter. To be compatible with earlier versions, the value contains a maximum of 100 characters. However, the system uses only the first character as the drive letter.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/recordplay/1010/record?filename=xxxxx HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- If the interface is successfully invoked, the agent receives the following events:

[AgentMediaEvent_Record \(Recording Started\)](#)

- If the interface fails to be invoked, the agent receives the following event:

[AgentMediaEvent_Record_Fail \(Recording Start Failed\)](#)

Error Code

- 000-002
- 100-006
- 100-007

- 500-008

Parent topic: [Recording and Playback: recordplay](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Starting Recording (File Name Automatically Generated by the System)

Interface Description

This interface is used to start recording for an agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/recordwithoutfilename
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/recordplay/1010/recordwithoutfilename HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- If the interface is successfully invoked, the agent receives the following events:

[AgentMediaEvent_Record \(Recording Started\)](#)

- If the interface fails to be invoked, the agent receives the following event:

[AgentMediaEvent_Record_Fail \(Recording Start Failed\)](#)

Error Code

- 000-002
- 100-006
- 100-007
- 500-008

Pausing Recording

NOTE

This interface is not supported in IPCC V200R001C80.

Interface Description

This interface is used to pause recording for an agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is being recorded.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/pauserecord
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/recordplay/1010/pauserecord HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0"}</pre>

Triggered Event

- [AgentMediaEvent_PauseRecordDone \(Recording Paused\)](#)

Error Code

- 100-006
- 100-007
- 500-004

Parent topic: [Recording and Playback: recordplay](#)

Resuming Recording

NOTE

This interface is not supported in IPCC V200R001C80.

Interface Description

This interface is used to resume recording.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has paused recording.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/resumerecord
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/recordplay/1010/resumerecord HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- [AgentMediaEvent_ResumeRecordDone \(Recording Resumed\)](#)

Error Code

- 100-006
- 100-007
- 500-006

Parent topic: [Recording and Playback: recordplay](#)

Stopping Recording

Interface Description

This interface is used to stop recording for an agent.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent is being recorded.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/stoprecord
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/recordplay/1010/stoprecord HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- [AgentMediaEvent_StopRecordDone \(Recording Stopped\)](#)

Error Code

- 100-006
- 100-007
- 500-010

Parent topic: [Recording and Playback: recordplay](#)

Starting Screen Recording

Interface Description

This interface is used to start screen recording.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The video record client (VRC) component is successfully initialized at the agent side.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/startrecordscreen
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/recordplay/1010/startrecordscreen HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- If the interface is successfully invoked, the agent receives the following event:

[AgentMediaEvent_StartRecordScreen_Succ \(Starting Screen Recording Succeeded\)](#)

- If the interface fails to be invoked, the agent receives the following event:

[AgentMediaEvent_StartRecordScreen_Fail \(Starting Screen Recording Failed\)](#)

Error Code

- 100-006
- 100-007

Parent topic: [Recording and Playback: recordplay](#)

Stopping Screen Recording

Interface Description

This interface is used to stop screen recording.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The VRC component is successfully initialized at the agent side.
 - Screen recording of the agent is in process.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/stoprecordscreen
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/recordplay/1010/stoprecordscreen HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- If the interface is successfully invoked, the agent receives the following event:
[AgentMediaEvent_StopRecordScreen_Succ \(Stopping Screen Recording Succeeded\)](#)
- If the interface fails to be invoked, the agent receives the following event:
[AgentMediaEvent_StopRecordScreen_Fail \(Stopping Screen Recording Failed\)](#)

Error Code

- 100-006
- 100-007

Parent topic: [Recording and Playback: recordplay](#)

Obtaining the Screen Recording Authentication Information

Interface Description

This function is used to obtain the authentication information when screen recording is started, used for VRC authentication.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The VRC component is successfully initialized at the agent side.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/recordplay/{agentid}/getconnecttoken
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	See Table 3 .

Table 3 Authentication information

Parameter	Data Type	Description
token	string	Authentication information

Interface Example

Example Type	Reference Format
Example of a request packet	GET /agentgateway/resource/recordplay/1010/getconnecttoken HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "token": "123456789198765432111212" } }

Triggered Event

None

Error Code

- 100-006
- 100-007

Real-Time Quality Control: [qualitycontrol](#)

[Switching Between Listening and Inserting](#)

[Making an Agent Rest Forcibly](#)

[Configuring Automatic Recording for an Inspected Agent](#)

[Canceling Automatic Recording for an Inspected Agent](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Switching Between Listening and Inserting

Interface Description

This interface is used by an inspector that has logged in to switch between listening and inserting on a specified agent.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/switch/{workNo}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
workNo	int	Yes	Indicates the work ID of the specified agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1010/switch/1011 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Making an Agent Rest Forcibly

Interface Description

This interface is used by an inspector that has logged in to make a specified agent rest forcibly.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/forcerest/{workNo}/{time}/{reason}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
workNo	int	Yes	Indicates the work ID of the specified agent.
time	int	Yes	Indicates the rest duration, in seconds. The value ranges from 1 to 86399.
reason	int	Yes	Indicates the reason of rest. The value ranges from 1 to 255.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1010/forcerest/1011/3000/1 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 100-006
- 900-001
- 900-002
- 900-003

Configuring Automatic Recording for an Inspected Agent

Interface Description

This interface is used by an inspector that has logged in to configure automatic recording for an inspected agent.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/setselfrecord/{recordflag}/{recordbeforetalking}?agents={agents}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
recordflag	int	Yes	Indicates whether to enable automatic recording (1: yes 0: no).
recordbeforetalking	int	Yes	Indicates whether automatic recording starts before call pickup. 1: Start automatic recording before call pickup. 0: Start automatic recording after call pickup.
agents	string	Yes	Indicates the work ID of the agent to be inspected. (For multiple agents, separate the IDs with the semicolon (;). The maximum length is 100 characters.)
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1010/setselfrecord/0/0?agents=1011 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007

- 900-001

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Canceling Automatic Recording for an Inspected Agent

Interface Description

This interface is used by an inspector that has logged in to cancel automatic recording for an inspected agent.

Usage Description

1. Prerequisites
 - The agent has logged in as an inspector.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/qualitycontrol/{agentid}/cancelselfrecord?agents={agents}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
agents	string	Yes	Indicates the work ID of the agent to be inspected. (For multiple agents, separate the IDs with the semicolon (;). The maximum length is 100 characters.)
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/qualitycontrol/1010/cancelselfrecord?agents=1011 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 100-007
- 900-001

Parent topic: [Real-Time Quality Control: qualitycontrol](#)

Agent Event: agentevent

[AGENT POLL Mode](#)

[HTTP PUSH Mode](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

AGENT POLL Mode

[Obtaining All Agent Events by Polling](#)

Parent topic: [Agent Event: agentevent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Obtaining All Agent Events by Polling

Interface Description

This interface is used to obtain all agent events by polling.

Usage Description

1. Prerequisites

Configurations in the **basic.properties** file have been modified as follows:

EVENT_METHOD = AGENT_POLL

GET_EVENT_MODE = 2

2. Precautions

- This interface is designed for obtaining associated events of all agents that have logged in to a specific Agent Gateway. The events are obtained by polling in short HTTP connection mode.
- Only one third-party service can connect to one Agent Gateway.

3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/agentevent/allagentevent
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
event	list	Indicates an agent event. For the parameter description of event , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the content of an event. The definition varies with the event.

Interface Example

Example Type	Reference Format
Example of a request packet	GET /agentgateway/resource/agentevent/allagentevent HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 { "message": "", "retcode": "0", "event": [{ "eventType": "AgentOther_InService", "workNo": "291", "content": null }, { "eventType": "AgentOther_InService", "workNo": "49999", "content": null }] }

Triggered Event

- None

Error Code

- 000-001

Parent topic: [AGENT POLL Mode](#)

Copyright © Chengdu TD-Tech Co., Ltd.

HTTP PUSH Mode

[Sending Agent Events to a Specified Service](#)

Parent topic: [Agent Event: agentevent](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Sending Agent Events to a Specified Service

Interface Description

This interface is used to send agent events to a specified service.

Usage Description

1. Prerequisites

- The specified service needs to provide a URL to the Agent Gateway service for receiving events that are sent by the Agent Gateway.
- Configurations in the **basic.properties** file have been modified as follows:
 - EVENT_METHOD = HTTP_PUSH
 - HTTP_PUSH_URL = https://127.0.0.1:8043/SAP/SapAdapterEventServlet

Currently, the Agent Gateway supports only HTTP basic authentication on the URL provided by the specified service. To implement HTTP basic authentication on the URL, configure parameters as follows:

- HTTP_PUSH_URL_BASIC_AUTH_USERNAME=sap
- HTTP_PUSH_URL_BASIC_AUTH_PASSWORD.password=
- HTTP_PUSH_URL_BASIC_AUTH_PASSWORD.encryptpassword=G6+cVqpxv0ACW/Dc5SQIGw==:juZX/pUASSBuWG2yEe5w5w==

If the URL starts with "https", configure the certificate and password for the service as follows:

- HTTP_PUSH_TRUST_KEYSTORE_FILE =keystore/.keystore
- HTTP_PUSH_TRUST_KEYSTORE_PASSWORD.password =
- HTTP_PUSH_TRUST_KEYSTORE_PASSWORD.encryptpassword=G6+cVqpxv0ACW/Dc5SQIGw==:juZX/pUASSBuWG2yEe5w5w==

2. Precautions

- This interface is designed for obtaining associated events of all agents that have logged in to a specific Agent Gateway. The obtained agent events are then sent to the specified service in HTTP mode.
- In this mode, users do not need to invoke the event obtaining interface of the Agent Gateway.

3. Use restrictions

None

Interface Prototype

Request URL	https://127.0.0.1:8043/SAP/SapAdapterEventServlet (HTTP_PUSH_URL in basic.properties)
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
eventType	string	Yes	Indicates the event type.
workNo	string	Yes	Indicates the work ID of an agent.
content	object	Yes	Indicates the content of an event. The definition varies with the event.

Response Message

- None

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/agentevent/allagentevent HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000 {"eventType": "AgentOther_InService", "workNo": "291", "content": null}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8</pre>

Triggered Event

- None

Error Code

- None

Configuration Parameter: queryconfig

[Obtaining the Operation Parameters of a Multimedia Client](#)

[Obtaining the Media Gateway Information](#)

[Obtaining VDN System Configuration Information](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Obtaining the Operation Parameters of a Multimedia Client

Interface Description

After logging in to the system, the agent obtains the operation parameters of a multimedia client.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queryconfig/{agentid}/getclientparam
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
LogLevel	int	Indicates the log level. The options are as follows: 0 : Error 1 : Warning 2 : Info 3 : Debug
LogKeepDays	int	Indicates the number of days for which the log is kept. The value ranges from 0 to 3650 . 0 indicates that the log will not be deleted.
SipLocalPort	int	Indicates the voice SIP port of the client.
RtpLocalPort	int	Indicates the voice media port of the client.
SipTransMode	int	Indicates the SIP transmission mode. The options are as follows: 1 : UDP 2 : TLS 3 : TCP
RtpTransMode	int	Indicates the media transmission mode. The options are as follows: 0 : Both Real-time Transport Protocol (RTP) and Secure RTP (SRTP) are supported. 1 : Only RTP is supported.

Parameter	Data Type	Description
		2: Only SRTP is supported.
RegisterMode	int	Indicates the phone number registration mode. The options are as follows: 0: Simultaneous registration 1: Sequential registration
AgentLoginState	int	Indicates the initial state of an agent after the agent logs in to the system. The options are as follows: 4: idle 5: work
AgentReleaseState	int	Indicates the status that an agent enters after the agent release the call. 4: idle 5: work
EntryVrp	string	Indicates the IP address and port number of an entry video record process (VRP). Values of multiple VRPs are separated using commas (,), for example: "10.177.254.207(6600),10.114.12.12(6100)" A maximum of five VRPs are supported.
RecordType	int	Indicates the recording type. The options are as follows: 1: single-screen 2: double-screen
ScreenNo	int	Indicates the screen number. The options are as follows: 0: main screen 1: extended screen
VideoDevices	array	Indicates a camera configuration object. For the parameter description of VideoDevices , see Table 4 .

Table 4 Parameter description of **VideoDevices**

Parameter	Data Type	Description
No	int	Indicates the number of a camera.
Type	int	Indicates the camera type. The options are as follows: 1: primary camera 2: extended camera
Name	string	Indicates the camera name.
VideoFrameRate	int	Indicates the video frame rate of the camera.
VideoResolution	int	Indicates the video resolution of the camera. 1280 x 720 960 x 720 704 x 576 640 x 480 352 x 288 320 x 240 176 x 144 160 x 120
Desc	string	Provides the camera description.

Interface Example

Example Type	Reference Format
Example of a request packet	GET /agentgateway/resource/queryconfig/1010/getclientparam HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "LogLevel": 2, "LogKeepDays": 100, "SipLocalPort": 2048, "RtpLocalPort": 2048, "SipTransMode": 2, "RtpTransMode": 2, "RegisterMode": 1, "AgentLoginState": 4, "AgentReleaseState": 4, "EntryVrp": "10.175.1.1(6100),10.175.1.3(6100)", "RecordType": 2, "ScreenNo": 1, "VideoDevices": [{ "No": 1, "Type": 1, "Name": "CAM1", "VideoFrameRate": 30, "VideoResolution": "1280*720", "Desc": "CAM1"}], [{"No": 2, "Type": 2, "Name": "CAM2", "VideoFrameRate": 25, "VideoResolution": "640*480", "Desc": "CAM2"}]} } }

Triggered Event

- None

Error Code

- 100-006
- 800-001
- 800-002

Parent topic: [Configuration Parameter: queryconfig](#)

Obtaining the Media Gateway Information

Interface Description

This interface is used by an agent to obtain media gateway information after login.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queryconfig/{agentid}/requiremediagwinfo
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
mgelp	string	Indicates the entry IP address of the media gateway.
mgePort	int	Indicates the entry port of the media gateway.
mgeDomain	string	Indicates the domain name of the media gateway.

Interface Example

Example Type	Reference Format
Example of a request packet	GET /agentgateway/resource/queryconfig/1010/requiremediagwinfo HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "mgePort": 1064, "mgeIp": "127.0.0.1", "mgeDomain": "test.com" } }

Triggered Event

- None

Error Code

- 100-006
- 800-001
- 800-002

Parent topic: [Configuration Parameter: queryconfig](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Obtaining VDN System Configuration Information

Interface Description

This interface is used by an agent to obtain VDN system configuration information after login.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/queryconfig/{agentid}/vdninfo
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
systemAni	string	Indicates the system calling number.
vdnName	string	Indicates the VDN name.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/queryconfig/1010/vdninfo HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"systemAni":"10086","vdnName":"jst"}}</pre>

Triggered Event

- None

Error Code

- 100-006
- 800-002

Telepresence Call: vccall

[Answering a Call](#)

[Ending a Call](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Answering a Call

NOTE

Currently, telepresence calls are applicable only to the ECC scenario.

Interface Description

This interface is used by an agent to answer a call when receiving the [AgentVCCall_Ringing \(Call Ringing\)](#) event.

NOTE

The telepresence call does not support call rejection during ringing.

Usage Description

- Prerequisites
 - The agent has logged in.
 - The agent has been configured with a telepresence call skill queue.
 - The agent has signed in the WebM server.
- Precautions
 - None
- Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/vccall/{agentid}/answer
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/vccall/1010/answer HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- After the agent successfully answers the call and joins the conference on the user side, the agent receives the following event:
[AgentVCCall_Connected \(Call Setup\)](#)

- If a call is not answered for a long period of time, the agent receives the following events:

[AgentVCCall_NoAnswer \(No Answering of a Telepresence Call\)](#)

[AgentVCCall_Release \(Call Released\)](#)

Error Code

- 100-006
- 100-007
- 200-026

Parent topic: [Telepresence Call: vccall](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Ending a Call

Interface Description

This interface is used by an agent to end a call.

Usage Description

1. Prerequisites
 - The agent has logged in.
 - The agent has received the [AgentVCCall_Connected \(Call Setup\)](#) event.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/vccall/{agentid}/drop
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/vccall/1010/drop HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- [AgentVCCall_Release \(Call Released\)](#)

Error Code

- 100-006
- 100-007
- 200-026

Parent topic: [Telepresence Call: vccall](#)

ECC Interfaces: eccconfig

[Adding Agent Skill Queue Monitoring](#)

[Removing Agent Skill Queue Monitoring](#)

[Querying a Specified Wireless Device](#)

[Querying All Wireless Devices](#)

[Applying for Wireless Device Resources](#)

[Releasing Wireless Device Resources](#)

[Setting VoiceCodes Recording Parameters](#)

[Setting VoiceCodes Recording Parameters \(Extended\)](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Adding Agent Skill Queue Monitoring

Interface Description

This interface is used by an agent to add skill queue monitoring after login.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/queuemonitor?queueId={queueId}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
queueId	int	No	Indicates the ID of a skill queue. The value is number of 1 to 6 digits. If this parameter is left empty, the agent adds monitoring of all skill queues).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/eccconfig/1010/queuemonitor?queueId=10010 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 103-014
- 103-015
- 103-026

Removing Agent Skill Queue Monitoring

Interface Description

This interface is used by an agent to remove skill queue monitoring based on the skill queue ID after login.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/queuemonitor?queueId={queueId}
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
queueId	int	No	Indicates the ID of a skill queue. The value is number of 1 to 6 digits. If this parameter is left empty, the agent removes monitoring of all skill queues).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/eccconfig/1010/queuemonitor?queueId= HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 103-016
- 103-026

Parent topic: [ECC Interfaces: eccconfig](#)

Querying a Specified Wireless Device

Interface Description

This interface is used by an agent to query a specified wireless device based on the device ID after login.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/wirelessdevice?deviceId={deviceId}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
deviceId	string	Yes	Indicates the ID of a device (the value contains a maximum of 36 characters and cannot be empty).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	list	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
lockId	string	Indicates the lock ID.
deviceId	string	Indicates the ID of a device.
deviceDesc	string	Indicates the device description.
deviceState	string	Indicates the device status.
Indicates the ID of an agent.	string	Indicates the ID of an agent.
lockDate	long	Indicates the locking time (timestamp, in milliseconds).
channel	string	Indicates the channel.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/eccconfig/1010/wirelessdevice?deviceId=xxx HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{ "lockId": "5549DA4A2C5119ABE053F0C6A20AB5AC", "deviceId": "1", "deviceDesc": "test1", "deviceState": "BUSY", "agentId": "6004", "lockDate": 1501176459000, "channel": null }] }

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 103-018
- 103-026

Parent topic: [ECC Interfaces: eccconfig](#)

Querying All Wireless Devices

Interface Description

This interface is used by an agent to query all wireless devices after login.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/allwirelessdevice
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	list	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
lockId	string	Indicates the lock ID.
deviceId	string	Indicates the ID of a device.
deviceDesc	string	Indicates the device description.
deviceState	string	Indicates the device status.
agentId	string	Indicates the ID of an agent.
lockDate	long	Indicates the locking time (timestamp, in milliseconds).
channel	string	Indicates the channel.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /agentgateway/resource/eccconfig/1010/allwirelessdevice HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{"lockId": "5549DA4A2C5119ABE053F0C6A20AB5AC", "deviceId": "1", "deviceDesc": "test1", "deviceState": "BUSY", "agentId": "6004", "lockDate": 1501176459000, "channel": null}]

Triggered Event

- None

Error Code

- 100-006
- 100-007
- 100-008
- 103-019
- 103-026

Parent topic: [ECC Interfaces: eccconfig](#)

Applying for Wireless Device Resources

Interface Description

This interface is used by an agent to apply for wireless device resources after login.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/wirelessdevice
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
callType	int	Yes	Indicates the call type. 1 : group call 0 : non-group call Only the preceding two options are available.
groupId	string	Yes	Indicates the group ID. The value contains a maximum of 36 characters.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /agentgateway/resource/eccconfig/1010/wirelessdevice HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000 {"callType": "1", "groupId": "1"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0", "result": {}}</pre>

Triggered Event

- None

Error Code

- 000-002

- 100-006
- 103-017
- 103-026

Parent topic: [ECC Interfaces: eccconfig](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Releasing Wireless Device Resources

Interface Description

This interface is used by an agent to release wireless device resources after login.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/wirelessdevice?deviceId={deviceId}
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
deviceId	string	Yes	Indicates the ID of a device (the value contains a maximum of 36 characters and cannot be empty).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Reserved.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /agentgateway/resource/eccconfig/1010/wirelessdevice?deviceId=xxx HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result": {}}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 103-020
- 103-026

Parent topic: [ECC Interfaces: eccconfig](#)

Setting VoiceCodes Recording Parameters

Interface Description

This interface is used to set VoiceCodes recording parameters.

Usage Description

1. Prerequisites
 - The agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/customizedrecordinfo
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
recordId	string	Yes	Indicates the recording address. The value contains 1 to 129 characters.
data	string	Yes	Indicates the setting content. The value contains 1 to 1024 characters.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	int	Indicates the return result of a successful setting.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/eccconfig/1010/customizedrecordinfo HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8000 {"recordId":"Y:\\2\\0\\20170112\\6001\\1710081.V3","data":"dsadhasdjkha"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0","result":1}</pre>

Triggered Event

- None

Error Code

- 000-002
- 100-006
- 103-024

- 103-026

Parent topic: [ECC Interfaces: eccconfig](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Setting VoiceCodes Recording Parameters (Extended)

Interface Description

This interface is used to set VoiceCodes recording parameters.

Usage Description

1. Prerequisites
 - An agent has logged in.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/agentgateway/resource/eccconfig/{agentid}/customizedrecordinfoEx
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the Agent Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the Agent Gateway.
agentid	int	Yes	Indicates the work ID of an agent.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the agent authentication information.
Request Body			
callID	string	Yes	The value is a string of 1 to 129 characters.
data	string	Yes	Indicates the content to be set. The value is a string of 1 to 1024 characters.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	int	Indicates the return result of a successful setting.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /agentgateway/resource/eccconfig/1010/customizedrecordinfoEx HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000 {"callID":"1578453363-16777304","data":"dsadhasdjkha"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":1}</pre>

Triggering Event

- None

Error Code

- 000-002
- 100-006
- 103-024

- 103-026

Parent topic: [ECC Interfaces: eccconfig](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Events

[Telepresence Call Events](#)

Parent topic: [Extended Interfaces and Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Telepresence Call Events

[AgentVCCall_PhoneStatus \(Telepresence Phone Status\)](#)
[AgentVCCall_Ringing \(Call Ringing\)](#)
[AgentVCCall_Connected \(Call Setup\)](#)
[AgentVCCall_AnswerFailed \(Call Answering Failed\)](#)
[AgentVCCall_NoAnswer \(No Answering of a Telepresence Call\)](#)
[AgentVCCall_Release \(Call Released\)](#)
[AgentVCCall_ReleaseFailed \(Call Releasing Failed\)](#)
[AgentVCCall_RecordStart \(Recording Started\)](#)
[AgentVCCall_RecordEnd \(Recording Ended\)](#)
[AgentVCCall_RecordFailed \(Recording Failed\)](#)

Parent topic: [Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

AgentVCCall_PhoneStatus (Telepresence Phone Status)

Event Description

This event indicates that the status of the telepresence phone is changed.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
status	int	Indicates the phone status. 0 : ringing. 1 : off-hook. 2 : on-hook.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"AgentVCCall_PhoneStatus","workNo":"1010","content":{"status":0}}}</pre>

Parent topic: [Telepresence Call Events](#)

AgentVCCall_Ringing (Call Ringing)

Event Description

This event indicates that a telepresence call is distributed to the current agent.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the ID of a telepresence call.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"AgentVCCall_Ringing","workNo":"1010","content":{"callId":"1476955940-16777241"}}}</pre>

Parent topic: [Telepresence Call Events](#)

AgentVCCall_Connected (Call Setup)

Event Description

This event indicates that a telepresence call is set up.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the ID of a telepresence call.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"AgentVCCall_Connected","workNo":"1010","content":{"callId":"1476955940-16777241"}}}</pre>

Parent topic: [Telepresence Call Events](#)

AgentVCCall_AnswerFailed (Call Answering Failed)

Event Description

This event indicates that a telepresence call is not set up after the agent invokes the call answering interface.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the ID of a telepresence call.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"AgentVCCall_AnswerFailed","workNo":"1010","content":{"callId":"1476963123-16777247"}}}</pre>

Parent topic: [Telepresence Call Events](#)

AgentVCCall_NoAnswer (No Answering of a Telepresence Call)

Event Description

This event indicates that the agent does not answer a telepresence call for a long period of time.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	ID of a telepresence call.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"AgentVCCall_NoAnswer","workNo":"1010","content":{"callId":"1476963123-16777247"}}}</pre>

Parent topic: [Telepresence Call Events](#)

AgentVCCall_Release (Call Released)

Event Description

This event indicates that a telepresence call is released.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
type	int	Indicates the call release type. 0: The call is released before setup. 1: The call is proactively released by a user. 2: The call is proactively released by an agent.
callId	string	ID of a telepresence call.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"AgentVCCall_Release","workNo":"1010","content":{"type":3,"callId":"1476955940-16777241","jsonKey":{"type","callId"},"jsonKey":{"eventType","workNo","content"}}}}</pre>

Parent topic: [Telepresence Call Events](#)

AgentVCCall_ReleaseFailed (Call Releasing Failed)

Event Description

This event indicates that releasing a telepresence call fails.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the ID of a telepresence call.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"AgentVCCall_ReleaseFailed","workNo":"1010","content":{"callId":"1476963123-16777247"}}</pre>

Parent topic: [Telepresence Call Events](#)

AgentVCCall_RecordStart (Recording Started)

Event Description

This event indicates that a telepresence call is being recorded.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the ID of a telepresence call.
confId	long	Indicates the ID of a telepresence conference site.
recordUrl	string	Indicates the path of a recorded file.
recordNo	string	Indicates the ID of a recorded file. This field is reserved.
callerNo	string	Indicates the calling number.
calledNo	string	Indicates the called number.
uvid	long	Indicates the customer access ID.
beginTime	long	Indicates the start time of recording (timestamp, in milliseconds).
endTime	long	Reserved.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0", "event": {"eventType": "AgentVCCall_RecordStart", "workNo": "1010", "content": {"callId": "1476963123-16777247", "confId": "948", "recordUrl": "http://192.168.0.0/rse/rse/html/play/play.html?recordId=20a6c88a-8679-4f8d-b3ed-e3f0674514d7", "recordNo": "", "callerNo": "UserAppMe", "calledNo": "60015", "uvid": "2747761", "beginTime": "1476963124", "endTime": "0"}}</pre>

Parent topic: [Telepresence Call Events](#)

AgentVCCall_RecordEnd (Recording Ended)

Event Description

This event indicates that telepresence call recording is ended.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
recordInfo	object	Indicates the recording file information object. For the parameter description of event , see Table 4 .

Table 4 Parameter description of recordInfo

Parameter	Data Type	Description
callId	string	Indicates the ID of a telepresence call.
confId	string	Indicates the ID of a telepresence conference site.
recordUrl	string	Indicates the path of a recorded file.
recordNo	string	Indicates the ID of a recorded file. This field is reserved.
callerNo	string	Indicates the calling number.
calledNo	string	Indicates the called number.
uvid	int	Indicates the customer access ID.
beginTime	long	Reserved.
endTime	long	Indicates the end time of recording (timestamp, in milliseconds).

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"AgentVCCall_RecordEnd","workNo":"1010","content":{"recordInfo":{"callId":"1476963123-16777247","confId":"948","recordUrl":"http://192.168.0.0/rse/rse/html/play/play.html?recordId=20a6c88a-8679-4f8d-b3ed-e3f0674514d7","recordNo":"","callerNo":"UserAppMe","calledNo":"60015","uvid":2747761,"beginTime":0,"endTime":1476963160}}}}</pre>

Parent topic: [Telepresence Call Events](#)

AgentVCCall_RecordFailed (Recording Failed)

Event Description

This event indicates that telepresence call recording fails.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"AgentVCCall_RecordFailed","workNo":"1010", "content":{}}}</pre>

Parent topic: [Telepresence Call Events](#)

Appendix

[Error Codes](#)

[Agent Status](#)

[Operating Status of Agents](#)

[Call Types](#)

[Media Types](#)

[Error Codes about Multimedia Conferences](#)

[Device Types](#)

[pushUrl Request](#)

[Rich Media File Restrictions](#)

Parent topic: [Agent Server Interfaces \(RESTful\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Error Codes

Table 1 Error codes

Error Code	Description
000-001	The method for obtaining agent events is incorrect.
000-002	The parameters transmitted using the URL are incorrect, the IP address is incorrect, or the interface parameters are invalid and do not comply with relevant definitions.
000-003	The agent has no right to invoke interfaces.
000-004	The agent is switching to another server.
100-001	The login parameters are empty or set incorrectly.
100-002	The agent has logged in.
100-003	During agent login, the exception ResourceUnavailableException or ProviderUnavailableException is thrown.
100-004	The agent enters an incorrect user name or password during login.
100-006	The agent has not logged in.
100-005	The logout parameter is invalid.
100-007	An exception occurs when the agent performs an operation. The possible cause is that WAS resources are not accessible or an internal error occurs.
100-008	The agent has logged out.
100-009	The agent fails to configure the status.
100-011	The login parameters are invalid.
100-012	The agent type used for login is invalid.
100-013	The agent phone number to be bound is invalid.
100-014	The agent phone number used for login is out of the configured range.
100-015	The agent has logged in, and cannot be forcibly logged out.
100-016	The IP address is invalid during login.
100-017	CAC authentication fails.
100-018	The target agent has not logged in.
100-019	No agent work ID matching a third-party account is found.
100-020	No location information of the calling party is found.
100-021	Failed to transferring a call to an internal skill queue.
100-022	The reason for showing busy state is changed.
100-023	The parameter for transferring an internal call to a skill queue is invalid.
100-031	The phone number used for sign-in is an access code or network code, or has been used by another agent.
110-016	The account is locked.
101-001	No conference call exists for the agent to answer.
101-002	The agent is not the conference chair of the current conference call.
103-001	The number of phone numbers in the blacklist has reached the maximum.
103-002	Failed to add a phone number to the blacklist.
103-003	Failed to query a phone number in the blacklist.
103-004	Failed to query all phone numbers in the blacklist.
103-005	Failed to query all phone numbers in the blacklist.
103-006	Failed to delete all phone numbers from the blacklist.
103-007	The number of phone numbers in the redlist has reached the maximum.
103-008	Failed to add a phone number to the redlist.
103-009	Failed to query all phone numbers in the redlist.
103-010	Failed to query a phone number in the redlist.
103-011	Failed to update the redlist.
103-012	Failed to delete all phone numbers from the redlist.
103-013	Failed to delete a phone number from the redlist.
103-014	The number of monitored agent queues has reached the maximum.
103-015	Failed to add a monitored agent queue.
103-016	Failed to remove a monitored agent queue.
103-017	Failed to apply for a wireless device.

Error Code	Description
103-018	Failed to query a specified wireless device.
103-019	Failed to query all wireless devices.
103-020	Failed to release wireless device resources.
103-021	Failed to query the number of abandoned calls in the recent week.
103-022	Failed to query abandoned call records in the recent week.
103-023	Failed to query prank call records.
103-024	Failed to configure recording information.
103-025	Failed to query recording information.
103-026	The database is not configured and fails to be connected.
103-027	The queue monitoring subscription parameter is abnormal.
103-028	Failed to subscribe to queue monitoring.
104-001	The recording download function is disabled.
104-002	The user does not have the recording inspection or playback right.
104-003	Failed to download the recording file due to an invalid name.
104-004	Failed to download the recording file because no drive mapping is configured.
104-005	Failed to download the recording file because it does not exist.
104-006	Failed to download the recording file due to insufficient space.
104-007	The recording file format is not supported.
104-008	The recording format system parameter is not configured.
104-009	Failed to convert the recording file.
200-001	The number dialed by the agent is incorrect.
200-002	No call exists for the agent to answer.
200-003	No call exists for the agent to mute.
200-004	The call state is incorrect when the agent mutes the call.
200-005	No call exists for the agent to hold.
200-006	No call is held during call holding.
200-007	No call exists for the agent to unmute.
200-008	A call state error occurs when the agent unmutes a call.
200-009	No call exists for the agent to play an announcement.
200-010	No call exists for the agent to perform three-party conversation.
200-011	No call is held for the agent to perform three-party conversation.
200-012	No call exists for the agent to transfer.
200-013	No call exists for the agent to hold.
200-014	A call state error occurs after the agent holds the call.
200-015	No call exists for the agent to unhold.
200-016	A call state error occurs when the agent unholds the call.
200-017	No call exists for the agent to end.
200-018	No call exists for the agent to ask for internal help.
200-019	No call exists for the agent to freeze.
200-020	A call state error occurs when the agent freezes the image of a call.
200-021	No call exists for the agent to unfreeze.
200-022	A call state error occurs when the agent unfreezes the image of a call.
200-023	No call exists when the agent releases the specified phone number.
200-024	No phone number exists when the agent releases the phone number.
200-025	No call exists when the agent releases the call.
200-026	The call does not exist.
200-027	You do not have the right to initiate an outgoing call.
200-028	The MSD data is empty.
200-029	The current call state does not support call hold.
200-030	The agent requests internal help while not talking on a call.

Error Code	Description
300-001	The agent has no right to query agent information.
300-002	The agent does not exist when agents are queried.
300-003	The agent does not exist when agent groups are queried.
300-004	The agent group does not exist when agent groups are queried.
400-001	No call information exists when the agent sets call-associated data.
400-003	No call information exists when the agent queries held calls.
500-001	A state error occurs when recording is rewind.
500-002	A state error occurs when recording is fast forwarded.
500-003	A state error occurs when recording playback pauses.
500-004	A state error occurs when recording pauses.
500-005	A state error occurs when recording playback resumes.
500-006	A state error occurs when recording resumes.
500-007	A state error occurs when recording playback starts.
500-008	A state error occurs when recording starts.
500-009	A state error occurs when recording playback stops.
500-010	A state error occurs when recording stops.
600-001	No information about the agent exists or no skill queue is configured for the agent when the agent queries information about the skill queues of the agent.
600-002	No skill queue information exists when the agent queries the information about skill queues of a specified VDN.
600-003	No configuration information exists when the agent queries the access code of the home VDN of the agent.
600-004	No configuration information exists when the agent queries the IVR information of the home VDN of the agent.
600-005	No skill queue information exists when the agent queries the information about skill queues of the home VDN of the agent.
700-001	The session does not exist.
700-002	An anomaly occurs when the platform is called.
700-012	A message fails to be sent.
700-013	The rich media file upload function is not enabled.
700-014	A file server exception occurs during rich media file upload.
700-015	The file name extension or file size does not meet the requirements during rich media file upload.
700-016	The rich media file to be downloaded does not exist.
700-017	No download right is available during rich media file download.
700-018	The database is abnormal.
701-001	The parameter of conference member is empty.
701-002	The result of querying conference status is null.
701-003	When creating a conference, the creator or participant has joined another conference.
701-004	When inviting participants, the current agent is not in the conference.
701-005	When stopping a conference, the conference does not exist or the current agent has no right to stop it.
701-006	When creating a conference, the MS IP address is not configured in the WAS.
800-001	The proxy service configuration is empty.
800-002	When querying configuration information, an exception occurs.
800-003	The default media gateway information does not exist.
900-001	The NOPROVIDER error occurs during quality check.
900-002	The necessary right is not granted for the quality control operation.
900-003	The ResourceUnavailableException occurs during the quality control operation.
900-004	No agent information is found during quality check monitoring.
900-005	A state error occurs during the quality control operation.
900-006	The video recording time parameter is invalid during the quality control operation.
900-007	No video recording license is loaded during the quality control operation.
900-008	An unknown video recording platform exception occurs during the quality control operation.
900-009	No quality control task is found when the task is deleted.
900-010	The input time parameter is incorrect or abnormal during the quality control operation.
900-011	A parameter error or exception occurs during the quality control operation.

Error Code	Description
999-001	The WAS URL in the configuration file of the server is incorrect.

Parent topic: [Appendix](#)

Agent Status

Table 1 Agent gateway status

Value	Description
0	Unknown. It maps status 9 on the CTI platform.
1	Login. This value is not used.
2	Logout. It maps status 0 on the CTI platform.
3	Busy. It maps status 7 on the CTI platform.
4	Idle. It maps status 1 on the CTI platform.
5	ACW. It maps status 6 on the CTI platform.
6	Same as Idle. This value is not used.
7	Talking. It maps status 2, 3, 4 and 5 on the CTI platform.
8	Rest. It maps status 8 on the CTI platform.

Table 2 CTI platform status

Value	Description
0	NOT_LOGINED
1	IDLE
2	PREOCCUPY
3	OCCUPY
4	ANSWERING
5	TALKING
6	WORK_ADJUST
7	SETBUSY
8	REST
9	STUDYING (The Agent Gateway does not support this state.)

Parent topic: [Appendix](#)

Operating Status of Agents

Value	Description
0	NOT_LOGINED
1	Studying
2	Idle
3	Busy
4	Talking
5	Answering
6	WORK_ADJUST
9	Ringin
10	Making a three-party call
13	Hang up after transferring to IVR
14	Entering the work state
15	ACW
16	Quitting the work state
20	Listening or barging
22	Recording
26	Rest
27	Work
28	Listening and barging
29	Muting an ongoing call
30	Holding a call
31	Freezing image
32	Muting an ongoing call and freezing image

Parent topic: [Appendix](#)

Call Types

Table 1 Call types

Value	Description
0	Common incoming call
6	Internal call
7	Common outgoing call
40	Reserved outgoing call
41	Preemptive outgoing call
43	Predictive outgoing call
44	Previewed outgoing call
45	Reserved callback
51	Call for internal help during two-party conversation
52	Call for internal help during three-party conversation
53	Multi-party call

Parent topic: [Appendix](#)

Media Types

Table 1 Media types

Media Type	Description
1	Text Chat
2	CTD
3	Escorted browsing; form sharing
4	Callback request
5	Common voice call
6	Email call
7	Fax call
8	IP video call (H.323)
9	Whiteboard
10	Application sharing
11	File transfer
12	2B+D ISDN video call
13	6B+D ISDN video call
14	OPS call
15	Predicted outbound call
16	Previewed outbound call
17	Message media
18	CTD video call
19	Common video call
20	Web message access

Parent topic: [Appendix](#)

Error Codes about Multimedia Conferences

Table 1 Error codes about multimedia conferences

Error Code	Description
3609	When applying for a conference, the system fails to create the object.
3610	No member is invited.
3611	CCS times out.
3612	The participant is not an agent.
3613	The applicant or participant has joined another conference.
3614	The number of conference members exceeds 30.
3615	When inviting participants, the current agent is not in the conference.
3616	The agent has not logged in.
3617	The agent does not respond.
3618	The operation is not allowed in the current conference status.
3619	When stopping a conference, the conference does not exist or the current agent has no right to stop it.
3620	The invited member rejected to join the conference.
3621	The system fails to initialize the authentication thread (when creating a conference)
3622	When applying for a conference, the MS IP address is not configured in WAS.

Parent topic: [Appendix](#)

Device Types

Table 1 Device types

Device Type ID	Device Type Description
1	Skill
2	Agent
3	IVR

Parent topic: [Appendix](#)

pushUrl Request

NOTE

If event push is enabled, each event of an agent corresponds to a request and the interface described in [Detecting Heartbeat](#) is invoked every minute.

- Request Method
POST
- Request header
Content-Type: application/json; charset=UTF-8
- Request message
event: event content
- Request example
POST /AgentServerDemo/AgentEventServlet
HTTP/1.1 Content-Length: 103
Content-Type: application/json; charset=UTF-8
Host: 10.177.244.143:8072 Connection: Keep-Alive
User-Agent: Apache-HttpClient/4.3.6 (java 1.5)
Accept-Encoding: gzip,deflate
{ "message": "", "retcode": "0", "event": { "eventType": "AgentOther_InService", "workNo": "110", "content": null } }
- Response example

NOTE

The server must return 200 OK. Otherwise, the Agent Gateway re-pushes the event.

HTTP/1.1 200 OK
Server: Apache-Coyote/1.1
Content-Length: 0
Date: Fri, 02 Mar 2018 03:22:15 GMT

Parent topic: [Appendix](#)

Rich Media File Restrictions

Rich media file restrictions are configured in the `tomcat7/webapps/agentgateway/confing/mediafile.xml` file of the AgentServer installation directory. [Figure 1](#) shows the default supported file format.

Table 1 Parameter Description

Parameter	Data Type	Description
id	int	Virtual contact center ID.
subMediaType	int	Sub media type of the text chat skill queue. When a text chat skill queue is configured in the WAS, the sub media type can be obtained.
type	String	Allowed file name extension.
maxsize	int	Allowed file size, in MB.

Figure 1 mediafile.xml

```
<?xml version="1.0" encoding="UTF-8"?>
<mediafiles>
  <!-- the max value of maxsize is 10 -->
  <vdnId id="1">
    <mediaType subMediaType="0">
      <mediafile>
        <type>PNG</type>
        <maxsize>10</maxsize>
      </mediafile>
      <mediafile>
        <type>mp3</type>
        <maxsize>2</maxsize>
      </mediafile>
      <mediafile>
        <type>JPG</type>
        <maxsize>10</maxsize>
      </mediafile>
      <mediafile>
        <type>TXT</type>
        <maxsize>10</maxsize>
      </mediafile>
    </mediaType>
  </vdnId>
</mediafiles>
```

Parent topic: [Appendix](#)

ICS Server Interface (RESTful)

- About This Document
- Interfaces
- Events
- Appendix

Copyright © Chengdu TD-Tech Co., Ltd.

About This Document

[Intended Audience](#)

[Symbol Conventions](#)

[Change History](#)

Parent topic: [ICS Server Interface \(RESTful\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Intended Audience

This document guides the secondary development engineers on the multimedia access (such as text chat and callback). Development personnel must have the following skills

- Be familiar with the JSON format.
- Be familiar with knowledge related to HTTP request sending.

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Symbol Conventions

The symbols that may be found in this document are defined as follows.

Symbol	Description
 DANGER	Indicates an imminently hazardous situation which, if not avoided, will result in death or serious injury.
 WARNING	Indicates a potentially hazardous situation which, if not avoided, could result in death or serious injury.
 CAUTION	Indicates a potentially hazardous situation which, if not avoided, may result in minor or moderate injury.
 NOTICE	Indicates a potentially hazardous situation which, if not avoided, could result in equipment damage, data loss, performance deterioration, or unanticipated results. NOTICE is used to address practices not related to personal injury.
 NOTE	Calls attention to important information, best practices and tips. NOTE is used to address information not related to personal injury, equipment damage, and environment deterioration.

Parent topic: [About This Document](#)

Change History

- [V100R023C00](#)
- [V100R022C00](#)
- [V600R019C00](#)
- [V600R006C10](#)
- [V200R001C80](#)
- [V200R001C60](#)

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V100R023C00

V600R019C00SPC630

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00SPC630

Compared with V600R019C00SPC591, V600R019C00SPC630 does not include any changes.

Parent topic: [V100R023C00](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V100R022C00

V600R019C00SPC590

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00SPC590

Compared with V600R019C00SPC580, V600R019C00SPC590 does not include any changes.

Parent topic: [V100R022C00](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00

[V600R019C00SPC100](#)
[V600R019C00](#)

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Table 1 List of new interfaces

Interface Type	Interface Name
Server connection interfaces	Sending an AML SMS Message When There Is No Call
	Sending a Certificate Expiration Alarm

Parent topic: [V600R019C00](#)

V600R019C00

No change is made in CloudIPCC V600R019C00 compared with CloudIPCC V600R006C10.

Parent topic: [V600R019C00](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R006C10

[V600R006C10SPC100](#)

[V600R006C10](#)

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R006C10SPC100

The following tables describe changes made in CloudIPCC V600R006C10SPC100 compared with CloudIPCC V600R006C10.

Interface Changes

Table 1 List of new interfaces

Interface Type	Interface Name
Quasi-real-time calling interfaces	Querying_CDRs

Table 2 List of modified interfaces

Interface Type	Interface Name	Changes
User login and logout interfaces	Logging_In	Input parameters pushUrl are added.
	Logging_In (Extended)	Input parameters pushUrl are added.
Quasi-real-time calling interfaces	Creating_Quasi-Real-Time Calls	Request parameter mediaAbility is deleted (The interface compatibility with the original version of the interface).
	Creating_Quasi-Real-Time Calls	Input parameter mediaAbility is added.

Parent topic: [V600R006C10](#)

V600R006C10

The following tables describe changes made in IPCC V200R001C80SPC701 compared with IPCC V200R001C80SPC700.

Interface Changes

Table 1 List of new interfaces

Interface Type	Interface Name
User login and logout interfaces	Logging In (Extended)
	Detecting Heartbeat
Quasi-real-time calling interfaces	Uploading a Rich Media File
	Downloading a Rich Media File
	Confirming Message Receiving

Table 2 List of modified interfaces

Interface Type	Interface Name	Changes
Quasi-real-time calling interfaces	Creating Quasi-Real-Time Calls	Input parameters realCaller , displayName , userInfo , and mediaAbility are added. The caller parameter is marked as useless.
	Sending Text Messages	Input parameters needCheck , chatId , sendTime are added.

Event Changes

Table 3 List of new events

Event Type	Event Name
Call events	WECC_CHAT_RECEIVEDDATA_EX (Receiving of an Agent's Message Requiring a Reply)
Other related events	WECC_MESSAGE_WITHOUTCALL_EVENT (Agent Sending Content to a User Without Call)

Table 4 List of modified events

Event Type	Event Name	Changes
Call events	WECC_CHAT_POSTDATA_SUCC (Message Sending Success)	Output parameter chatContentType is added.
	WECC_CHAT_POSTDATA_FAIL (Message Sending Failure)	Output parameter chatContentType is added.
	WECC_CHAT_RECEIVEDATA (Message Receiving Success)	Output parameter chatContentType is added.

Parent topic: [V600R006C10](#)

V200R001C80

[V200R001C80SPC701](#)

[V200R001C80SPC700](#)

[V200R001C80SPC600](#)

[V200R001C80SPC500](#)

[V200R001C80SPC300](#)

[V200R001C80SPC200](#)

[V200R001C80SPC100](#)

[V200R001C80](#)

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC701

The following tables describe changes made in IPCC V200R001C80SPC701 compared with IPCC V200R001C80SPC700.

Interface Changes

Table 1 List of modified interfaces

Interface Type	Interface Name	Changes
Interfaces for obtaining events	Obtaining Events of a Specified User	Optimized the description of the interface.

Parent topic: [V200R001C80](#)

V200R001C80SPC700

No change is made in IPCC V200R001C80SPC700 compared with IPCC V200R001C80SPC600.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC600

No change is made in IPCC V200R001C80SPC600 compared with IPCC V200R001C80SPC500.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC500

The following tables describe changes made in IPCC V200R001C80SPC500 compared with IPCC V200R001C80SPC300.

Interface Changes

Table 1 List of modified interfaces

Interface Type	Interface Name	Changes
Quasi-real-time calling interfaces	Sending Text Messages	The maximum length of content is changed to 6144 characters.

Parent topic: [V200R001C80](#)

V200R001C80SPC300

The following tables describe changes made in IPCC V200R001C80SPC300 compared with IPCC V200R001C80SPC200.

Interface Changes

Table 1 List of modified interfaces

Interface Type	Interface Name	Changes
Quasi-real-time calling interfaces	Sending Text Messages	The maximum length of content is changed to 2048 characters.

Parent topic: [V200R001C80](#)

V200R001C80SPC200

No change is made in IPCC V200R001C80SPC200 compared with IPCC V200R001C80SPC100.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC100

The following tables describe changes made in IPCC V200R001C80SPC100 compared with IPCC V200R001C80.

Event Changes

Table 1 List of new events

Event Type	Event Name
Inspection notification events	WECC_BE_QC_START (Starting the Inspection)
	WECC_BE_QC_STOP (Stopping the Inspection)

Parent topic: [V200R001C80](#)

V200R001C80

The following tables describe changes made in IPCC V200R001C80 compared with IPCC V200R001C60SPC100.

Interface Changes

Table 1 List of new interfaces

Interface Type	Interface Name
Parameter configuration interfaces	Obtaining the Operation Parameters of a Multimedia Client
	Obtaining the Media Gateway Information
Verification code interfaces	Obtaining the Call Verification Code

Table 2 List of modified interfaces

Interface Type	Interface Name	Changes
User login and logout interfaces	Logging In	Input parameter entryIp is added.
Quasi-real-time calling interfaces	Creating Quasi-Real-Time Calls	Input parameter verifyCode is added.

Parent topic: [V200R001C80](#)

V200R001C60

[V200R001C60SPC100](#)

[V200R001C60](#)

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C60SPC100

No change is made in IPCC V200R001C60SPC100 compared with IPCC V200R001C60.

Parent topic: [V200R001C60](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C60

The following tables describe changes made in IPCC V200R001C60 compared with eSpace CC V200R001C50SPC103.

Interface Changes

Table 1 List of new interfaces

Interface Type	Interface Name
Multimedia conference interfaces	Applying for a Multimedia Conference and Requiring the Current Agent to Participate in the Conference
	Re-inviting the Current Agent to Participate in the Multimedia Conference
	Ending the Multimedia Conference
	Reporting Conference Participation Results

Table 2 List of modified interfaces

Interface Type	Interface Name	Changes
Quasi-real-time calling interfaces	Creating Quasi-Real-Time Calls	The option indicating telepresence call is added to mediaType .

Event Changes

Table 3 List of new events

Event Type	Event Name
Multimedia conference events	WECC_MEETING_PREPARE_JOIN (Will Participate in the Multimedia Conference)
	WECC_MEETING_STOP (Notifying the Conference Ending)
	WECC_MEETING_STATUS (Notifying the Conference Status)

Table 4 List of modified events

Event Type	Event Name	Changes
Call events	WECC_WEBM_CALL_CONNECTED (Call Setup)	The vcConfInfo message is incorporated in return messages.

Parent topic: [V200R001C60](#)

Interfaces

[The Description Of Interface Parameter](#)

[User Login and Logout Interfaces](#)

[Quasi-Real-Time Calling Interfaces](#)

[Interfaces for Obtaining Events](#)

[Interfaces for Querying Queue Devices](#)

[Multimedia Conference Interfaces](#)

[Parameter Configuration Interfaces](#)

[Verification Code Interfaces](#)

[Server Connection Interfaces](#)

Parent topic: [ICS Server Interface \(RESTful\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

The Description Of Interface Parameter

- The interface parameters that you need to pass the skill queue ID, access code, VDNID, callId, and so on must be real.
- userName: case-sensitive, a string of 1 to 20 digits and letters.

NOTE

The user name is recorded in the **icsgateway-rest.log** file for ICS Gateway interface invocation in plain text for fault locating. It is not recommended to use mobile number or bank card number as the user name.

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

User Login and Logout Interfaces

A user needs to invoke the login interface to log in and then request services.

Upon login, the system obtains the following information:

- User authentication Information
- User information registered on the platform

[Logging In](#)

[Logging In \(Extended\)](#)

[Logging Out](#)

[Detecting Heartbeat](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Logging In

Interface Description

This interface is used for user login.

Usage Description

1. Prerequisites
None
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/onlinewecc/{vdnId}/{userName}/login
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID. The value is a numeric string ranging from 1 to 9999.
userName	String	Yes	Indicates the login user name. The value is a string of 1 to 20 characters including digits and case-sensitive letters.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
Request Body			
userIp	string	No	Indicates the IP address of the user.
appld	string	No	Indicates the ID of a third-party application. The value is a string of 0 to 10 case-sensitive letters. In server connection mode, this parameter is mandatory and the application ID must have been configured in the appConfig.xml file.
entryIp	string	No	Indicates the entry IP address of the client application gateway.
pushUrl	string	No	Indicates the URL for receiving an event. The URL can contain a maximum of 512 characters. If this parameter is not empty, the user event will be pushed to the specified URL. For details, see Pushing a Request Based on pushUrl .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Set-GUID	string	Indicates the GUID returned after login, which is contained in all the subsequent request messages.
Set-Cookie	string	Indicates the cookie returned after login, which is contained in all the subsequent request messages. Modify the following configuration in the icsgateway/WEplatB-INF/config/platform.properties file: ICS.COOKIES.WRITEBACK.FLAG = ON The value ON indicates that a cookie is returned; the value OFF indicates that no cookie is returned.
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Indicates the name of the ICS Gateway cluster to which the user logs in.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /icsgateway/resource/onlinewecc/1/testuser/login HTTP/1.1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280 {"userIp": "127.0.0.1", "appId": "", "entryIp": "127.0.0.1"}</pre>

Example Type	Reference Format
Example of a response packet	<pre>HTTP/1.1 200 OK Set-Cookie:JSESSIONID=97b3ba90ba17dfcfedea36f99a5fc1bd.ICSGateway1; Path=/; HttpOnly Set-GUID:JSESSIONID=590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":"ICSGateway1"}</pre>

Triggered Event

- [WECC_PROVIDER_IN_SERVER \(User Login\)](#)

Error Code

- 10-100-003
- 10-100-004
- 10-100-007
- 10-100-008
- 10-100-009
- 10-100-010
- 10-100-015

Parent topic: [User Login and Logout Interfaces](#)

Logging In (Extended)

Interface Description

This interface is used for user login.

Usage Description

1. Prerequisites
 - None
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/onlinewecc/{vdnId}/{userName}/loginex
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID. The value is a numeric string ranging from 1 to 9999.
userName	String	Yes	Indicates the login user name. The value is a string of 1 to 20 characters including digits and case-sensitive letters.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
Request Body			
userIp	string	No	Indicates the user IP address.
appld	string	No	Indicates the ID of a third-party application. The value is a string of 0 to 10 case-sensitive letters. In server connection mode, this parameter is mandatory and the application ID must have been configured in the appConfig.xml file.
entryIp	string	No	Indicates the entry IP address of the client application gateway.
pushUrl	string	No	Indicates the URL for receiving an event. The URL can contain a maximum of 512 characters. If this parameter is not empty, the user event will be pushed to the specified URL. See Pushing a Request Based on pushUrl .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Set-GUID	string	Indicates the GUID returned after login, which is contained in all the subsequent request messages.
Set-Cookie	string	Indicates the cookie returned after login, which is contained in all the subsequent request messages. Modify the following configuration in the icsgateway/WEB-INF/config/platform.properties file: ICS.COOKIES.WRITEBACK.FLAG = ON The value ON indicates that a cookie is returned; the value OFF indicates that no cookie is returned.
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	object	Table 3

Table 3 Parameter description of **result**

Parameter	Data Type	Description
loginServer	string	Indicates the name of the ICS Gateway cluster to which the user logs in.
loginTime	string	Indicates the time when the user logs in to the server. (The value is a timestamp, and the unit is millisecond.)

Interface Example

Example Type	Reference Format
Example of a request packet	POST /icsgateway/resource/onlinewecc/1/testuser/loginex HTTP/1.1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280 { "userIp": "127.0.0.1", "appId": "", "entryIp": "127.0.0.1" }
Example of a response packet	HTTP/1.1 200 OK Set-Cookie:JSESSIONID=97b3ba90ba17dfcfedea36f99a5fc1bd.ICSGateway1; Path=/; HttpOnly Set-GUID:JSESSIONID=590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "loginServer": "IcsGateway1", "loginTime": "1502192475892" } }

Triggered Event

- [WECC_PROVIDER_IN_SERVER \(User Login\)](#)

Error Code

- 10-100-003
- 10-100-004
- 10-100-007
- 10-100-008
- 10-100-009
- 10-100-010
- 10-100-015

Parent topic: [User Login and Logout Interfaces](#)

Logging Out

Interface Description

This interface is used for user logout.

Usage Description

1. Prerequisites
 - The user has logged in to the system.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/onlinewecc/{vdnId}/{userName}/logout
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	String	Yes	Indicates the user name that logs in.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Description
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /icsgateway/resource/onlinewecc/1/testuser/logout HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 10-100-006

Parent topic: [User Login and Logout Interfaces](#)

Detecting Heartbeat

Interface Description

This interface is used to maintain the heartbeat connection between a user and the server in server connection mode.

NOTE

- It is recommended that this interface be invoked every minute.
- This interface is not required in client connection mode.
- In server connection mode, you can modify the following configuration in the `icsgateway/WEB-INF/config/platform.properties` file to force a user to log out when the user's heartbeat response times out:

`USER_TIMEOUT_FORSERVERMODE = 43200000 // The unit is millisecond.`

Usage Description

- Prerequisites
 - The user has logged in to the system.
- Precautions
 - None
- Use restrictions
 - None

Interface Prototype

Request URL	<code>http(s)://ip:port/icsgateway/resource/onlinewecc/{vdnId}/{userName}/heartbeat</code>
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	String	Yes	Indicates the user name that logs in.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
result	Object	Table 3

Table 3 Parameter description of result

Parameter	Data Type	Description
loginTime	long	Indicates the time when the user logs in to the current server (timestamp, in milliseconds).

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /icsgateway/resource/onlinewecc/1/testuser/heartbeat HTTP/1.1 guid:5c28e38ac-b7b4-405a-9210-0205db026997.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "loginTime": 1502192475892 } }

Triggered Event

- None

Error Code

- 10-100-006

Parent topic: [User Login and Logout Interfaces](#)

Quasi-Real-Time Calling Interfaces

[Creating Quasi-Real-Time Calls](#)

[Ending Quasi-Real-Time Calls](#)

[Canceling Queuing Calls](#)

[Sending Text Messages](#)

[Obtaining Queuing Information](#)

[Uploading a Rich Media File](#)

[Downloading a Rich Media File](#)

[Confirming Message Receiving](#)

[Querying CDRs](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Creating Quasi-Real-Time Calls

Interface Description

This interface is used by a user to initiate a text chat, click to call, callback, or telepresence call.

The processes of the text chat, click to call, callback, or telepresence call are similar. The difference is that the interface for sending text chat content (see [Sending Text Messages](#)) is invoked after a text chat call is set up ([WECC_WEBM_CALL_CONNECTED \(Call Setup\)](#)).

NOTE

When the user initiates click to call and the call is allocated to an agent, if the agent does not answer the call within the timeout interval, the call is directly released and will not be queued.

Usage Description

1. Prerequisites
The user has logged in to the system.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/realtimecall/{vdnId}/{userName}/dcreatecall
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	String	Yes	Indicates the user name that logs in.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.
Request Body			
mediaType	int	Yes	Indicates the media type (1 : text chat; 2 : CTD; 4 : callback; 22 : telepresence call).
caller	string	No	Indicates the user name of the calling party, which contains 1 to 20 case-sensitive letters and digits. This parameter is useless.
accessCode	string	Yes	Indicates the access code (a string of 1 to 24 digits).
callData	string	No	Indicates the channel-associated data (a string of 0 to 1024 characters). In the callback scenario, enter the called number for this field.
uvid	long	No	Indicates the unique ID of the same user. (The default value is -1. In the collaboration call scenario, enter the uvid of the other call.)
verifyCode	String	No	Indicates the verification code (with a maximum length of 200 bytes).
realCaller	String	No	Indicates the real calling party information, which contains a maximum of 64 characters. This field is used to supplement the following item: The called field in the interface can contain only 1 to 20 letters and digits.
displayName	String	No	Indicates the display name of a user, which can contain a maximum of 64 characters.
userInfo	String	No	Indicates user information, which can contain a maximum of 512 characters.
mediaAbility	int	No	Indicates the media capability. The value 0 indicates voice call and the value 1 indicates video call. The default value is 0 .

NOTE

The code verification function is used to verify a user during call initiation and is a new feature introduced in IPCC V200R001C80. This function can be adjusted by configuring parameters in **verifyCode.properties** in **icsgateway/WEB-INF/config**.

- **VERIFYCODE_ISUSERFORCALL**: specifies whether to enable the code verification function. The default value is **true**, indicating that the code verification function is enabled. When this parameter is set to **false**, there may be security risks. You need to modify this parameter with caution.
- **VERIFYCODE_MAXVALIDTIME**: specifies the validity period of a verification code in milliseconds. The default value is **300000**.
- **VERIFYCODE_ISONLY_VERIFYFIRSTCALL**: specifies whether to verify only the first call when a user initiates multiple calls. The default value is **false**, indicating that the verification code of each call needs to be checked.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	string	Indicates the unique identifier (callId) of a call.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /icsgateway/resource/realtimecall/1/testuser/docreatecall HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280 {"mediaType": 1, "caller": "1", "accessCode": "1009", "callData": "", "verifyCode": "5876"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message": "", "retcode": "0", "result": "1455523808-16777480"}</pre>

Triggered Event

- If a call fails because no agent is on duty or due to other reasons, the following event is received:
[WECC_WEBM_CALL_FAIL \(Call Failure\)](#)
- When all agents are busy and the user is waiting in a queue, the following event is received:
[WECC_WEBM_CALL_QUEUEING \(Call Queuing\)](#)
- When user queuing times out, the following event is received:
[WECC_WEBM_QUEUE_TIMEOUT \(Queuing Timeout\)](#)
- After a call is set up between the user and agent, the following event is received:
[WECC_WEBM_CALL_CONNECTED \(Call Setup\)](#)
- After a call between the user and agent ends, the following event is received:
[WECC_WEBM_CALL_DISCONNECTED \(Call Disconnection\)](#)

Error Code

- 10-100-006
- 10-100-009
- 10-100-011
- 10-100-012
- 10-100-014
- 10-200-001
- 10-200-002
- 10-200-008

Parent topic: [Quasi-Real-Time Calling Interfaces](#)

Ending Quasi-Real-Time Calls

Interface Description

This interface is used to a user to end a quasi-real-time call.

Usage Description

1. Prerequisites
 - The user has logged in to the system.
 - The user has set up a quasi-real-time call.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/realtimecall/{vdnId}/{userName}/dodropcall?callId={callId}
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name that logs in.
callId	string	Yes	Indicates the unique ID of the current call.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /icsgateway/resource/realtimecall/1/testuser/dodropcall?callId=1514337973-16777431 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- When a user ends a call, the following event is received:
[WECC_WEBM_CALL_DISCONNECTED \(Call Disconnection\)](#)

Error Code

- 10-100-006
- 10-100-007
- 10-100-009
- 10-100-011

- 10-200-003

Parent topic: [Quasi-Real-Time Calling Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Canceling Queuing Calls

Interface Description

This interface is used by a user to cancel queuing a call.

Usage Description

1. Prerequisites
 - The user has logged in to the system.
 - The user initiates a quasi-real-time call and receives the queuing message. The call enters the waiting queue.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/realtimecall/{vdnId}/{userName}/docancelqueuecall?callId={callId}
Request Method	DELETE

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name that logs in.
callId	string	Yes	Indicates the unique ID of the current call.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>DELETE /icsgateway/resource/realtimecall/1/testuser/docancelqueuecall?callId=1514337973-16777431 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- When a user who is queuing cancels queuing, the following event is received after the interface is successfully invoked:
[WECC_WEBM_CANCEL_QUEUE \(Queuing Cancellation\)](#)

Error Code

- 10-100-006
- 10-100-007
- 10-100-009
- 10-100-011

- 10-200-003

Parent topic: [Quasi-Real-Time Calling Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Sending Text Messages

Interface Description

This interface is used by a user to send a text message.

Usage Description

1. Prerequisites
 - The user has logged in to the system.
 - The user has set up a quasi-real-time call.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/realtimecall/{vdnId}/{userName}/dosendmessage
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name that logs in.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.
Request Body			
callId	string	Yes	Indicates the unique ID of the current call. The value contains 1 to 50 characters.
content	string	Yes	Indicates the message content, which cannot be left empty and can contain a maximum of 6144 characters.
needCheck	boolean	No	Indicates whether the peer party needs to send a confirmation message. The default value is false .
chatId	long	No	Indicates the unique ID of the content to be sent. When the value of needCheck is true , the parameter is valid. After receiving content sent by an agent, the peer party returns a confirmation message containing the value of chatId . The default value is 0 .
sendTime	long	No	Indicates the UTC timestamp for sending the content, in milliseconds. The value 0 indicates the current system time. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /icsgateway/resource/realtimecall/1/testuser/dosendmessage HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8280 {"callId": "1455537015-16777499", "content": "hello!"}</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0" }

Triggered Event

- When a message is successfully sent, the following event is received:
[WECC_CHAT_POSTDATA_SUCC \(Message Sending Success\)](#).
- When a message fails to be sent, the following event is received:
[WECC_CHAT_POSTDATA_FAIL \(Message Sending Failure\)](#)

Error Code

- 10-100-006
- 10-100-009
- 10-200-003
- 10-200-004

Parent topic: [Quasi-Real-Time Calling Interfaces](#)

Obtaining Queuing Information

Interface Description

This interface is used by a user to obtain queuing information.

Usage Description

1. Prerequisites
 - The user has logged in to the system.
 - The user initiates a quasi-real-time call and receives the queuing message. The call enters the waiting queue.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/realtimecall/{vdnId}/{userName}/getcallqueue?callId={callId}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name that logs in.
callId	string	Yes	Indicates the unique ID of the current call. The value contains 1 to 50 characters.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Object	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of **result**

Parameter	Data Type	Description
skillId	int	Indicates the skill ID of the corresponding queue.
onlineAgentNum	int	Indicates the number of registered agents in the queue.
position	long	Indicates the position in the queue of the current call.
totalWaitTime	long	Indicates the total waiting time of the current call.
currentDeviceWaitTime	long	Indicates the actual waiting time in the skill queue. The unit is second.
configMaxcWaitTime	long	Indicates the longest waiting time configured for the queue. The unit is second.
longestWaitTime	long	Indicates the longest waiting time among all queuing calls. The unit is second.

Interface Example

Example Type	Reference Format
Example of a request packet	GET /icsgateway/resource/realtimecall/1/testuser/getcallqueue?callId=1514337973-16777431 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "skillId": 10, "onlineAgentNum": 1, "position": 1, "totalWaitTime": 9, "currentDeviceWaitTime": 9, "configMaxcWaitTime": 30, "longestWaitTime": 9 } }

Triggered Event

- None

Error Code

- 10-100-006
- 10-100-007
- 10-100-009
- 10-100-012
- 10-200-003
- 10-200-006

Parent topic: [Quasi-Real-Time Calling Interfaces](#)

Uploading a Rich Media File

Interface Description

This interface is used by a user to upload a rich media file to an agent after a text chat session is created.

Usage Description

1. Prerequisites
 - The user has logged in and created a text chat.
 - The rich media files that can be uploaded and file size limitations have been configured by referring to [Rich Media File Restrictions](#).
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/realtimecall/{vdnId}/{userName}/mediafile?callId={callId}&isNeedConfirm={isNeedConfirm}&chatId={chatId}&remark={remark}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name that logs in.
isNeedConfirm	boolean	No. If this parameter is not set, the value false is used.	Indicates whether confirmation of the peer end is required.
callId	string	Yes	Indicates the current session ID, which can contain a maximum of 30 characters.
chatId	long	This parameter cannot be left empty when isNeedConfirm is set to true .	Indicates the message ID ranging from 1 to 4294967295.
remark	string	No	Indicates remarks, which can contain a maximum of 1024 characters.
msgType	string	No	Indicates message type, which can contain a maximum of 10 characters.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.
Request Body			
File formats that meet the standards for uploading files in HTTP mode.			

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Object	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
-----------	-----------	-------------

Parameter	Data Type	Description
filePath	String	Indicates the file server path.
fileName	String	Indicates the uploaded file name.
chatId	String	Indicates the message ID.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /icsgateway/resource/realtimecall/1/testuser/mediafile?callId=1514337973-16777431&isNeedConfirm=false&chatId=1&remark=test HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"filePath":"XXXX","fileName":"XXXX","chatId":"XXXX"}}</pre>

Triggered Event

When **isNeedConfirm** is set to **true**:

- If the user successfully invokes the interface but the peer end does not return a confirmation message within 12 seconds, the user will receive the event indicating the sending failure:
[WECC_CHAT_POSTDATA_FAIL \(Message Sending Failure\)](#)
- If the peer end returns a confirmation message within 12 seconds, the user will receive the event:
[WECC_CHAT_POSTDATA_SUCC \(Message Sending Success\)](#)

Error Code

10-100-006
10-200-003
10-200-010
10-200-011
10-200-012
10-200-013

Parent topic: [Quasi-Real-Time Calling Interfaces](#)

Downloading a Rich Media File

Interface Description

This interface is used by a user to download a rich media file for the agent after a text chat session is created.

Usage Description

1. Prerequisites
The user has logged in and created a text chat.
2. Precautions
None
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/realtimecall/{vdnId}/{userName}/mediafile?filePath={filePath}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name that logs in.
filePath	string	Yes	Indicates the path of the file to be downloaded (a string of 1 to 200 characters).
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	GET /icsgateway/resource/realtimecall/1/testuser/mediafile?filePath=xxx HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8280
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 { "message": "", "retcode": "xxx" }

Triggered Event

None

Error Code

10-100-006
10-200-010
10-200-011
10-200-014
10-200-015

Parent topic: [Quasi-Real-Time Calling Interfaces](#)

Confirming Message Receiving

Interface Description

This interface is used by a user to confirm message receiving with an agent.

Usage Description

- Prerequisites
 - The user has received the event [WECC_CHAT_RECEIVEDDATA_EX \(Receiving of an Agent's Message Requiring a Reply\)](#).
- Precautions
 - None
- Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/realtimecall/{vdnId}/{userName}/message
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name that logs in.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.
Request Body			
callId	string	Yes	Indicates the unique ID of the call. This parameter cannot be left empty and the value can contain 1 to 50 characters.
senderSessionId	int	Yes	Indicates the session ID of the message sender, which comes from the event WECC_CHAT_RECEIVEDDATA_EX (Receiving of an Agent's Message Requiring a Reply) .
chatId	long	Yes	Indicates the message ID, which comes from the WECC_CHAT_RECEIVEDDATA_EX (Receiving of an Agent's Message Requiring a Reply) event. The value ranges from 0 to 4294967295.
result	int	No	Indicates the configuration result (self-defined). The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /icsgateway/resource/realtimecall/1/testuser/message HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8280 {callId: "1503297816-16777401", senderSessionId: 110, chatId: 1955757892, result: 12}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0"}</pre>

Triggered Event

- None

Error Code

- 10-100-006
- 10-100-007
- 10-100-009
- 10-100-012
- 10-200-003
- 10-200-006

Parent topic: [Quasi-Real-Time Calling Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying CDRs

Interface Description

This interface is used to query CDRs based on the calling party information, time, media type, and sub media type of the user.

Usage Description

1. Prerequisites

- The **IS_SUPPORT_QUERY_CALL_SESSION** parameter in the configuration file **platform.properties** has been set to **true**.
- The CDR recording function has been configured.

2. Precautions

This interface is disabled by default.

3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/realtimecall/{vdnId}/{userName}/callsession
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
Indicates the VDN ID.	int	Yes	Indicates the VDN ID.
userName	String	Yes	Indicates the user name that logs in.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.
Request Body			
startTime	long	Yes	Indicates the query start time (timestamp, in milliseconds).
endTime	long	Yes	Indicates the query end time (timestamp, in milliseconds). The interval between the start time and end time cannot be greater than two days.
userList	list	Yes	Indicates the user information list to be queried. The list can be empty but cannot be null. The maximum length of the list cannot exceed 3 records. For details, see Table 2 .

Table 2 Parameter description of userList

Parameter	Data Type	Mandatory (Yes/No)	Description
realCaller	string	Yes	Indicates the calling party to be queried, which cannot be empty.
mediaType	int	Yes	Indicates the media type to be queried. The value can be only the following numbers: 0, 1, 2, 4, and 22. If the value is 0, the recording information table is queried. If the value is not 0, the CDR table is queried.
subMediaType	int	Yes	Indicates the sub media type to be queried. The value ranges from 0 to 255.

Response Message

Table 3 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
resultContent	Object	Table 4

Table 4 Parameter description of resultContent

Parameter	Data Type	Description
callId	string	Indicates the call ID.
agentId	string	Indicates the work ID of an agent.
ccId	int	Indicates the contact center ID.
Indicates the VDN ID.	int	Indicates the VDN ID.
mediaType	int	Indicates the media type.
submediaType	int	Indicates the sub media type.
caller	string	Indicates the call initiator.
beginTime	long	Indicates the call start time.
endTime	long	Indicates the call end time.
connectTime	long	Indicates the call connection time.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /icsgateway/resource/realtimecall/1/testuser/callsession HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280 {"startTime":1511452800000,"endTime":1511625600000,"userList":[{"realCaller":"xxx","mediaType":x,"subMediaType":xxx}, {"realCaller":"xxx","mediaType":x,"subMediaType":xxx}, {"realCaller":"xxx","mediaType":x,"subMediaType":xxx}]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"result": {"resultContent": [{"callId": "1511592478-97","agentId": "110","ccId": 1, "vdnId": 1,"mediaType": 5,"subMediaType": null, "caller": "110","beginTime": 1511621281000,"endTime": 1511621397000,"connectTime": null}, {"callId": "1511578743-16777229","agentId": "110", "ccId": 1,"vdnId": 1,"mediaType": 1,"subMediaType": 255,"caller": "1234567898","beginTime": 1511578728000,"endTime": 1511579324000, "connectTime": 1511578752000}]},"message": "", "retcode": "0"}</pre>

Triggered Event

None

Error Code

- 10-100-007
- 10-200-017

Parent topic: [Quasi-Real-Time Calling Interfaces](#)

Interfaces for Obtaining Events

[Obtaining Events of a Specified User](#)

[Obtaining Events of a Specified appld](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Obtaining Events of a Specified User

Interface Description

This interface is used to obtain user events.

Usage Description

1. Prerequisites
 - The user has logged in to the system.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/icsevent/{vdnId}/{userName}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name that logs in.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	array	Indicates the return result of a successful query. For the parameter description of event , see Table 3 .

Table 3 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name.
vdnId	int	Indicates the VDN ID.
content	map	Indicates the content returned by the user. In the content, chatContent stores the text content returned by the user. For the parameter description of content , see Table 4 .

Table 4 Parameter description of content

Parameter	Data Type	Description
sender	string	Indicates the ID of the message sender.
chatContent	string	Indicates the message content.
callId	string	Indicates the unique ID of the current call.

Interface Example

Example Type	Reference Format
Example of a request packet	<code>GET /icsgateway/resource/icsevent/1/testuser HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000</code>
Example of a response packet	<code>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "event": { "eventType": "WECC_CHAT_RECEIVEDATA", "userName": "q", "vdnId": 1, "content": {"sender": "310", "chatContent": "qqq", "callId": "1438685892-16849196"} }}</code>

Triggered Event

- None

Error Code

- 10-100-002
- 10-100-006

Parent topic: [Interfaces for Obtaining Events](#)

Obtaining Events of a Specified appld

Interface Description

This interface is used to obtain all user events who log in from a Specified appld by polling.

Usage Description

1. Prerequisites
The app information has been configured in the **appConfig.xml** file.
2. Precautions
You are advised not to use the interface.
3. Use restrictions
None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/icsevent/{appld}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
appld	string	Yes	Indicates the ID of a third-party application. The value is a string of 0 to 10 case-sensitive letters. The ID must have been configured in the appConfig.xml file.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	array	Indicates the return result of a successful query. For the parameter description of event , see Table 3 .

Table 3 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content.

Interface Example

Example Type	Reference Format
Example of a request packet	GET /icsgateway/resource/icsevent/100 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8000
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": null, "retcode": "0", "event": [{"eventType": "WECC_PROVIDER_IN_SERVER", "userName": "291", "vdnId": 1, "content": null}] }

Triggered Event

- None

Error Code

- 10-100-002
- 10-100-007

Parent topic: [Interfaces for Obtaining Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Interfaces for Querying Queue Devices

[Querying Queue Statistics Based on the Access Code](#)

[Querying Queue Statistics Based on ID of the Skill Queue](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying Queue Statistics Based on the Access Code

Interface Description

This interface is used to query queue statistics based on the access code.

Usage Description

1. Prerequisites
 - None
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/queuedevice/getskillstatistic
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.
Request Body			
vdnId	int	No	Indicates the VDN ID. The default value is 0.
accessCodes	List<String>	No	Indicates the access code to be queried. The array contains a maximum of 30 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the return result of a successful query. Key: access code. Value: queue statistics. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
accessCode	string	Indicates the access code.
deviceNo	int	Indicates the device serial number.
queueSize	int	Indicates the number of calls that are currently waiting in the queue.
queueTime	long	Indicates the longest waiting time (sec) among all queuing calls.
loggedOnAgents	int	Indicates the number of registered agents at present.
availAgents	int	Indicates the number of available agents at present.
skillDescrip	string	Indicates the description of the skill.
maxQueueSize	int	Indicates the maximum number of calls that can wait in the queue.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /icsgateway/resource/queuedevice/getskillstatistic HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280 {"vdnId": "1", "accessCodes": ["1009"]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"1009": {"accessCode":"1009","deviceNo":10,"queueSize":0,"queueTime":0,"loggedOnAgents":1,"availAgents":0,"skillDescrip":"Text chat_jinsitao","maxQueueSize":100}}}</pre>

Triggered Event

- None

Error Code

- 10-100-007
- 10-100-013
- 10-100-014

Parent topic: [Interfaces for Querying Queue Devices](#)

Querying Queue Statistics Based on ID of the Skill Queue

Interface Description

This interface is used to query queue statistics based on ID of the skill queue.

Usage Description

1. Prerequisites
 - None
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/queuedevice/getskillstatisticx
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.
Request Body			
vdnId	int	No	Indicates the VDN ID. The default value is 0.
skillIds	List<int>	No	Indicates the skill queue to be queried. The array contains a maximum of 30 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Map	Indicates the return result of a successful query. Key: skill queue ID. Value: queue statistics. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
accessCode	string	Indicates the access code.
deviceNo	int	Indicates the device serial number.
queueSize	int	Indicates the number of calls that are currently waiting in the queue.
queueTime	long	Indicates the longest waiting time (sec) among all queuing calls.
loggedOnAgents	int	Indicates the number of registered agents at present.
availAgents	int	Indicates the number of available agents at present.
skillDescrip	string	Indicates the description of the skill.
maxQueueSize	int	Indicates the maximum number of calls that can wait in the queue.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /icsgateway/resource/queuedevice/getskillstatisticx HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280 {"vdnId": "1", "skillIds": ["10"]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"10": {"accessCode":null,"deviceNo":10,"queueSize":1,"queueTime":8,"loggedOnAgents":1,"availAgents":0,"skillDescrip":"Text chat_jinsitao","maxQueueSize":100}}}</pre>

Triggered Event

- None

Error Code

- 10-100-007
- 10-100-013

Parent topic: [Interfaces for Querying Queue Devices](#)

Multimedia Conference Interfaces

[Applying for a Multimedia Conference and Requiring the Current Agent to Participate in the Conference](#)

[Re-inviting the Current Agent to Participate in the Multimedia Conference](#)

[Ending the Multimedia Conference](#)

[Reporting Conference Participation Results](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Applying for a Multimedia Conference and Requiring the Current Agent to Participate in the Conference

Interface Description

This interface is used to apply for a multimedia conference and require the current agent to participate in the conference.

Usage Description

1. Prerequisites
 - The user has logged in to the system.
 - A text chat, CTD, or callback session has been set up.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/meetingcall/{vdnId}/{userName}/requestmeeting?callId={callId}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name that logs in.
callId	string	Yes	Indicates the unique ID of the current call.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /icsgateway/resource/meetingcall/1/testuser/requestmeeting?callId=1514337973-16777431 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- [WECC_MEETING_PREPARE_JOIN](#) (Will Participate in the Multimedia Conference)

Error Code

- 10-100-006
- 10-100-007
- 10-100-009
- 10-100-012
- 10-200-003

- 10-200-007
- 10-300-001

Parent topic: [Multimedia Conference Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Re-inviting the Current Agent to Participate in the Multimedia Conference

Interface Description

This interface is used to re-invite the current agent to participate in the multimedia conference.

Usage Description

1. Prerequisites
 - The user has logged in to the system.
 - A multimedia conference has been created.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/meetingcall/{vdnId}/{userName}/reinvitemeeting?confId={confId}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name that logs in.
confId	string	Yes	Indicates the unique ID of a conference.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Description
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /icsgateway/resource/meetingcall/1/testuser/reinvitemeeting?confId=13107325 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 10-100-006
- 10-100-009
- 10-100-012
- 10-200-003
- 10-200-007

- 10-300-002

Parent topic: [Multimedia Conference Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Ending the Multimedia Conference

Interface Description

This interface is used by a user to end a multimedia conference.

Usage Description

1. Prerequisites
 - The user has logged in to the system.
 - A multimedia conference has been created.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/meetingcall/{vdnId}/{userName}/stopmeeting?confId={confId}
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name that logs in.
confId	string	Yes	Indicates the unique ID of a conference.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /icsgateway/resource/meetingcall/1/testuser/stopmeeting?confId=13107325 HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

- None

Error Code

- 10-100-006
- 10-100-009
- 10-100-012
- 10-300-002

Reporting Conference Participation Results

Interface Description

This interface is used by a user to report conference participation results.

Usage Description

1. Prerequisites
 - The user has logged in to the system.
 - A multimedia conference has been created.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/meetingcall/{vdnId}/{userName}/reportresult
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name that logs in.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.
Request Body			
confId	long	Yes	Indicates the unique ID of a conference.
result	int	Yes	Indicates conference participation results. 0 : Succeed 1 : Fail
cause	int	Yes	Indicates the failure cause code returned by the TUP component.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /icsgateway/resource/meetingcall/1/testuser/reportresult HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8280 {"confId": "1455537015", "result": "0", "cause": "0"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0"}</pre>

Triggered Event

- None

Error Code

- 10-100-006
- 10-100-009
- 10-100-012
- 10-300-002

Parent topic: [Multimedia Conference Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Parameter Configuration Interfaces

[Obtaining the Operation Parameters of a Multimedia Client](#)

[Obtaining the Media Gateway Information](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Obtaining the Operation Parameters of a Multimedia Client

Interface Description

This interface is used to obtain the operation parameters of a multimedia client.

Usage Description

1. Prerequisites
 - The user has logged in to the system.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/queryconfig/{vdnId}/{userName}/getclientparam
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name that logs in.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
LogLevel	int	Indicates the log level. The options are as follows: 0 : Error 1 : Warning 2 : Info 3 : Debug
LogKeepDays	int	Indicates the number of days for which the log is kept. The value ranges from 0 to 3650 . 0 indicates that the log will not be deleted.
SipLocalPort	int	Indicates the voice SIP port of the client.
RtpLocalPort	int	Indicates the voice media port of the client.
SipTransMode	int	Indicates the SIP transmission mode. The options are as follows: 1 : UDP 2 : TLS 3 : TCP
RtpTransMode	int	Indicates the media transmission mode. The options are as follows: 0 : Both Real-time Transport Protocol (RTP) and Secure RTP (SRTP) are supported. 1 : Only RTP is supported.

Parameter	Data Type	Description
		2: Only SRTP is supported.
RegisterMode	int	Indicates the phone number registration mode. The options are as follows: 0: Simultaneous registration 1: Sequential registration
AnonymousCard	string	Indicates an anonymous card.
VideoDevices	array	Indicates a camera configuration object. For the parameter description of VideoDevices , see Table 4 .

Table 4 Parameter description of VideoDevices

Parameter	Data Type	Description
No	int	Indicates the number of a camera.
Type	int	Indicates the camera type. The options are as follows: 1: primary camera 2: extended camera
Name	string	Indicates the camera name.
VideoFrameRate	int	Indicates the video frame rate of the camera.
VideoResolution	int	Indicates the video resolution of the camera. 1280 x 720 960 x 720 704 x 576 640 x 480 352 x 288 320 x 240 176 x 144 160 x 120
Desc	string	Provides the camera description.

Interface Example

Example Type	Reference Format
Example of a request packet	GET /icsgateway/resource/queryconfig/1/testuset/getclientparam HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "LogLevel": 2, "LogKeepDays": 100, "SipLocalPort": 2048, "RtpLocalPort": 2048, "SipTransMode": 2, "RtpTransMode": 2, "RegisterMode": 1, "AnonymousCard": "AnonymousCard", "VideoDevices": [{ "No": 1, "Type": 1, "Name": "CAM1", "VideoFrameRate": 30, "VideoResolution": "1280*720", "Desc": "CAM1" }, { "No": 2, "Type": 2, "Name": "CAM2", "VideoFrameRate": 25, "VideoResolution": "640*480", "Desc": "CAM2" }] } }

Triggered Event

- None

Error Code

- 10-100-006
- 10-100-013
- 10-100-016
- 10-100-017

Parent topic: [Parameter Configuration Interfaces](#)

Obtaining the Media Gateway Information

Interface Description

This interface is used to obtain the media gateway information.

Usage Description

1. Prerequisites
 - The user has logged in to the system.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/queryconfig/{vdnId}/{userName}/requiremediagwinfo
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name that logs in.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	map	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
mgelp	string	Indicates the entry IP address of the media gateway.
mgePort	int	Indicates the entry port of the media gateway.
mgeDomain	string	Indicates the domain name of the media gateway.

Interface Example

Example Type	Reference Format
Example of a request packet	GET /icsgateway/resource/queryconfig/1/testuser/requiremediagwinfo /icsgateway/resource/queryconfig/1/testuser/getclientparam HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "mgePort": 1064, "mgeIp": "127.0.0.1", "mgeDomain": "test.com" } }

Triggered Event

- None

Error Code

- 10-100-006
- 10-100-016
- 10-100-017
- 10-100-018

Parent topic: [Parameter Configuration Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Verification Code Interfaces

[Obtaining the Call Verification Code](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Obtaining the Call Verification Code

Interface Description

This interface is used to obtain the verification code before the user initiates a call, and check the verification code in the call initiation interface

Usage Description

1. Prerequisites
 - The user has logged in to the system.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/verifycode/{vdnId}/{userName}/verifycodeforall
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name that logs in.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	string	It is a picture encoded based on Base64.

 NOTE

This picture can be directly used on an HTML page, and the method is ``, where XXXXXX indicates the **result** parameter in the message body.

Interface Example

Example Type	Reference Format
Example of a request packet	GET /icsgateway/resource/verifycode/1/testuser/verifycodeforall HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": "/9j/4AAQSkZJRgABAgAAAQABAAD/2wBDAAGBgCGBqGHBwcJCQgKDBQNDAsLDBkSEwUHROfHh0a\r\nhNBwgJC4nICIsIxwcKDcpLDAxNDQ0Hyc5PTgyPC4zNDU/2wBDAQkJCWkLDBoNRdyIRwhmJiYmJiY\r\nnmJiYmJiYmJiYmJiYmJiYmJiYmJiYmJiYmJiYmJiYmJiYmJiYmJl/wAARCAAJAGkDASIA\r\nr\nehAEBAxEB/8QAHA AAAQUBAQEBAQEAAAAAAAAAAAEACAwFbgICQoL/8QATRAAAEGDAWEAwFUaBAQ\r\nr\neAAFA9AQIDAAQRBRIhMUEGE1FhByJxFDKBkaEII0KxwRVS0fAkM2JyggkKFhcYGRolJicoKSo0NTY3\r\nr\nodK6QORFRkdISUpTVFVWV1hZWmNkZWZnaGlqc3R1ndd4eXqDIWGH4IjIpKTlJWW15iZmqKjpKmW\r\nr\nnp6ipqrKztLWt7i5usLDxMXGx8JjYtLTlnXWU192JuHi4+Tl5ufo6erx8vP9fb3+Pn6/8QAHwEA\r\nr\nAwEBAQEBAQEBAQAAAAAAAAECAwQFBgcICQoL/8QATREAAECBAQDBAcFBAQAAQJ3AAECAxEEBSEx\r\nr\nBhYkBUQdhcRMiMoEIFEKRobHBCSMzUvAVYnLRChYkNOEl8RCYGRomJygpKfjU2Nzg5OkNERUZHSElK\r\nr\nU1RVVldYWVvpjZGVmZ2hpandN0dXZ3eHl6goOEhYaHiImKkpOUlZaXmJmaoqKOpaanqKmqsrO0tb3\r\nr\nnuLM6wsPExcbyMnK0tPUlDbX2Nna4UPk5ebn6OngrV9P9fb3+Pn6/9oADAMBAAIRAxEAPD0oeH9\r\nr\nnb0/bNY2+nmnAWexFiI20/fmhX.

Example Type	Reference Format
	/cseRwdp4yBipLPxVNBLLFqX2a0uI1GLW/ufKL16lch2UI65Unc\r\nuevXtXSEapG4INnOpByMNEQeMc/Nnv6V59r0DeJPIa6ZfWJmt7K2LzQwTz3ZGc7jtxyU/Ks3oKp\r\nX 01jqbmfxASUEpb6fgHGW1aFc/g2DTra61d7dbnQtIiihbO1Yr+OW2bBwcKOBg5+4Vyeua5hvDOh\r\nn6JPANQ0We+06ZsG6InimtyScB1B2ycFeUxwrHB4zD4mq069i8M+GtFu / tOm3FwZVWJgXjUnnJJ6/\r\nmM5wwGOh9nBSbtzf1/ka0ptvaNvK/+26D/b2p23z6joE8EHTzIbhJQp9W6bVxnLHgVDFmZYn1G20y\r\nnf50EjiWaE286gD748wr0AxIBkbV6qN p 5ZL4SeGZ8iO/1Qsv3lMiBl+oMerWJ480238O6XpHhnSPN\r\nn3XDMZXZsPMC3yh9oAb5mOMjjHHetVFS0Tir16dKm5pfLX/MtXvjfsjDDbwTSQXNtloZCRKbeTj5U\r\nnkU4eH j K/N25OcbR2Nh40t9QtVnt9LlKYdGNvCJEDY5AYHnrXPRfDLSrKwMF7YSXZxg31tOwlU9c+\r\nnUflwOehYnjjnA5fwfq9z4X8WT6QbrNmZihEmVTOcBmB+52yeq46HGDmqaSco s 4o1a1GadWK5Zdm9\r\nnd0fVPELzafII9I1WJ0Kyq8tp8gKMG+b5uB8vJqpH430XU/Egghkne30+CW4eYQsUDfKobj5sBwKb\r\nnyaAOfpXH614/1vxTDJY6BYT29vsJnkTLPt75 Y cKv+c9qvwAumLd+JLmBtNj1J4IGdI2k2qGV1AY5I\r\nnDDn7p65rGNV8yXQ7ZKL1SPVbrxvBPE39i2810gyrXssUi20LYPDEKWJzt4A53DkViJd6WmqRXN/q\r\nnj6nfwsGS6u 0Y QQngfu4UHBxjOcqgDmuhh0fVze20k39miOBdsa4dlhxnGxBtGMbRySeM57VonSr2\r\nrn4i1S61q6+dsj7MiQhR1ABwW/HPSt3OW0NPzFGEgXrU1/r0Zk2eveHLaQzzam9zdHrNL C5 K+yjb8o5\r\nnPA9avf8ACZaB/wA//wD5Bk/+JgyPD+ns0LXCS3bxDctdTNL1GCcMdvP0qb+xdK/6B11/34X/AArO\r\nrn0u/4f8E1/dLo/v8A+AXq8/n8BanqPirUtSutW+y2t2 du 2zc+Y6DACsSAAmAevSurOlXtxPKl1rV1\r\nrn87ZH2ZEHcjgADgt+Oe1crZ39o3ji80bXoIR5PzWDZyyOHU9j5j5pJGOGhKvInK3Uwmo03MZ1/4Q\r\nrn0/QIZ7zQfE8tvqFsGb YP bhGLleqkADntg+1c5DBrXi/xBa6vpmmJbEIY5p4rdDGZcEuxDfKW07P\r\nrnzc9Oe1eu6pqOl+F9InuCLE2RVLPegC+Y+OAAPOBXnXgHW7rwdWekarFFbWGp011DNICG3nCj Jz \r\nnjBCemfmFOkTLQIJRnaHbUyBo3i/Q7lppr+W0us5hSRiY5yQ3yoy5QMOp+U1ScjHWq2o65P4i8T+H\r\nrnL152aZhCrBYGLcTMCAvRugIzlyBXr3ifX9C0ntZE1eS21DpuW Od RIZepX5eeMr1fPGe9dy6ZeaT\r\nrnp+16o8gQTOZiIlikLHggnj5cjbXr61tBdzLHOLocyVrNHsMt41vfSRfbrWryXb1t5pIJIiCF0\r\nrn5E+VB8ynLle9ebpZ/iUbafTSn zk tZWxcgcPOzfYT/tY98Y7egeGW8L3mmvNa3VnaRJGwkt0+SS\r\nrnNtnJkd/nfAcDdueORXN+DSNU+Jt/q1rC0tlb7yHRAuFI2KdoA6jJwBnrX2pRsk7HPiOatgr7tOx\r\nrnOw k0 LTp7C7xP91U/ZLYwvEQJCP3iNgFSnnKsB7McAVq+G11aWnj3UmeXyYXglWMzDYf9YpAPPBwP\r\nrnWvRtbdrq9s7nTlE13p6vckKStt4VoiMHazgtjIz1CB3I808Jyx6n8StUli iR /tLzyQxXEasjfvN+\r\nrn1+u3gH5lyQcHkZB5JaOMTsh1T37nt9FcbI15byCGynmW5iG+Swa4LPGq9DFyA8Z4XcVbHTG7Ki9b\r\nrn6rIAk82qC3id0DeRK0TnPVZF2jscKcNwSV Hb ZXFQacr2tqdJRWeJNXiSQvb2c5BJTy5WjLDsMEEZ\r\nrn/HFQf2hrP/QC/wDJtP8ACjmE6iW9/uZr1yvjrTPlDQZbq6tUkntl/dSZIzeemR1HsaKKHsOavF3\r\nrnPOvhvo2n6r rT i+tUnEQ3Krk4yPuDd+Nd98TLG1uPBF3NLAJS25RoXI5Ql1BwfcGiinh916mNDSnd\r\nrnHkXg7TrTUvEVpb3cIliaVaykkAgkele2+JNG05/B99aGzi8iOFpEUDGHVeGyOc8daK K On8Z04jW6\r\nrnfy+cq+gPhTY21p4MtJoIVSW5BeZx1c5I5/AUUVpV2PDy1fvX6Fy8ysur36sy3NvNHBE6sRhNsbbS\r\nrnOhG52PPr7Cvk/DF1MvxQmnd/ALy8cM2BzulAb8wT RR XHU/iRPXn/Df9dT2HxH+78P310nE9pBjc\r\nrnQSDrHIqEgj+RHQgkHIJFzelzOX803QIWbUbTfdlVCiVvLD7iBxncScjloog5bG1Rfuk/NFi4/wCJ\r\nrnV410azsf3Freef50C /c +RMrtXonJJO3Ge+a6GiitJbL+uppPaL8v1Z//2Q=="}

Triggered Event

- None

Error Code

- 10-100-006
- 10-200-009

Parent topic: [Verification Code Interfaces](#)

Server Connection Interfaces

[Sending Messages Without Call](#)

[Confirming the Receiving of a Message Sent by an Agent Without Call](#)

[Sending an AML SMS Message When There Is No Call](#)

[Sending a Certificate Expiration Alarm](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Sending Messages Without Call

Interface Description

This interface is used to send message content to an online agent without call.

Usage Description

1. Prerequisites
An agent is online.
2. Precautions
None
3. Use restrictions
This interface is an internal interface between the ICS Server and SMS adapter and cannot be used in other scenarios.

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/servermode/messagewithoutcall
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.
Request Body			
vdnId	int	Yes	Indicates the VDN ID.
userName	string	Yes	Indicates the user name, which contains 1 to 20 case-sensitive letters and digits.
agentId	int	Yes	Indicates the work ID of an agent, ranging from 101 to 59999.
content	string	Yes	Indicates the message content, which cannot be left empty and can contain a maximum of 6144 characters.
subMediaType	int	Yes	Indicates the sub media type, which can contain 1 to 255 characters.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
result	Object	Table 3

Table 3 Parameter description of result

Parameter	Data Type	Description
seqNo	int	Indicates the message sequence number.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /icsgateway/resource/servermode/messagewithoutcall HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280 {"vdnId": 1, "userName": "TestUser", "agentId":110,"content":"test interface", "subMediaType":2}</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": { "seqNo": 1 } }

Triggered Event

None

Error Code

- 10-100-004
- 10-100-007
- 10-100-009

Parent topic: [Server Connection Interfaces](#)

Confirming the Receiving of a Message Sent by an Agent Without Call

Interface Description

This interface is used to confirm that a message sent by an agent without call is received.

Usage Description

- Prerequisites
 - The server connection mode is configured.
 - The [WECC_MESSAGE_WITHOUTCALL_EVENT \(Agent Sending Content to a User Without Call\)](#) event sent by an agent has been received.
- Precautions
 - None
- Use restrictions
 - This interface is an internal interface between the ICS Server and SMS adapter and cannot be used in other scenarios.

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/servermode/messagewithoutcall
Request Method	PUT

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.
Request Body			
vdnId	int	Yes	Indicates the VDN ID.
receiver	string	Yes	Indicates the message recipient, which cannot be left empty and can contain a maximum of 24 characters.
dataSeqNo	int	Yes	Indicates the message ID, which comes from the WECC_MESSAGE_WITHOUTCALL_EVENT (Agent Sending Content to a User Without Call) event.
webmGroupId	int	Yes	Indicates the WebM ID, which comes from the WECC_MESSAGE_WITHOUTCALL_EVENT (Agent Sending Content to a User Without Call) event.
result	int	Yes	Indicates the self-defined confirmation result.
senderSessionId	int	Yes	Indicates the agent ID, which comes from the WECC_MESSAGE_WITHOUTCALL_EVENT (Agent Sending Content to a User Without Call) event.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>PUT /icsgateway/resource/servermode/messagewithoutcall HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json; charset=UTF-8 Host: 192.168.0.0:8280 {"vdnId": 1, "receiver": "TestUser", "dataSeqNo":1, "webmGroupId":110,"result":1, "senderSessionId":1}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

None

Error Code

- 10-100-004
- 10-100-009

Parent topic: [Server Connection Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Sending an AML SMS Message When There Is No Call

Interface Description

This interface is used to send AML SMS message content to the ICP system when there is no call.

Usage Description

1. Prerequisites

- The AML function must be enabled for the corresponding VDN.

2. Precautions

None

3. Use restrictions

This interface is an internal interface between the ICS Server and SMS adapter and cannot be used in other scenarios.

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/servermode/amlmessage
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.
Request Body			
vdnId	int	Yes	Indicates the VDN ID.
sender	string	Yes	Indicates the sender number, that is, number of the incident reporter. The value is a numeric string of 1 to 24 digits.
content	string	Yes	Indicates the content of an AML message. The value contains a maximum of 160 English characters.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /icsgateway/resource/servermode/amlmessage HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type: application/json;charset=UTF-8 Host: 192.168.0.0:8280 {"vdnId": 1, "sender": "13123456789", "content": "A\\\"ML=1;lt=+54.76397;lg=-0.18305;rd=50;top=20130717141935;lc=90;pm=W;si=123456789012345;ei=1234567890123456;mcc=234;mnc=30; ml=128"} A\</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Triggered Event

None

Error Code

- 10-100-004
- 10-100-007
- 10-100-009

- 10-100-018
- 10-100-019

Parent topic: [Server Connection Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Sending a Certificate Expiration Alarm

Interface Description

This interface is used to send an alarm to the monitoring console when the client certificate expires.

Usage Description

1. Prerequisites
The user has logged in to the system.
2. Precautions
None
3. Use restrictions
This interface is an internal interface between the ICS Server and SMS adapter and cannot be used in other scenarios.

Interface Prototype

Request URL	http(s)://ip:port/icsgateway/resource/alarm/send
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the ICS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the ICS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
guid	string	Yes	Indicates the user authentication Information.
Request Body			
alarmKind	int	Yes	The minimum value is 1.
alertId	int	Yes	The minimum value is 1.
ip	string	Yes	This parameter is mandatory.
rawData	string	Yes	The value contains a maximum of 200 bytes.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /icsgateway/resource/alarm/send HTTP/1.1 guid:590b218cdcd61aad2e86de127f420cf9.ICSGateway1 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:8280 {"alarmKind": "1", "alertId": "1", "ip": "w", "rawData": "ss"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message": "", "retcode": "0"}</pre>

Parent topic: [Server Connection Interfaces](#)

Events

- [Call Events](#)
- [Multimedia Conference Events](#)
- [Inspection Notification Events](#)
- [Other Related Events](#)

Parent topic: [ICS Server Interface \(RESTful\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Call Events

[WECC_WEBM_CALL_CONNECTED \(Call Setup\)](#)
[WECC_WEBM_CALL_DISCONNECTED \(Call Disconnection\)](#)
[WECC_WEBM_CALL_QUEUING \(Call Queuing\)](#)
[WECC_WEBM_QUEUE_TIMEOUT \(Queuing Timeout\)](#)
[WECC_WEBM_CANCEL_QUEUE \(Queuing Cancellation\)](#)
[WECC_WEBM_CALL_FAIL \(Call Failure\)](#)
[WECC_WEBM_CALL_TRANSFER \(Call Transfer\)](#)
[WECC_CHAT_POSTDATA_SUCC \(Message Sending Success\)](#)
[WECC_CHAT_POSTDATA_FAIL \(Message Sending Failure\)](#)
[WECC_CHAT_RECEIVEDATA \(Message Receiving Success\)](#)
[WECC_CHAT_RECEIVEDDATA_EX \(Receiving of an Agent's Message Requiring a Reply\)](#)

Parent topic: [Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

WECC_WEBM_CALL_CONNECTED (Call Setup)

Event Description

A call is set up.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
caller	string	Indicates the user name that logs in.
vcConfInfo	map	Indicates VC call information. If the call is not a VC call, the value is empty. For the parameter description of vcConfInfo , see Table 4 .
called	string	Indicates the called party, that is, the work ID of the current agent.
uvid	long	Indicates the unique call ID of the same user (used for collaboration call).
agentId	string	Indicates the work ID of the agent who answers the call.
clickToDial	string	Indicates the combination of the special route access code and UIVD returned in a CTD call.
callId	string	Indicates the unique ID of the current call.
mediaType	int	Indicates the type of the current call.

Table 4 Parameter description of vcConfInfo

Parameter	Data Type	Description
callId	string	Indicates the unique ID of the current call.
serverIp	string	Indicates the SC address.
port	int	Indicates the SC port.
isRecordEnabled	int	Indicates whether to record the VC call. 1: Record. Other values: Not record.
protocolType	string	Indicates the SC protocol type.
accessNumber	string	Indicates the access code of the VC call.
clustered	string	Reserved.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_WEBM_CALL_CONNECTED","userName":"UserAppMe","vdnId":2,"content":{"caller":"UserAppMe","vcConfInfo":{"callId":"1476964703-16777249-22","serverIp":"192.168.0.0","port":5060,"isRecordEnabled":1,"protocolType":"UDP","accessNumber":"0755666*5624840063243513","clustered":""},"called":"1010","uvid":"2867202","agentId":"1010","clickToDial":"","callId":"1476964703-16777249","mediaType":22}}}</pre>

Parent topic: [Call Events](#)

WECC_WEBM_CALL_DISCONNECTED (Call Disconnection)

Event Description

A call is released.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
caller	string	Indicates the calling party.
causeId	string	Indicates the call releasing reason code on the CTI platform.
causeDesc	string	Indicates the call releasing reason description on the CTI platform.
called	string	Indicates the called party, that is, the work ID of the current agent.
uvid	long	Indicates the unique call ID of the same user (used for collaboration call).
agentId	string	Indicates the work ID of the agent who answers the call.
callId	string	Indicates the unique ID of the current call.
mediaType	int	Indicates the type of the current call.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_WEBM_CALL_DISCONNECTED","userName":"jst","vdnId":1,"content":{"caller":"jst","causeId":"1055","causeDesc":"CLRC_WEBM_NORMAL_RELEASE","called":"291","uvid":96764349,"agentId":"291","callId":"1441699677-16777229","mediaType":1}}}</pre>

Parent topic: [Call Events](#)

WECC_WEBM_CALL_QUEUEING (Call Queuing)

Event Description

As all agents are busy now, the call enters the waiting queue.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
uvid	long	Indicates the unique call ID of the same user (used for collaboration call).
callId	string	Indicates the unique ID of the current call.
mediaType	int	Indicates the type of the current call.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_WEBM_CALL_QUEUEING","userName":"jst","vdnId":1,"content":{"uvid":594323521,"callId":"1442894279-16777248","mediaType":1}}}</pre>

Parent topic: [Call Events](#)

WECC_WEBM_QUEUE_TIMEOUT (Queuing Timeout)

Event Description

Timeout in queue.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
caller	string	Indicates the calling party.
causeId	int	Indicates the call releasing reason code on the CTI platform.
causeDesc	string	Indicates the call releasing reason description on the CTI platform.
called	string	Indicates the called party, that is, the work ID of the current agent.
uvid	long	Indicates the unique call ID of the same user (used for collaboration call).
agentId	string	Indicates the work ID of the agent who answers the call.
callId	string	Indicates the unique ID of the current call.
mediaType	int	Indicates the type of the current call.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_WEBM_QUEUE_TIMEOUT","userName":"jst","vdnId":1,"content": {"caller":"jst","causeId":22002,"causeDesc":"ROUTING FAILED WHEN THE QUEUED TIMED OUT","called":"0","uvid":98377028,"agentId":"0","callId":"1441699956-16777230","mediaType":1}}}</pre>

Parent topic: [Call Events](#)

WECC_WEBM_CANCEL_QUEUE (Queuing Cancellation)

Event Description

A user cancels queuing a call.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
caller	string	Indicates the calling party.
causeId	int	Indicates the call releasing reason code on the CTI platform.
causeDesc	string	Indicates the call releasing reason description on the CTI platform.
called	string	Indicates the called party, that is, the work ID of the current agent.
uvid	long	Indicates the unique call ID of the same user (used for collaboration call).
agentId	string	Indicates the work ID of the agent who answers the call.
callId	string	Indicates the unique ID of the current call.
mediaType	int	Indicates the type of the current call.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_WEBM_CANCEL_QUEUE","userName":"jst","vdnId":1,"content": {"caller":"jst","causeId":22001,"causeDesc":"ROUTE_FAILURE_CAUSE_IS_WHEN_CANCEL_QUEUE","called":"0","uvid":98377028, "agentId":"0","callId":"1441699956-16777230","mediaType":1}}}</pre>

Parent topic: [Call Events](#)

WECC_WEBM_CALL_FAIL (Call Failure)

Event Description

A user fails to set up a call.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
caller	string	Indicates the calling party.
causeId	int	Indicates the call releasing reason code on the CTI platform.
causeDesc	string	Indicates the call releasing reason description on the CTI platform.
called	string	Indicates the called party, that is, the work ID of the current agent.
uvid	long	Indicates the unique call ID of the same user (used for collaboration call).
agentId	string	Indicates the work ID of the agent who answers the call.
callId	string	Indicates the unique ID of the current call.
mediaType	int	Indicates the type of the current call.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_WEBM_CALL_FAIL","userName":"jst","vdnId":1,"content": {"caller":"jst","causeId":20139,"causeDesc":"QUEUE_AND_AGENT_INVALID_FAILED","called":"0","uvid":99452150,"agentId":"0", "callId":"1441700180-16777231","mediaType":1}}}</pre>

Parent topic: [Call Events](#)

WECC_WEBM_CALL_TRANSFER (Call Transfer)

Event Description

An agent transfers a call to another agent.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
caller	string	Indicates the calling party.
called	string	Indicates the called party, that is, the work ID of the current agent.
uvid	long	Indicates the unique call ID of the same user (used for collaboration call).
agentId	string	Indicates the work ID of the agent who answers the call.
callId	string	Indicates the unique ID of the current call.
mediaType	int	Indicates the type of the current call.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_WEBM_CALL_TRANSFER","userName":"jst","vdnId":1,"content":{"caller":"jst","called":"292","uvid":99810518,"agentId":"292","callId":"1441700246-16777232","mediaType":1}}}</pre>

Parent topic: [Call Events](#)

WECC_CHAT_POSTDATA_SUCC (Message Sending Success)

Event Description

A user sends a text message successfully.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
chatContentType	string	Indicates the type of the sent content. The value 0 indicates a text message, and the value 1 indicates a file.
chatContent	string	Indicates the sent content.
callId	string	Indicates the unique ID of the current call.
chatId	long	Indicates the message ID.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_CHAT_POSTDATA_SUCC","userName":"jst","vdnId":1,"content":{"chatContentType":"0","chatContent":"121212","callId":"1503297816-16777401","chatId":121}}}</pre>

Parent topic: [Call Events](#)

WECC_CHAT_POSTDATA_FAIL (Message Sending Failure)

Event Description

A user fails to send a text message.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
chatContentType	string	Indicates the type of the sent content. The value 0 indicates a text message, and the value 1 indicates a file.
chatContent	string	Indicates the sent content.
callId	string	Indicates the unique ID of the current call.
chatId	long	Indicates the message ID.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_CHAT_POSTDATA_FAIL","userName":"jst","vdnId":1,"content":{"chatContentType":"0","chatContent":"121212","callId":"1503297816-16777401","chatId":121}}}</pre>

Parent topic: [Call Events](#)

WECC_CHAT_RECEIVEDATA (Message Receiving Success)

Event Description

A user receives a message from an agent.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
sender	string	Indicates the sender of the message.
chatContentType	string	Indicates the type of the received content. The value 0 indicates a text message, and the value 1 indicates a file.
chatContent	string	Indicates the received content.
callId	string	Indicates the unique ID of the current call.

Event Example

Table 4 Example when chatContentType is 0

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_CHAT_RECEIVEDATA","userName":"jst","vdnId":1,"content":{"sender":"291","chatContentType":"0","chatContent":"2323","callId":"1441700548-16777233"}}</pre>

Table 5 Example when chatContentType is 1

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_CHAT_RECEIVEDATA","userName":"jst","vdnId":1,"content":{"sender":"111","chatContentType":"1","chatContent":{"remark":"fileupload","filePath":"/mnt/file/1/1/2017/11/16/1510833295-16777216/111/IGT7iUgRPhToVrrp.txt","fileName":"test.txt","msgType":"1"},"callId":"1441700548-16777233"}}</pre>

NOTE

The value of **chatContent** is in JSON format. In the value, **remark** indicates remarks, **msgType** indicates the message type, **fileName** indicates the file name, and **filePath** indicates the file path.

Parent topic: [Call Events](#)

WECC_CHAT_RECEIVEDDATA_EX (Receiving of an Agent's Message Requiring a Reply)

Event Description

A user receives a message from an agent and needs to invoke the interface [Confirming Message Receiving](#) to confirm the receiving.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
sender	string	Indicates the sender of the message.
chatContentType	string	Indicates the type of the received content. The value 0 indicates a text message, and the value 1 indicates a file.
chatContent	string	Indicates the received content.
callId	string	Indicates the unique ID of the current call.
senderSessionId	int	Indicates the ID of the message sender.
chatId	long	Indicates the message ID. The value ranges from 0 to 4294967295.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_CHAT_RECEIVEDDATA_EX","userName":"jst","vdnId":1,"content":{"sender":"110","chatContentType":"0","chatContent":"1212","callId":"1503297816-16777401","senderSessionId":110,"chatId":1955757892}}}</pre>

Parent topic: [Call Events](#)

Multimedia Conference Events

- [WECC MEETING PREPARE JOIN \(Will Participate in the Multimedia Conference\)](#)
- [WECC MEETING STOP \(Notifying the Conference Ending\)](#)
- [WECC MEETING STATUS \(Notifying the Conference Status\)](#)

Parent topic: [Events](#)

WECC_MEETING_PREPARE_JOIN (Will Participate in the Multimedia Conference)

Event Description

When a user attempts to join a multimedia conference, the event is used to return the user information and participant information.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
confId	long	Indicates the conference ID.
confInfo	string	Indicates conference information.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 {"message": "", "retcode": "0", "event": {"eventType": "WECC_MEETING_PREPARE_JOIN", "userName": "jst", "vdnId": 1, "content": {"confId": 0, "confInfo": "desktop101"}}}</pre>

Parent topic: [Multimedia Conference Events](#)

WECC_MEETING_STOP (Notifying the Conference Ending)

Event Description

After an agent who is a multimedia conference initiator successfully invites a user to join the conference, when the agent ends the conference, the event is used to notify the user of the multimedia conference ending. (This scenario is not involved currently. The event is reserved)

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Reserved.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_MEETING_STOP","userName":"jst","vdnId":1,"content":null}}</pre>

Parent topic: [Multimedia Conference Events](#)

WECC_MEETING_STATUS (Notifying the Conference Status)

Event Description

After a user who is a multimedia conference initiator successfully invites an agent to join the conference, the event is used to notify the user of the agent conference joining result.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
cause	int	Indicates the failure cause code returned by the TUP component.
confState	int	Indicates the conference status (0 indicates success and other values indicate failure).
agentId	string	Indicates the work ID of an agent.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_MEETING_STATUS","userName":"jst","vdnId":1,"content":{"cause":0,"confState":0,"agentId":"101"}}</pre>

Parent topic: [Multimedia Conference Events](#)

Inspection Notification Events

- [WECC_BE_QC_START \(Starting the Inspection\)](#)
- [WECC_BE_QC_STOP \(Stopping the Inspection\)](#)

Parent topic: [Events](#)

WECC_BE_QC_START (Starting the Inspection)

Event Description

An inspector inspects an agent who provides services for users.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
qcAgentId	string	Indicates the work ID of the inspector who has logged in.
qcType	int	Indicates the inspection type. 8 : Listen. 9 : Insert.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_BE_QC_START","userName":"jst","vdnId":1,"content":{"qcAgentId":"20016","qcType":8}}}</pre>

Parent topic: [Inspection Notification Events](#)

WECC_BE_QC_STOP (Stopping the Inspection)

Event Description

An inspector stops inspecting an agent who provides services for users.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
qcAgentId	string	Indicates the work ID of the inspector who has logged in.
qcType	int	Indicates the inspection type. 8 : Listen. 9 : Insert.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_BE_QC_STOP","userName":"jst","vdnId":1,"content":{"qcAgentId":"20016","qcType":8}}}</pre>

Parent topic: [Inspection Notification Events](#)

Other Related Events

[WECC_PROVIDER_IN_SERVER \(User Login\)](#)

[WECC_PROVIDER_SHUTDOWN \(Automatic User Logout\)](#)

[WECC_USER_LONGTIME_NOOPERATE \(No Operations Within a Long Period of Time\)](#)

[WECC_MESSAGE_WITHOUTCALL_EVENT \(Agent Sending Content to a User Without Call\)](#)

Parent topic: [Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

WECC_PROVIDER_IN_SERVER (User Login)

Event Description

The user logs in to the system successfully.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	null

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_PROVIDER_IN_SERVER","userName":"jst","vdnId":1,"content":null}}</pre>

Parent topic: [Other Related Events](#)

WECC_PROVIDER_SHUTDOWN (Automatic User Logout)

Event Description

The user automatically logs out. The user may not receive such an event

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	null

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_PROVIDER_SHUTDOWN","userName":"jst","vdnId":1,"content":null}}</pre>

Parent topic: [Other Related Events](#)

WECC_USER_LONGTIME_NOOPERATE (No Operations Within a Long Period of Time)

Event Description

A user does not perform any operations for a long period of time.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_USER_LONGTIME_NOOPERATE","userName":"jst","vdnId":1}}</pre>

NOTE

This event is only sent in the server interconnection mode, to tell the third party that the user does not perform operations for a long period of time. Users automatically log out if they do not invoke the ICS Gateway within 12 hours.

In **platform.properties**,

USER_TIMEOUT_FORSERVERMODE = 43200000 // indicates that agents will become unavailable if users do not perform any operations for a specific period of time.

USER_TIMEOUT_ALARMINTERVAL_FORSERVERMODE = 600000 // indicates that a WECC_USER_LONGTIME_NOOPERATE event is sent to the third-party server after a specific period of time if users do not perform any operations in the period.

Parent topic: [Other Related Events](#)

WECC_MESSAGE_WITHOUTCALL_EVENT (Agent Sending Content to a User Without Call)

Event Description

A user receives the content sent by an agent without call.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
userName	string	Indicates the user name that logs in.
vdnId	int	Indicates the VDN ID.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
receiver	string	Indicates the content recipient.
dataSeqNo	string	Indicates the message ID.
webmGroupId	string	Indicates the internal WebM ID.
senderSessionId	string	Indicates the work ID of an agent.
subMediaType	int	Indicates the sub media type, which can contain 1 to 255 characters.
chatContent	string	Indicates the message content.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"WECC_MESSAGE_WITHOUTCALL_EVENT","userName":null,"vdnId":1,"content":{"receiver":"291","dataSeqNo":"1","webmGroupId":"2323","senderSessionId":"1441","subMediaType":2,"chatContent":"XXXX"}}}</pre>

NOTE

This event is an internal event between the ICS Gateway and SMS adapter and cannot be used in other scenarios.

Parent topic: [Other Related Events](#)

Appendix

[Error Codes](#)

[Pushing a Request Based on pushUrl](#)

[Rich Media File Restrictions](#)

Parent topic: [ICS Server Interface \(RESTful\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Error Codes

Table 1 Error code description

Error Code	Description
10-100-002	The EVENT_METHOD configuration in platform.properties is incorrect.
10-100-003	CCS connection fails. The WAS service is unavailable.
10-100-004	The WebmAnyService is unavailable.
10-100-005	You do not have permission to invoke the interface.
10-100-006	The user has not logged in.
10-100-007	Empty or invalid parameters in the user's request.
10-100-008	The user has logged in to the system.
10-100-009	Resources are unavailable.
10-100-010	The method is not supported.
10-100-011	The status is incorrect.
10-100-012	WebmServer of the user is empty.
10-100-013	The VDN ID does not exist.
10-100-014	The access code does not exist.
10-100-015	The maximum number of concurrent login users has been reached.
10-100-016	The configuration agent is empty.
10-100-017	The configuration agent fails to send messages normally.
10-100-018	The AML function is not enabled.
10-100-019	The AML information table overflows.
10-200-001	The call matching the access code has existed.
10-200-002	Exceed the maximum number of concurrent calls.
10-200-003	The call does not exist.
10-200-004	Code conversion fails.
10-200-006	The call is not in the queuing state.
10-200-007	The call has not been set up.
10-200-008	The verification code is invalid.
10-200-009	The verification code fails to be generated.
10-200-010	The rich media file upload function is not enabled.
10-200-011	The file server is abnormal during rich media file upload.
10-200-012	The file name extension or file size does not meet the requirements during rich media file upload.
10-200-013	During rich media file upload, the file sending fails.
10-200-014	The rich media file to be downloaded does not exist.
10-200-015	The user does not have the permission to download the rich media file.
10-300-001	Is in the conference or applying for a conference.
10-300-002	The conference does not exist.

Parent topic: [Appendix](#)

Pushing a Request Based on pushUrl

NOTE

When the pushed mode is used, each agent event corresponds to a request. When the event pushing mode is used, the Heartbeat Detection Interface described in [Detecting Heartbeat](#) is invoked every minute.

- Request method
POST
- Request header
Content-Type: application/json; charset=UTF-8
- Request message
event: event content
- Request example
POST /ICSServerDemo/UserEventServlet HTTP/1.1
Content-Length: 123
Content-Type: application/json; charset=UTF-8
Host: 10.177.244.143:8072
Connection: Keep-Alive
User-Agent: Apache-HttpClient/4.3.6 (java 1.5)
Accept-Encoding: gzip,deflate
{ "message": "", "retcode": "0", "event": { "eventType": "WECC_PROVIDER_IN_SERVER", "userName": "testUser", "vdnId": 1, "content": null } }
- Response example

NOTE

The response sent by the server must be 200 OK. Otherwise, the ICS Server pushes the event again.

HTTP/1.1 200 OK
Server: Apache-Coyote/1.1
Content-Length: 0
Date: Fri, 02 Mar 2018 03:28:23 GMT

Parent topic: [Appendix](#)

Rich Media File Restrictions

Rich media file limitations are configured in `tomcat7/webapps/icsgateway/confing/mediafile.xml` in the ICS Server installation server. [Figure 1](#) shows the supported formats of files to be uploaded.

Table 1 Parameters

Parameter	Data Type	Description
id	int	Virtual call center ID.
subMediaType	int	Sub media type of the text chat skill queue. When a text chat skill queue is configured in the WAS, the sub media type can be obtained.
type	String	Allowed file name extension.
maxsize	int	Allowed file size, in MB.

Figure 1 mediafile.xml

```
<?xml version="1.0" encoding="UTF-8"?>
<mediafiles>
  <!-- the max value of maxsize is 10 -->
  <vdnId id="1">
    <mediaType subMediaType="0">
      <mediafile>
        <type>PNG</type>
        <maxsize>10</maxsize>
      </mediafile>
      <mediafile>
        <type>mp3</type>
        <maxsize>2</maxsize>
      </mediafile>
      <mediafile>
        <type>JPG</type>
        <maxsize>10</maxsize>
      </mediafile>
      <mediafile>
        <type>TXT</type>
        <maxsize>10</maxsize>
      </mediafile>
    </mediaType>
  </vdnId>
</mediafiles>
```

Parent topic: [Appendix](#)

CMS Server Interface (RESTful)

[About This Document](#)

[Interfaces](#)

[Secondary Development Guide](#)

[Appendix](#)

Copyright © Chengdu TD-Tech Co., Ltd.

About This Document

[Intended Audience](#)

[Symbol Conventions](#)

[Change History](#)

Parent topic: [CMS Server Interface \(RESTful\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Intended Audience

This document guides the secondary development of the operation and management system. Development personnel must have the following skills:

- Be familiar with the JSON format.
- Be familiar with knowledge related to HTTP request sending.

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Symbol Conventions

The symbols that may be found in this document are defined as follows.

Symbol	Description
 DANGER	Indicates an imminently hazardous situation which, if not avoided, will result in death or serious injury.
 WARNING	Indicates a potentially hazardous situation which, if not avoided, could result in death or serious injury.
 CAUTION	Indicates a potentially hazardous situation which, if not avoided, may result in minor or moderate injury.
 NOTICE	Indicates a potentially hazardous situation which, if not avoided, could result in equipment damage, data loss, performance deterioration, or unanticipated results. NOTICE is used to address practices not related to personal injury.
 NOTE	Calls attention to important information, best practices and tips. NOTE is used to address information not related to personal injury, equipment damage, and environment deterioration.

Parent topic: [About This Document](#)

Change History

- [V100R023C00](#)
- [V100R022C00](#)
- [V600R019C00](#)
- [V600R006C10](#)
- [V200R001C80](#)
- [V200R001C60](#)

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V100R023C00

V600R019C00SPC630

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00SPC630

Compared with V600R019C00SPC591, V600R019C00SPC630 does not include any changes.

Parent topic: [V100R023C00](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V100R022C00

V600R019C00SPC590

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00SPC590

Compared with V600R019C00SPC580, V600R019C00SPC590 does not include any changes.

Parent topic: [V100R022C00](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00

- [V600R019C00SPC201](#)
- [V600R019C00SPC100](#)
- [V600R019C00](#)

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00SPC201

The following tables describe changes made in IPCC V600R019C00SPC201 compared with IPCC V600R019C00SPC200.

Table 1 New interface list

Interface Type	Interface
Real-time interface	Querying the Agent Status Change Reason in a Specified VDN

Parent topic: [V600R019C00](#)

V600R019C00SPC100

The following tables describe changes made in IPCC V600R019C00SPC200 compared with IPCC V600R019C00.

Table 1 List of new interfaces

Interface Type	Interface Name
Report interfaces	Downloading Voice Call CDRs of a VDN

Parent topic: [V600R019C00](#)

V600R019C00

No change is made in CloudIPCC V600R019C00 compared with CloudIPCC V600R006C10.

Parent topic: [V600R019C00](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R006C10

[V600R006C10SPC100](#)

[V600R006C10](#)

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R006C10SPC100

The following tables describe changes made in CloudIPCC V600R006C10SPC100 compared with CloudIPCC V600R006C10.

Table 1 List of new interfaces

Interface Type	Interface Name
Interfaces for authentication: auth	Authenticating Agents

Parent topic: [V600R006C10](#)

V600R006C10

The following tables describe changes made in CloudIPCC V600R006C10 compared with IPCC V200R001C80SPC700.

Index Changes

Table 1 List of new indexes

Index Type	Index ID	Index Description
Table 1	IDX_04_01_011	Indicates the reason for the rest or show-busy state.

Parent topic: [V600R006C10](#)

V200R001C80

[V200R001C80SPC700](#)

[V200R001C80SPC600](#)

[V200R001C80SPC500](#)

[V200R001C80SPC300](#)

[V200R001C80SPC200](#)

[V200R001C80SPC100](#)

[V200R001C80](#)

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC700

The following tables describe changes made in IPCC V200R001C80SPC700 compared with IPCC V200R001C80SPC600.

Index Changes

Table 1 List of new indexes

Index Type	Index ID	Index Description
Table 1	IDX_03_01_004	Indicates the maximum waiting time for queuing.

Parent topic: [V200R001C80](#)

V200R001C80SPC600

No change is made in IPCC V200R001C80SPC600 compared with IPCC V200R001C80SPC500.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC500

No change is made in IPCC V200R001C80SPC500 compared with IPCC V200R001C80SPC300.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC300

No change is made in IPCC V200R001C80SPC300 compared with IPCC V200R001C80SPC200.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC200

No change is made in IPCC V200R001C80SPC200 compared with IPCC V200R001C80SPC100.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC100

The following tables describe changes made in IPCC V200R001C80SPC100 compared with IPCC V200R001C80.

Interface Changes

Table 1 List of modified interfaces

Interface Type	Interface Name	Changes
Interfaces for synchronizing WAS configuration data	Synchronizing CTI Data	Request parameters wasIp , wasPort , wasPath , isSSL , workNo , and password are deleted (The interface compatibility with the original version of the interface).
	Synchronizing VDN Data	Request parameters wasIp , wasPort , wasPath , isSSL , workNo , and password are deleted (The interface compatibility with the original version of the interface).
	Testing CTI Synchronization	Request parameters wasIp , wasPort , wasPath , isSSL , workNo , and password are deleted (The interface compatibility with the original version of the interface).
	Testing VDN Synchronization	Request parameters wasIp , wasPort , wasPath , isSSL , workNo , and password are deleted (The interface compatibility with the original version of the interface).
Real-time interfaces	Interface for Bulk Querying the Agent Information	The return parameter inMultimediaConf is added.
	Querying the Information About All Agents of a Specified VDN	The return parameter inMultimediaConf is added.

Parent topic: [V200R001C80](#)

V200R001C80

No change is made in IPCC V200R001C80 compared with IPCC V200R001C60SPC100.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C60

V200R001C60SPC100

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C60SPC100

No change is made in IPCC V200R001C60SPC100 compared with IPCC V200R001C60.

Parent topic: [V200R001C60](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Interfaces

[Notices for Interface Use](#)

[Interfaces for authentication](#)

[Interfaces for Synchronizing the WAS Configuration Data](#)

[Interfaces for Querying Historical Indexes](#)

[Interfaces for Querying Real-Time Indexes](#)

[Real-Time Interfaces](#)

[Report interface](#)

[Interface for Managing Inspection User Groups](#)

Parent topic: [CMS Server Interface \(RESTful\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Notices for Interface Use

- All time returned by the interface is based on the Coordinated Universal Time (UTC).
- It is recommended that all the interfaces be invoked at an interval of 5s during periodic invocation.
- The interface parameters that you need to pass the skill queue ID, access code, VDNID, work ID, and agent group ID must be real.
- Users whose agent IDs range from 1 to 100 are system administrators, and users whose agent IDs range from 101 to 59999 are VDN users.
- Only VDN users who have the inspection monitoring rights can successfully invoke the authentication interface.

Permission Configuration			
Customized Permission			
☐ Busy-Indicating/Idle-Indicating	☐ Mute/Cancel Mute	☐ Hold Call/Cancel Held Call	☐ Connect Held Call
☐ Common Outgoing Call	☐ Internal Call	☐ Internal Transfer	☐ Answer Transferred Call
☐ Three-Party Conversation	☐ Transfer Out	☐ Transfer from Manual Station to Auto-Station	☐ Not Answer Incoming Call
☐ Monitor/Insert/Whisper	☐ Intercept	☐ Forcible Logout/Forcible Busy-Indicating/Forcible Idle-Indicating	☐ QC Inspection Recording/QC Inspection Voice Playing
☒ QC Inspection Monitoring	☐ Evaluate Administrator	☐ Ordinary Appraiser	☐ Alarm Console
☐ Report Handler	☐ Monitoring Console	☐ Config Admin	☐ Report Administrator
☐ National Outgoing Call	☐ International Outgoing Call	☐ Outgoing Call of Call Center Access Code	☐ Full-Screen QC Inspection
☐ Call Pick-Up by Agents in a Same Group	☐ Configure Agent	☐ Configure Skill Queue	☐ Non-External Calling Party
☐ Offline Playback	☐ Force Release Call	☐ Media Inspect	

Parent topic: [Interfaces](#)

Interfaces for authentication

Authenticating Agents

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Authenticating Agents

Interface Description

The CMS provides the inspection authentication interface. The interface needs to control the authority through the work ID to avoid unauthorized access to the tenant data.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/userauth/auth
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
Request Body			
agentId	string	Yes	Indicates the work ID of an agent.
password	string	Yes	Indicates the password of an agent.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	map	Indicates the return result of a successful query. For the parameter description of result , see the following table.

Table 3 Parameter description of result

Parameter	Data Type	Description
token	string	Indicates the sequence value generated after the user has logged in successfully, used for interface authentication.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/userauth/auth HTTP/1.1 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"agentId": "204", "password": "Huawei123"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"token":"5e36f8db-57b5-4f3d-89e9-e11a4c627e4b"}}</pre>

Error Code

- 300-002
- 300-006
- 300-007

- 300-011
- 300-014

Parent topic: [Interfaces for authentication](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Interfaces for Synchronizing the WAS Configuration Data

[Synchronizing CTI Data](#)

[Synchronizing VDN Data](#)

[Testing CTI Synchronization](#)

[Testing VDN Synchronization](#)

[Obtaining the Information of All VDNs](#)

[Obtaining the Agent Information of a Specified VDN](#)

[Obtaining the Agent Group Information of a Specified VDN](#)

[Obtaining the Resting Reason Information of a Specified VDN](#)

[Obtaining the Service Type Information of a Specified VDN](#)

[Obtaining the Skill Information of a Specified VDN](#)

[Obtaining the Skill Group Information of a Specified VDN](#)

[Obtaining the Called Configuration Information of a Specified VDN](#)

[Obtaining the Configuration Information Version](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Synchronizing CTI Data

Interface Description

The interface is used to obtain a list of all VDNs configured on the WAS and update the VDN information under **T_CMSGW_WAS_VDN**. If any VDN is deleted, the system deletes the agents, agent groups, resting reasons, service types, skills, skill groups, and called configuration information of this VDN after CTI synchronization. If any VDN is added, the system invokes the VDN synchronization interface to obtain the agents, agent groups, resting reasons, service types, skills, skill groups, and called configuration information of this VDN.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - The report script has been executed.
 - The VDN synchronization interface and CTI synchronization interface are not being invoked.
 - This interface can be invoked only when the user is a system administrator.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/synwas/syncti
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/synwas/syncti HTTP/1.1 Content-Type:application/json;charset=UTF-8 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Host: 192.168.0.0:9248 {"ccId": "1"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message": "", "retcode": "0"}</pre>

Error Code

- 000-002
- 100-001
- 100-006
- 100-007
- 300-008

- 300-009
- 300-010
- 300-013

Parent topic: [Interfaces for Synchronizing the WAS Configuration Data](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Synchronizing VDN Data

Interface Description

The interface is used to obtain the agents, agent groups, resting reasons, service types, skills, skill groups, and called configuration information of the corresponding VDN, the information of which is configured on the WAS.

Usage Description

1. Prerequisites

- The CMS Gateway is properly connected to the CCS.
- The report script has been executed.
- The CTI synchronization interface and current VDN synchronization interface are not being invoked.
- The system has invoked the CTI synchronization interface to obtain the information about the synchronized VDN.
- This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.

2. Precautions

None

3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/synwas/synvdm
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnId	int	No	Indicates the VDN ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/synwas/synvdm HTTP/1.1 Content-Type:application/json;charset=UTF-8 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Host: 192.168.0.0:9248 {"ccId":"1","vdnId":"1"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Error Code

- 000-002
- 100-001
- 100-006
- 100-007

- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Synchronizing the WAS Configuration Data](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Testing CTI Synchronization

Interface Description

The interface is used to test whether parameters are configured correctly after CTI synchronization.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/synwas/testcticonnect
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccId	int	No	Indicates the contact center ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/synwas/testcticonnect HTTP/1.1 Content-Type:application/json;charset=UTF-8 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Host: 192.168.0.0:9248 {"ccId": "1"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message": "", "retcode": "0"}</pre>

Error Code

- 000-002
- 100-001
- 300-008
- 300-009
- 300-010
- 300-013

Parent topic: [Interfaces for Synchronizing the WAS Configuration Data](#)

Testing VDN Synchronization

Interface Description

The interface is used to test whether parameters are configured correctly after VDN synchronization.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/synwas/testvsnconnect
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/synwas/testvsnconnect HTTP/1.1 Content-Type:application/json;charset=UTF-8 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Host: 192.168.0.0:9248 {"ccld":"1","vdnld":"1"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0"}</pre>

Error Code

- 000-002
- 100-001
- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Synchronizing the WAS Configuration Data](#)

Obtaining the Information of All VDNs

Interface Description

The interface is used to obtain the VDN information configured on the WAS after the successful CTI synchronization.

Usage Description

1. Prerequisites
 - CTI synchronization has been performed.
 - The database is connected properly.
 - This interface can be invoked only when the user is a system administrator.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/synwas/vdns
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
ccId	int	Indicates the contact center ID.
vdnId	int	Indicates the VDN ID.
vdnName	string	Indicates the VDN name.

Interface Example

Example Type	Reference Format
Example of a request packet	GET /cmsgateway/resource/synwas/vdns HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248
Example of a response packet	HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{ "ccId": "1", "vdnId": "2", "vdnName": "credit card", "ccId": "1", "vdnId": "1", "vdnName": "social cc" }] }

Error Code

- 300-008

- 300-009
- 300-013

Parent topic: [Interfaces for Synchronizing the WAS Configuration Data](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Obtaining the Agent Information of a Specified VDN

Interface Description

The interface is used to obtain the information about all agents of a specified VDN after the successful VDN synchronization.

Usage Description

1. Prerequisites
 - VDN synchronization has been performed.
 - The database is connected properly.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/synwas/agents/{ccld}/{vdnId}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
ccld	int	Yes	Indicates the contact center ID.
vdnId	int	Yes	Indicates the VDN ID.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
ccld	int	Indicates the contact center ID.
vdnId	int	Indicates the VDN ID.
agentNo	string	Indicates the work ID of an agent.
agentName	string	Indicates the name of an agent.
skillGroupId	string	Indicates a group of skill group IDs. Multiple skill group IDs are separated from each other using a semicolon (;). For example, 1;2 .
skillId	string	Indicates a group of skill IDs. Multiple skill IDs are separated from each other using a semicolon (;). For example, 1;3;10;11;25;31;32;40 .
groupId	string	Indicates the ID of an agent group.
roleId	string	Indicates a group of agent roles. Multiple agent roles are separated from each other using a semicolon (;). For example, 2;3 . For details about the agent role description, see Table 4 .

NOTE

The **roleId** parameter is customized for CMS Server, and it cannot be expanded. Therefore, this parameter shall be used with caution.

Table 4 Agent role description

Role ID	Role Name
2	Indicates the configuration administrator. This agent role is configured with the configuration administrator permission on the WAS.
3	Indicates the inspector. This agent role is configured with the monitoring console permission on the WAS.
4	Indicates the common agent. Other agents who do not play any of the preceding three agent roles are common agents.
5	Indicates the report administrator. This agent role is configured with the report administrator permission on the WAS.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /cmsgateway/resource/synwas/agents/1/1 HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result": [{"ccId":"1","vdnId":"1","agentNo":"10000","agentName":"10000","skillGroupId":null,"skillId":null,"groupId":null,"roleId":"2"}, {"ccId":"1","vdnId":"1","agentNo":"101","agentName":"","skillGroupId":null,"skillId":null,"groupId":null,"roleId":"2"}]}</pre>

Error Code

- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Synchronizing the WAS Configuration Data](#)

Obtaining the Agent Group Information of a Specified VDN

Interface Description

The interface is used to obtain the information about all agent groups of a specified VDN after the successful VDN synchronization.

Usage Description

1. Prerequisites
 - VDN synchronization has been performed.
 - The database is connected properly.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/synwas/groups/{ccld}/{vdnId}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
ccld	int	Yes	Indicates the contact center ID.
vdnId	int	Yes	Indicates the VDN ID.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
ccld	int	Indicates the contact center ID.
vdnId	int	Indicates the VDN ID.
groupId	string	Indicates the ID of an agent group.
groupName	string	Indicates the name of an agent group.
monitorId	string	Indicates the work ID of a supervisor.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /cmsgateway/resource/synwas/groups/1/1 HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{ "ccId": "1", "vdnId": "1", "groupId": "1", "groupName": "test", "monitorId": "117"}, { "ccId": "1", "vdnId": "1", "groupId": "10", "groupName": "agent group", "monitorId": "102"}] }

Error Code

- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Synchronizing the WAS Configuration Data](#)

Obtaining the Resting Reason Information of a Specified VDN

Interface Description

The interface is used to obtain the information about all resting reasons of a specified VDN after the successful VDN synchronization.

Usage Description

1. Prerequisites
 - VDN synchronization has been performed.
 - The database is connected properly.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/synwas/restreasons/{ccld}/{vdnId}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
ccld	int	Yes	Indicates the contact center ID.
vdnId	int	Yes	Indicates the VDN ID.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
ccld	int	Indicates the contact center ID.
vdnId	int	Indicates the VDN ID.
reasonCode	string	Indicates the code of a resting reason.
reasonInfo	string	Indicates the description of the resting reason.

Interface Example

Example Type	Reference Format
Example of a request packet	GET /cmsgateway/resource/synwas/restreasons/1/1 HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248
Example of a response packet	HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{"ccId": "1", "vdnId": "1", "reasonCode": "5", "reasonInfo": "123456789"}] }

Error Code

- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Synchronizing the WAS Configuration Data](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Obtaining the Service Type Information of a Specified VDN

Interface Description

The interface is used to obtain the information about all service types of a specified VDN after the successful VDN synchronization.

Usage Description

1. Prerequisites
 - VDN synchronization has been performed.
 - The database is connected properly.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/synwas/servertypes/{ccld}/{vdnId}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
ccld	int	Yes	Indicates the contact center ID.
vdnId	int	Yes	Indicates the VDN ID.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
ccld	int	Indicates the contact center ID.
vdnId	int	Indicates the VDN ID.
serviceId	string	Indicates the ID of a service type.
serviceName	string	Indicates the name of the service type.

Interface Example

Example Type	Reference Format
Example of a request packet	GET /cmsgateway/resource/synwas/servertypes/1/1 HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248
Example of a response packet	HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8

Example Type	Reference Format
	<pre>{ "message": "", "retcode": "0", "result": [{ "ccId": "1", "vdnId": "1", "serviceId": "1", "serviceName": "Text chat" }, { "ccId": "1", "vdnId": "1", "serviceId": "9", "serviceName": "SMS" }] }</pre>

Error Code

- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Synchronizing the WAS Configuration Data](#)

Obtaining the Skill Information of a Specified VDN

Interface Description

The interface is used to obtain the information about all skills of a specified VDN after the successful VDN synchronization.

Usage Description

1. Prerequisites
 - VDN synchronization has been performed.
 - The database is connected properly.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/synwas/skills/{ccld}/{vdnId}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
ccld	int	Yes	Indicates the contact center ID.
vdnId	int	Yes	Indicates the VDN ID.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of **result**

Parameter	Data Type	Description
ccld	int	Indicates the contact center ID.
vdnId	int	Indicates the VDN ID.
skillId	string	Indicates the ID of a skill.
skillName	string	Indicates the name of a skill.
realFlag	string	Indicates whether it is in a real queue. The options are as follows: 1 : real queue 0 : virtual queue
serverId	string	Indicates the ID of a service type.
mediaType	string	Indicates the media type. For details about mediaType , see Media Types .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /cmsgateway/resource/synwas/skills/1/1 HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":0,"result":[{"ccId":1,"vdnId":1,"skillId":1,"skillName":"Text chat","realFlag":1,"serverId":1,"mediaType":1}, {"ccId":1,"vdnId":1,"skillId":10,"skillName":"Text chat 2","realFlag":1,"serverId":1,"mediaType":1}]}</pre>

Error Code

- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Synchronizing the WAS Configuration Data](#)

Obtaining the Skill Group Information of a Specified VDN

Interface Description

The interface is used to obtain the information about all skill groups of a specified VDN after the successful VDN synchronization.

Usage Description

1. Prerequisites
 - VDN synchronization has been performed.
 - The database is connected properly.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/synwas/skillgroups/{ccld}/{vdnId}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
ccld	int	Yes	Indicates the contact center ID.
vdnId	int	Yes	Indicates the VDN ID.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
ccld	int	Indicates the contact center ID.
vdnId	int	Indicates the VDN ID.
skillGroupId	string	Indicates the ID of a skill group.
skillGroupName	string	Indicates the name of the skill group.
skillIds	string	Indicates a group of skill IDs. Multiple skill IDs are separated from each other using a semicolon (;). For example, 1;2;3;4 .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /cmsgateway/resource/synwas/skillgroups/1/1 HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{"ccId": "1", "vdnId": "1", "skillGroupId": "1", "skillGroupName": "232323", "skillIds": "1;2;3;4"}] }

Error Code

- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Synchronizing the WAS Configuration Data](#)

Obtaining the Called Configuration Information of a Specified VDN

Interface Description

The interface is used to obtain the information about all called configuration of a specified VDN after the successful VDN synchronization.

Usage Description

1. Prerequisites
 - VDN synchronization has been performed.
 - The database is connected properly.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/synwas/calledconfigs/{ccld}/{vdnId}
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
ccld	int	Yes	Indicates the contact center ID.
vdnId	int	Yes	Indicates the VDN ID.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
ccld	int	Indicates the contact center ID.
vdnId	int	Indicates the VDN ID.
accessCode	string	Indicates the access code.
subCode	string	Indicates the subsequent access code.
deviceType	string	Indicates the device type. For details about deviceType , see Device Types .
deviceName	string	Indicates the device name.
deviceNo	string	Indicates the device ID.
clientLevel	string	Indicates the customer level.

Interface Example

Example Type	Reference Format
Example of a request packet	<code>GET /cmsgateway/resource/synwas/calledconfigs/1/1 HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248</code>
Example of a response packet	<code>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{"ccId": "1", "vdnId": "1", "accessCode": "6045", "subCode": null, "deviceType": "1", "deviceName": "Skill", "deviceNo": "22", "clientLevel": "1"}]}</code>

Error Code

- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Synchronizing the WAS Configuration Data](#)

Obtaining the Configuration Information Version

Interface Description

The interface is used to obtain the current versions of the CTI and VDN configuration information after CTI synchronization or VDN synchronization.

Usage Description

1. Prerequisites
 - CTI synchronization or VDN synchronization has been performed.
 - The database is connected properly.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/synwas/versions
Request Method	GET

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	No	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of **result**

Parameter	Data Type	Description
vdnsVersion	array	Indicates the version of the VDN configuration information. For the parameter description of vdnsVersion , see Table 4 .
ccId	int	Indicates the contact center ID.
version	int	Indicates the version of the CTI configuration information.
startTime	string	Indicates the start time of the CTI synchronization.
endTime	string	Indicates the end time of the CTI synchronization.
status	string	Indicates the synchronization status. For details about status , see WAS Synchronization Status .
clusterId	string	Indicates the cluster ID of the CMS Gateway that performs the synchronization task.
clusterName	string	Indicates the cluster name of the CMS Gateway that performs the synchronization task.

Table 4 Parameter description of **vdnsVersion**

Parameter	Data Type	Description
vdnId	int	Indicates the VDN ID.

Parameter	Data Type	Description
version	int	Indicates the version of the VDN configuration information.
startTime	string	Indicates the start time of the VDN synchronization.
endTime	string	Indicates the end time of the VDN synchronization.
status	string	Indicates the synchronization status. For details about status , see WAS Synchronization Status .
clusterId	string	Indicates the cluster ID of the CMS Gateway that performs the synchronization task.
clusterName	string	Indicates the cluster name of the CMS Gateway that performs the synchronization task.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>GET /cmsgateway/resource/synwas/versions HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"vdnsVersion": [{"vdnId":"2","version":1,"startTime":1453107495000,"endTime":1453107495000,"status":2,"clusterId":"f606ac62-58f8-4ca3-8ae5- 2744d079821b","clusterName":"cmsgateway"}, {"vdnId":"1","version":13,"startTime":1453448925000,"endTime":1453448927000,"status":2,"clusterId":"2552f1d7-016c-4c48-bd2b- 389af268c834","clusterName":"cmsgateway"}], "ccId":"1","version":6,"startTime":1453448054000,"endTime":1453448054000,"status":2,"clusterId":"2552f1d7-016c-4c48-bd2b- 389af268c834","clusterName":"cmsgateway"}}</pre>

Error Code

- 300-008
- 300-009
- 300-013

Parent topic: [Interfaces for Synchronizing the WAS Configuration Data](#)

Interfaces for Querying Historical Indexes

[Obtaining Monitoring Indexes About Agents](#)

[Obtaining Monitoring Indexes About Skills](#)

[Obtaining Monitoring Indexes About IVR Flows](#)

[Obtaining Monitoring Indexes About VDNs](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Obtaining Monitoring Indexes About Agents

Interface Description

The interface is used to obtain historical monitoring indexes about agents.

Usage Description

1. Prerequisites
 - The report script has been executed.
 - CDRs are imported to the database properly.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - This interface cannot be used for the public cloud.

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/hindex/agent
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
objectlds	array	Yes	Indicates an array of agent work IDs. The array contains a maximum of 20000 IDs. Each work ID is an integer.
indexlds	array	Yes	Indicates an array of indexes. Each index value is a string. The maximum number of indexes in the array is the number of historical monitoring indexes about agents. For details, see Agent .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of **result**

Parameter	Data Type	Description
id	int	Indicates the work ID of an agent.
idxs	array	Indicates a group of indexes. For the parameter description of idxs , see Table 4 .

Table 4 Parameter description of **idxs**

Parameter	Data Type	Description
id	int	Indicates the ID of an index.
val	Object	Indicates the value of the index. For details, see Agent .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/hindex/agent HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":"1","vdnId":"1","objectIds":[291,292],"indexIds":["IDX_04_02_001","IDX_04_04_001"]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"id":"291","idxs":{"id":"IDX_04_02_001","val":"1"}, {"id":"IDX_04_04_001","val":"3"}]},{"id":"292","idxs":{"id":"IDX_04_02_001","val":null}, {"id":"IDX_04_04_001","val":null}}]}</pre>

Error Code

- 000-002
- 200-001
- 200-002
- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Querying Historical Indexes](#)

Obtaining Monitoring Indexes About Skills

Interface Description

The interface is used to obtain historical monitoring indexes about skills.

Usage Description

1. Prerequisites
 - The report script has been executed.
 - CDRs are imported to the database properly.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - This interface cannot be used for the public cloud.

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/hindex/skill
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
objectlds	array	Yes	Indicates an array of skill queue IDs. The array contains a maximum of 2000 IDs. Each skill queue ID is an integer.
indexlds	array	Yes	Indicates an array of indexes. Each index value is a string. The maximum number of indexes in the array is the number of historical monitoring indexes about skills. For details, see Skill .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
id	int	Indicates the ID of a skill queue.
idxs	array	Indicates a group of indexes. For the parameter description of idxs , see Table 4 .

Table 4 Parameter description of idxs

Parameter	Data Type	Description
id	int	Indicates the ID of an index.
val	Object	Indicates the value of the index. For details, see Skill .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/hindex/skill HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":"1","vdnId":"1","objectIds":[11,24],"indexIds":["IDX_03_04_001","IDX_03_10_001"]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"id":"11","idxs":[{"id":"IDX_03_04_001","val":"3"},{"id":"IDX_03_10_001","val":{"2016-01-25 07:00:00":"1","2016-01-25 01:45:00":"2"}}]},{"id":"24","idxs":[{"id":"IDX_03_04_001","val":null}, {"id":"IDX_03_10_001","val":null}]}]}</pre>

Error Code

- 000-002
- 200-001
- 200-002
- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Querying Historical Indexes](#)

Obtaining Monitoring Indexes About IVR Flows

Interface Description

The interface is used to obtain historical monitoring indexes about IVR flows.

Usage Description

1. Prerequisites
 - The report script has been executed.
 - CDRs are imported to the database properly.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - This interface cannot be used for the public cloud.

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/hindex/ivr
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
objectlds	array	Yes	Indicates an array of service type IDs. The array contains a maximum of 500 IDs. Each service type ID is an integer.
indexlds	array	Yes	Indicates an array of indexes. Each index value is a string. The maximum number of indexes in the array is the number of historical monitoring indexes about IVR flows. For details, see IVR .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
id	int	Indicates the ID of a service type.
idxs	array	Indicates a group of indexes. For the parameter description of idxs , see Table 4 .

Table 4 Parameter description of idxs

Parameter	Data Type	Description
id	int	Indicates the ID of an index.
val	Object	Indicates the value of the index. For details, see IVR .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/hindex/ivr HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":"1","vdnId":"1","objectIds":[2, 3],"indexIds":["IDX_02_02_001","IDX_02_05_001"]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"id":"2","idxs":{"id":"IDX_02_02_001","val":"1"}, {"id":"IDX_02_05_001","val":{"2016-01-25 01:00:00":"1"}}]}, {"id":"3","idxs":{"id":"IDX_02_02_001","val":null}, {"id":"IDX_02_05_001","val":null}}]}</pre>

Error Code

- 000-002
- 200-001
- 200-002
- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Querying Historical Indexes](#)

Obtaining Monitoring Indexes About VDNs

Interface Description

The interface is used to obtain historical monitoring indexes about VDNs.

Usage Description

- Prerequisites
 - The report script has been executed.
 - CDRs are imported to the database properly.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
- Precautions
 - None
- Use restrictions
 - This interface cannot be used for the public cloud.

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/hindex/vdn
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccId	int	Yes	Indicates the contact center ID.
vdnId	int	No	Indicates the VDN ID.
objectIds	array	Yes	Indicates an array of VDN IDs. The array contains a maximum of 100 IDs. Each VDN ID must be an integer.
indexIds	array	Yes	Indicates an array of indexes. Each index value is a string. The maximum number of indexes in the array is the number of historical monitoring indexes about VDNs. For details, see VDN .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
id	int	Indicates the VDN ID.
idxs	array	Indicates a group of indexes. For the parameter description of idxs , see Table 4 .

Table 4 Parameter description of idxs

Parameter	Data Type	Description
id	int	Indicates the ID of an index.
val	Object	Indicates the value of the index. For details, see VDN .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/hindex/vdn HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":"1","objectIds":[1,2],"indexIds":["IDX_01_01_001","IDX_01_02_001"]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"id":"1","idxs":{"id":"IDX_01_01_001","val":{"2016-01-25 01:45:00":"3"}}, {"id":"IDX_01_02_001","val":"3"}]}, {"id":"2","idxs":{"id":"IDX_01_01_001","val":null}, {"id":"IDX_01_02_001","val":null}}]}</pre>

Error Code

- 000-002
- 200-002
- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Querying Historical Indexes](#)

Interfaces for Querying Real-Time Indexes

[Obtaining Monitoring Indexes About Agents](#)

[Obtaining Monitoring Indexes About Skills](#)

[Interface for Obtaining Monitoring Indexes About VDNs](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Obtaining Monitoring Indexes About Agents

Interface Description

The interface is used to obtain real-time monitoring indexes about agents.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/rindex/agent
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
objectlds	array	Yes	Indicates an array of agent work IDs. The array contains a maximum of 20000 IDs. Each work ID is an integer.
indexlds	array	Yes	Indicates an array of indexes. Each index value is a string. The maximum number of indexes in the array is the number of real-time monitoring indexes about agents. For details, see Agent .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
id	int	Indicates the work ID of an agent.
idxs	array	Indicates a group of indexes. For the parameter description of idxs , see Table 4 .

Table 4 Parameter description of idxs

Parameter	Data Type	Description
id	int	Indicates the ID of an index.
val	Object	Indicates the value of the index. For details, see Agent .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/rindex/agent HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":"1","vdnId":"1","objectIds":[291,292],"indexIds":["IDX_04_01_003","IDX_04_01_007"]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"id":"291","idxs":{"id":"IDX_04_01_003","val":"40101"},{"id":"IDX_04_01_007","val":"1"}]},{id:"292","idxs":{"id":"IDX_04_01_003","val":null},{id":"IDX_04_01_007","val":"0"}}]}</pre>

Error Code

- 000-002
- 200-001
- 200-002
- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Querying Real-Time Indexes](#)

Obtaining Monitoring Indexes About Skills

Interface Description

The interface is used to obtain real-time monitoring indexes about skills.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/rindex/skill
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnId	int	No	Indicates the VDN ID. The default value is 0 .
objectIds	array	Yes	Indicates an array of skill queue IDs. The array contains a maximum of 2000 IDs. Each skill queue ID is an integer.
indexIds	array	Yes	Indicates an array of indexes. Each index value is a string. The maximum number of indexes in the array is the number of real-time monitoring indexes about skills. For details, see Skill .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
id	int	Indicates the ID of a skill queue.
idxs	array	Indicates a group of indexes. For the parameter description of idxs , see Table 4 .

Table 4 Parameter description of idxs

Parameter	Data Type	Description
id	int	Indicates the ID of an index.
val	Object	Indicates the value of the index. For details, see Skill .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/rindex/skill HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":"1","vdnId":"1","objectIds":[25,24],"indexIds":["IDX_03_01_002","IDX_03_02_001"]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"id":"25","idxs":[{"id":"IDX_03_01_002","val":"0"}, {"id":"IDX_03_02_001","val":"1"}]}, {"id":"24","idxs":[{"id":"IDX_03_01_002","val":"0"}, {"id":"IDX_03_02_001","val":"0"}]}]}</pre>

Error Code

- 000-002
- 200-001
- 200-002
- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Querying Real-Time Indexes](#)

Interface for Obtaining Monitoring Indexes About VDNs

Interface Description

The interface is used to obtain real-time monitoring indexes about VDNs.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/rindex/vdn
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	Yes	Indicates the contact center ID.
vdnId	int	No	Indicates the VDN ID.
objectIds	array	Yes	Indicates an array of VDN IDs. The array contains a maximum of 100 IDs. Each VDN ID must be an integer.
indexIds	array	Yes	Indicates an array of indexes. Each index value is a string. The maximum number of indexes in the array is the number of real-time monitoring indexes about VDNs. For details, see VDN .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
id	int	Indicates the VDN ID.
idxs	array	Indicates a group of indexes. For the parameter description of idxs , see Table 4 .

Table 4 Parameter description of idxs

Parameter	Data Type	Description
id	int	Indicates the ID of an index.
val	Object	Indicates the value of the index. For details, see VDN .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/rindex/vdn HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":"1","vdnId":"1","objectIds":[1,2],"indexIds":["IDX_01_04_001","IDX_01_04_005"]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"id":"1","idxs":[{"id":"IDX_01_04_001","val":"0"}, {"id":"IDX_01_04_005","val":"2"}]},{"id":"2","idxs":[{"id":"IDX_01_04_001","val":"0"}, {"id":"IDX_01_04_005","val":"0"}]}</pre>

Error Code

- 000-002
- 200-001
- 200-002
- 300-008
- 300-009
- 300-010

Parent topic: [Interfaces for Querying Real-Time Indexes](#)

Real-Time Interfaces

[Querying the Call Information of Specified Access Codes](#)
[Querying the System Access Code Information of a Specified VDN](#)
[Querying the Agent Resting Condition of a Specified VDN](#)
[Bulk Querying the Agents Who Have Signed In to the Specified Skill Queues](#)
[Bulk Querying the Skill Queues to Which the Specified Agents Have Signed In](#)
[Interface for Bulk Querying the Agent Information](#)
[Querying Agent Phone Numbers of a Specified VDN](#)
[Querying the Current Call Information of a Specified Agent](#)
[Querying the Information About All Agents of a Specified VDN](#)
[Querying the Current State Information About All Agents of a Specified VDN](#)
[Querying the Static Configuration Information About All Agents of a Specified VDN](#)
[Bulk Querying the Call Information of Agents](#)
[Querying Private Calls of the Specified Agent](#)
[Querying the Basic Call Information of a Specified Call ID](#)
[Querying the Detailed Call Information of a Specified Call ID](#)
[Querying the Detailed Status Information About the IVR Flow of a Specified VDN](#)
[Querying the Access Code Information About the IVR Flow of a Specified VDN](#)
[Bulk Querying the Extended Information of Skill Queues](#)
[Bulk Querying the Call Statistics of Skill Queues in the Last Five Minutes](#)
[Querying the Status Information of a Specified Skill Queue](#)
[Bulk Querying the Configuration Information of Skill Queues](#)
[Bulk Querying the Detailed Statistics of Skill Queues](#)
[Querying the Information About All Skill Queues of a Specified VD](#)
[Bulk Querying All Queuing Calls in Skill Queues](#)
[Bulk Querying the Number of Calls that a Skill Queue Picks Up from Other Skill Queues in the Case that Multiple Skill Queues Have Waiting Calls](#)
[Querying the Service Type Information of a Specified VDN](#)
[Querying the Server Time of the CTI Platform](#)
[Querying the Current License Usage Condition of the System](#)
[Querying the Current License Usage Condition of a Specified VDN](#)
[Querying the Agent Resting Reason Codes of a Specified VDN](#)
[Querying All VDNs in a Specified Call Center](#)
[Querying the Number of Agents in Different States in Agent Groups](#)
[Querying the Number of Agents in Different States in Skill Queues](#)
[Querying the Agent Status Change Reason in a Specified VDN](#)

Parent topic: [Interfaces](#)

Querying the Call Information of Specified Access Codes

Interface Description

The interface is used to query the call information of specified access codes.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/accesscode/callstatbyinno
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
innolds	array	Yes	Indicates an array of access code IDs. The array contains a maximum of 500 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
innold	int	Indicates the ID of an access code.
allCallCount	long	Indicates the number of online customers using the access code.
ivrCallCount	long	Indicates the number of online customers using the access code for IVR flows.
agentCallCount	long	Indicates the number of online customers using the access code for agents.
queueCallCount	long	Indicates the number of online customers using the access code for skill queues.
longestWaitTime	long	Indicates the longest call waiting time of the access code.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /msgateway/resource/real/accesscode/callstatbyinno HTTP/1.1 msgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1,"innoIds":[40]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result": [{"innoId":40,"allCallCount":1,"ivrCallCount":0,"agentCallCount":1,"queueCallCount":0,"longestWaitTime":0}]}</pre>

Error Code

- 000-002
- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Querying the System Access Code Information of a Specified VDN

Interface Description

The interface is used to query the system access code information of a specified VDN.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/accesscode/totalinnoinfo
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
mediaType	int	Indicates the media type. For details, see Media Types .
id	int	Indicates the ID of an access code.
inno	string	Indicates the value of the access code.
description	string	Indicates the description of an access code.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/accesscode/totalinnoinfo HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8</pre>

Example Type	Reference Format
	<pre>{'message':"", 'retcode': "0", 'result': [{ 'mediaType': 1, 'id': 10, 'inno': "1008", 'description': "1008"}, {'mediaType': 1, 'id': 9, 'inno': "1007", 'description': "1007"}]}</pre>

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Querying the Agent Resting Condition of a Specified VDN

Interface Description

The interface is used to query the agent resting condition of a specified VDN.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/agent/agentrestdetailinfo
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
onRestAgentNum	int	Indicates the number of resting agents.
allowRestAgentNum	int	Indicates the number of agents who are allowed to rest but still do not rest.
waitRestAgentNum	int	Indicates the number of agents who are waiting to rest.
details	array	Indicates an array of the detailed information about resting agents or agents who apply for resting. For the parameter description of details , see Table 4 .

Table 4 Parameter description of details

Parameter	Data Type	Description
agentId	int	Indicates the work ID of an agent.
cantRestCause	int	Indicates the reason why an agent is not allowed to rest. This parameter is valid only for agents who are waiting to rest. For the parameter description of cantRestCause , see Table 5 .

Parameter	Data Type	Description
skillId	int	Indicates the ID of a skill queue in which the number of resting agents has reached the upper limit. If the number of resting agents has not reached the upper limit in a skill queue, the value is set to 65535 .
beginTime	string	Indicates the start time. For a resting agent, it refers to the time when the agent starts to rest. For an agent who applies for resting or is allowed to rest, it refers to the time when the agent applies for resting.
reqRestDura	long	Indicates the resting duration.
name	string	Indicates the name of an agent.

Table 5 Reasons that agents are not allowed to rest

Cause Value	Description
0	The agent is waiting for an approval of its resting application.
1	The agent is in the busy state.
2	The number of resting agents under the VDN has reached the upper limit.
3	The agent does not receive any incoming call and has not signed in to any skill queue.
4	The number of resting agents, who sign in to the skill queue, has reached the upper limit.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/agent/agentrestdetailinfo HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":0,"result":{"onRestAgentNum":1,"allowRestAgentNum":0,"waitRestAgentNum":0,"details":[{"agentId":291,"cantRestCause":5,"skillId":65535,"beginTime":1453710031000,"reqRestDura":720,"name":"291"}]}}</pre>

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Bulk Querying the Agents Who Have Signed In to the Specified Skill Queues

Interface Description

The interface is used to bulk query the agents who have signed in to the specified skill queues.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/agent/agentsinskill
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
skilllds	array	Yes	Indicates an array of skill queue IDs. The array contains a maximum of 1000 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
skillId	int	Indicates the ID of a skill queue.
agentIds	array	Indicates an array of work IDs corresponding to agents who have signed in to the skill queue.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/agent/agentsinskill HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1,"skillIds":[1,2]}</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{ "skillId": 1, "agentIds": {291}}, { "skillId": 2, "agentIds": {}] }}

Error Code

- 000-002
- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Bulk Querying the Skill Queues to Which the Specified Agents Have Signed In

Interface Description

The interface is used to bulk query the skill queues to which the specified agents have signed in.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/agent/agentsloginskills
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
agentlds	array	Yes	Indicates an array of agent work IDs. The array contains a maximum of 20000 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
agentld	int	Indicates the work ID of an agent.
skills	array	Indicates an array of skill queues to which the agent has signed in. For the parameter description of skills , see Table 4 .

Table 4 Parameter description of skills

Parameter	Data Type	Description
skillld	int	Indicates the ID of a skill queue.
isLogin	int	Indicates whether the agent has signed in to the skill queue. The options are as follows: 1 : Yes 0 : No

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/agent/agentsloginskills HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1,"agentIds":[291,101]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"agentId":291,"skills":[{"skillId":1,"isLogin":1}, {"skillId":3,"isLogin":1}, {"skillId":10,"isLogin":1}, {"skillId":11,"isLogin":1}, {"skillId":25,"isLogin":1}, {"skillId":31,"isLogin":1}, {"skillId":32,"isLogin":1}, {"skillId":40,"isLogin":1}]}], {"agentId":101,"skills":{}}]}</pre>

Error Code

- 000-002
- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Interface for Bulk Querying the Agent Information

Interface Description

The interface is used to bulk query the agent information.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/agent/agentstatusex3
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
agentlds	array	Yes	Indicates an array of agent work IDs. The array contains a maximum of 20000 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
agentId	int	Indicates the work ID of an agent.
locationId	int	Indicates the distributed access node of the agent.
currentStateReason	int	Indicates the reason of the current state. Currently, this parameter is valid only if the agent is in the resting state.
prevState	int	Indicates the last state.
prevStateTime	long	Indicates the duration of the last state.
currentState	int	Indicates the current state. For details, see Agent Status .
currentStateTime	long	Indicates the duration of the current state.
logonTime	long	Indicates the time when the agent signs in to the system.

Parameter	Data Type	Description
agentRelease	int	Indicates the number of times that the agent actively hangs up.
currentPrivateCallNum	int	Indicates the number of private calls of the agent.
inMultimediaConf	int	Indicates whether an agent is in a multimedia conference. 0 : no 1 : yes

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/agent/agentstatusex3 HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ceId":1,"vdnId":1,"agentIds":[291,101]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"agentId":291,"locationId":65535,"currentStateReason":5,"prevState":1,"prevStateTime":13,"currentState":8,"currentStateTime":2835,"logonTime":1453705395000,"agentRelease":1,"currentPrivateCallNum":0,"inMultimediaConf":0}, {"agentId":292,"locationId":65535,"currentStateReason":258,"prevState":255,"prevStateTime":4294967295,"currentState":0,"currentStateTime":259189,"logonTime":4294967295000,"agentRelease":0,"currentPrivateCallNum":0,"inMultimediaConf":0}]}</pre>

Error Code

- 000-002
- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Querying Agent Phone Numbers of a Specified VDN

Interface Description

The interface is used to query the phone numbers of agents who have signed in under a Specified VDN.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/agent/allagentphones
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnId	int	No	Indicates the VDN ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
agentId	int	Indicates the work ID of an agent.
phone	string	Indicates the phone number that the agent uses to sign in.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/agent/allagentphones HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"agentId":201,"phone":"59001"}, {"agentId":291,"phone":"40101"}, {"agentId":330,"phone":"59002"}]}</pre>

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying the Current Call Information of a Specified Agent

Interface Description

The interface is used to query the current call information of a specified agent.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/agent/callidonagent
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
agentld	int	No	Indicates the work ID of an agent. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. The return result indicates an array of call IDs corresponding to the calls that the agent is processing at present.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/agent/callidonagent HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccld":1,"vdnld":1,"agentld":291}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":["1453717570-564"]}</pre>

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Querying the Information About All Agents of a Specified VDN

Interface Description

The interface is used to query the information about all agents of a specified VDN, including the agents who are on hold.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/agent/totalagentabstractex3
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
agentId	int	Indicates the work ID of an agent.
workGroupld	int	Indicates the ID of an agent group.
record	int	Indicates whether the agent is recorded. The options are as follows: 0 : No 1 : Yes
supers	int	Indicates whether the agent is intercepted. The options are as follows: 0 : No 1 : Yes
monitor	int	Indicates whether the agent is monitored. The options are as follows: 0 : No 1 : Yes
status	int	Indicates the operating status of the agent. For details, see Operating Status of Agents .
agentStatusTime	long	Indicates the duration of the operating status of the agent.

Parameter	Data Type	Description
currentState	int	Indicates the current state of the agent. For details, see Agent Status .
currentStateTime	int	Indicates the duration of the current state.
locationId	int	Indicates the distributed access node of the agent.
currentPrivateCallNum	int	Indicates the number of private calls of the agent.
inMultimediaConf	int	Indicates whether an agent is in a multimedia conference. 0 : no 1 : yes

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/agent/totalagentabstractex3 HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":0,"result": [{"agentId":10000,"workGroupId":0,"record":0,"supers":0,"monitor":0,"status":0,"agentStatusTime":2762350,"currentState":0,"currentStateTime":2762288,"locationId":65535, "currentPrivateCallNum":0,"inMultimediaConf":0}, {"agentId":101,"workGroupId":0,"record":0,"supers":0,"monitor":0,"status":0,"agentStatusTime":2762350,"currentState":0,"currentStateTime":2762288,"locationId":65535, "currentPrivateCallNum":0,"inMultimediaConf":0}]}</pre>

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Querying the Current State Information About All Agents of a Specified VDN

Interface Description

The interface is used to query the current state information about all agents of a specified VDN.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/agent/totalagentdynamicinfo
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
agentId	int	Indicates the work ID of an agent.
state	int	Indicates the current state of the agent. For details, see Agent Status .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/agent/totalagentdynamicinfo HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"agentId":10000,"state":0},{"agentId":101,"state":0}]}</pre>

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying the Static Configuration Information About All Agents of a Specified VDN

Interface Description

The interface is used to query the static configuration information about all agents of a specified VDN.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/agent/totalagentinfo
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
agentId	int	Indicates the work ID of an agent.
groupId	int	Indicates the ID of an agent group.
rights	string	Indicates whether the agent has a permission. The options are as follows: 0 : no; 1 : yes For details, see Agent Permission Values .
realFlag	int	Indicates whether the agent is a network agent. The options are as follows: 0 : Network agent 1 : Common agent
privateQueueMode	int	Indicates the private queue mode of the agent. The options are as follows: 0 : The agent has no private queue. 1 : The agent uses default private queues. 2 : The agent has its own private queues.
name	string	Indicates the name of the agent.

Interface Example

Bulk Querying the Call Information of Agents

Interface Description

The interface is used to bulk query the call information of agents. The information includes the call status (on hold, mute, and third-party call), call type (incoming call and outgoing call), and call media (voice, fax, email, and WeChat).

Usage Description

- Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
- Precautions
 - None
- Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/agent/agentcalls
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnId	int	No	Indicates the VDN ID. The default value is 0 .
agentIds	array	Yes	Indicates an array of agent work IDs. The array contains a maximum of 20000 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
agentId	int	Indicates the work ID of an agent.
callList	object	Indicates an array of call information. For the parameter description of callList , see Table 4 .

Table 4 Parameter description of callList

Parameter	Data Type	Description
callId	string	Indicates the ID of a call.
callStatus	int	Indicates the call status.
callInOut	int	Indicates whether the call is an incoming or outgoing call. The options are as follows: 0 : Incoming call 1 : Outgoing call

Parameter	Data Type	Description
mediaType	int	Indicates the media type. For details, see Media Types .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /msggateway/resource/real/agent/agentcalls HTTP/1.1 msggateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1,"agentIds":[102,201,101]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result": [{"agentId":102,"callList":[]},{ "agentId":201,"callList":[{"callId":"1453721604-566", "callStatus":5,"callInOut":0,"mediaType":5}],{"agentId":101,"callList":[]}]}</pre>

Error Code

- 000-002
- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Querying Private Calls of the Specified Agent

Interface Description

The interface is used to query private calls of the specified agents.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/agent/agentprivatecall
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
agentld	int	No	Indicates the work ID of an agent. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates an array of call IDs.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/agent/agentprivatecall HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1,"agentId":291}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":["1453721604-566"]}</pre>

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Querying the Basic Call Information of a Specified Call ID

Interface Description

The interface is used to query the basic call information of a specified call ID.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/call/basecallinfo
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
callld	string	Yes	Indicates the call ID. The maximum value length is 24 characters.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callingNum	string	Indicates the calling number.
calledNum	string	Indicates the called number.
mid	int	Indicates the universal access platform (UAP) module ID.
trunkNo	int	Indicates the trunk number.
priority	int	Indicates the user priority.
deviceType	int	Indicates the type of the device that is processing the call. For details, see Device Types .
deviceNo	int	Indicates the ID of the device that is processing the call.
callSkill	int	Indicates the description of the skill queue.
partyNum	int	Indicates the number of devices that the call track passes by.

Parameter	Data Type	Description
callFeature	int	Indicates the call feature. For details, see Call Features .
orgiCalledNum	int	Indicates the original called number.
mediaType	int	Indicates the media type. For details, see Media Types .
waitTime	int	Indicates the waiting time in queues.
totalTalkingTimes	int	Indicates the call duration.
logonTimes	int	Indicates the total duration that the call accesses the device.
serviceType	int	Indicates the service type.
callInCause	int	Indicates the cause of the incoming call.
enterReason	int	Indicates the reason that the call accesses the device.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /msggateway/resource/real/call/basecallinfo HTTP/1.1 msggateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1,"callId":"1453723531-574"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"callingNum":"10086","calledNum":"40103","mid":40,"trunkNo":103,"priority":0,"deviceType":2,"deviceNo":291,"callSkill":"Voice_jinsita o","partyNum":1,"callFeature":7,"orgiCalledNum":""," "mediaType":5,"waitTime":0,"totalTalkingTimes":19,"logonTimes":20,"serviceType":2,"callInCause":65535,"enterReason":0}}</pre>

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Querying the Detailed Call Information of a Specified Call ID

Interface Description

The interface is used to query the detailed call information of a specified call ID.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/call/callinfo
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
callld	string	Yes	Indicates the call ID. The maximum value length is 24 characters.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callingNum	string	Indicates the calling number.
calledNum	string	Indicates the called number.
mid	int	Indicates the UAP module ID.
trunkNo	int	Indicates the trunk number.
priority	int	Indicates the user priority.
deviceType	int	Indicates the type of the device that is processing the call. For details, see Device Types .
deviceNo	int	Indicates the ID of the device that is processing the call.
callData	string	Indicates the call-associated data.
callSkill	int	Indicates the description of the skill queue.

Parameter	Data Type	Description
partyNum	int	Indicates the number of devices that the call track passes by.
callFeature	int	Indicates the call feature. For details, see Call Features .
orgiCalledNum	int	Indicates the original called number.
mediaType	int	Indicates the media type. For details, see Media Types .
waitTime	int	Indicates the waiting time in queues.
totalTalkingTimes	int	Indicates the call duration.
logonTimes	int	Indicates the total duration that the call accesses the device.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/call/callinfo HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1,"callId":"1453723531-574"}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"callingNum":"10086","calledNum":"40103","mid":40,"trunkNo":103,"priority":0,"deviceType":2,"deviceNo":291,"callData":"","callSkill":"Voice_jinsitao","partyNum":1,"callFeature":7,"orgiCalledNum":"","mediaType":5,"waitTime":0,"totalTalkingTimes":658,"logonTimes":659}}</pre>

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Querying the Detailed Status Information About the IVR Flow of a Specified VDN

Interface Description

The interface is used to query the detailed status information about the IVR flow of a specified VDN.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/ivr/ivrdevicestatus
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
flowld	int	No	Indicates the IVR flow ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callld	string	Indicates the ID of a call.
customerLevel	int	Indicates the customer level of the call.
requestType	int	Indicates the call feature. For details, see Call Features .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/ivr/ivrdevicestatus HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1,"flowId":1}</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{ "callId": "1453724606-576", "customerLevel": 1, "requestType": 0 }] }

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Querying the Access Code Information About the IVR Flow of a Specified VDN

Interface Description

The interface is used to query the access code information about the IVR flow of a specified VDN.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/ivr/totalivrinfo
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 4 .

Table 3 Parameter description of result

Parameter	Data Type	Description
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 4 .

Table 4 Parameter description of result

Parameter	Data Type	Description
id	int	Indicates the IVR flow ID.
serviceNo	int	Indicates the ID of a service type.
realFlag	int	Indicates whether the IVR flow is a local one. The options are as follows: 1 : Yes 0 : No

Parameter	Data Type	Description
inNo	string	Indicates the access code.
description	string	Indicates the description of the IVR flow.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/ivr/totalivrinfo HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"id":1,"serviceNo":2,"realFlag":1,"inNo":"6067","description":"transferToSkill"}]}</pre>

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Bulk Querying the Extended Information of Skill Queues

Interface Description

The interface is used to bulk query the extended information of skill queues.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/skill/totalskillstatusex3
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
skilllds	array	Yes	Indicates an array of skill queue IDs. The array contains a maximum of 1000 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
skillId	int	Indicates the ID of a skill queue.
queueSize	int	Indicates the number of calls that are currently waiting in the skill queue.
queueTime	long	Indicates the longest waiting time among all queuing calls.
loggedOnAgents	int	Indicates the number of agents who have signed in to the skill queue at present.
availAgents	int	Indicates the number of available agents at present.
skillDescrip	string	Indicates the description of the skill.
callId	string	Indicates the ID of the call that waits for the longest time.
maxQueueSize	int	Indicates the maximum number of calls that can wait in the queue.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/skill/totalskillstatusex3 HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1,"skillIds":[1,2]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":0,"result": [{"skillId":1,"queueSize":0,"queueTime":0,"loggedOnAgents":0,"availAgents":0,"skillDescrip":"Text chat 1","callId":"4294967295-4294967295","maxQueueSize":100}, {"skillId":2,"queueSize":0,"queueTime":0,"loggedOnAgents":0,"availAgents":0,"skillDescrip":"Text chat 2","callId":"4294967295-4294967295","maxQueueSize":100}]}</pre>

Error Code

- 000-002
- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Bulk Querying the Call Statistics of Skill Queues in the Last Five Minutes

Interface Description

The interface is used to bulk query the call statistics of skill queues in the last five minutes.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/skill/currentcallstateinfo
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
skilllds	array	Yes	Indicates an array of skill queue IDs. The array contains a maximum of 1000 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
id	int	Indicates the ID of a skill queue.
startTime	long	Indicates the start time of the statistics.
allCallCount	long	Indicates the total number of incoming calls in the last five minutes.
cnndCallCount	long	Indicates the total number of connected calls in the last five minutes.
abanCallCount	long	Indicates the total number of lost calls in the last five minutes.
callEndCount	long	Indicates the total number of completed calls in the last five minutes.
talkTimeOnlvr	long	Indicates the call duration of the IVR flow. For calls that are blocked and then transferred to the manual service, the blocked duration is included in the call duration.
cnndIn20sCallCount	long	Indicates the number of calls that are connected within 20s in the last five minutes.
clearUpCallCount	long	Indicates the number of calls that have been wrapped up in the last five minutes.

Parameter	Data Type	Description
clearUpTime	long	Indicates the total wrap-up duration in the last five minutes.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/skill/currentcallstateinfo HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1,"skillIds":[25,1]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":0,"result": [{"id":25,"startTime":1453789500000,"allCallCount":2,"cnndCallCount":1,"abanCallCount":1,"callEndCount":1,"talkTimeOnIvr":0,"cnndIn2 0sCallCount":1,"clearUpCallCount":0,"clearUpTime":0}, {"id":1,"startTime":1453789500000,"allCallCount":0,"cnndCallCount":0,"abanCallCount":0,"callEndCount":0,"talkTimeOnIvr":0,"cnndIn20s CallCount":0,"clearUpCallCount":0,"clearUpTime":0}]}</pre>

Error Code

- 000-002
- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Querying the Status Information of a Specified Skill Queue

Interface Description

The interface is used to query the information about queuing calls in a specified skill queue.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/skill/queuedevicestatus
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
skillld	int	No	Indicates the skill queue ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
callld	string	Indicates the ID of a call.
customerLevel	int	Indicates the customer level.
requestType	int	Indicates the call feature. For details, see Call Features .

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/skill/queuedevicestatus HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 1192.168.0.0:9248 {"ccId" : 1, "vdnId" : 1, "skillId" : 25}</pre>

Example Type	Reference Format
Example of a response packet	HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 { "message": "", "retcode": "0", "result": [{ "callId": "1453866903-655", "customerLevel": 1, "requestType": 0 }, { "callId": "1453866904-656", "customerLevel": 1, "requestType": 0 }] }

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Bulk Querying the Configuration Information of Skill Queues

Interface Description

The interface is used to bulk query the configuration information of skill queues.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - The skills to be queried exist.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/skill/skillcfginfo
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclId	int	No	Indicates the contact center ID. The default value is 0 .
vdnId	int	No	Indicates the VDN ID. The default value is 0 .
skillIds	array	Yes	Indicates an array of skill queue IDs. The array contains a maximum of 1000 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 4 .

Table 3 Parameter description of result

Parameter	Data Type	Description
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 4 .

Table 4 Parameter description of result

Parameter	Data Type	Description
skillId	int	Indicates the ID of a skill queue.
maxCallNum	int	Indicates the maximum number of queuing calls.

Parameter	Data Type	Description
maxHoldCallNum	int	Indicates the maximum number of calls that are placed on hold.
maxWaitTime	long	Indicates the longest waiting time in units of seconds.
maxAnswerWaitTime	long	Indicates the longest no-answer duration in units of seconds.
maxTalkTime	long	Indicates the longest call duration in units of seconds.
maxRestAgentNum	int	Indicates the maximum number of agents who are allowed to rest.
maxAgentWrapupTime	int	Indicates the longest duration of the wrap-up state among all agents in units of seconds.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /msggateway/resource/real/skill/skillcfginfo HTTP/1.1 msggateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1,"skillIds":[1, 2]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result": [{"skillId":1,"maxCallNum":100,"maxHoldCallNum":5,"maxWaitTime":60,"maxAnswerWaitTime":30,"maxTalkTime":86400,"maxRestAgentNum":1,"max AgentWrapupTime":0}, {"skillId":2,"maxCallNum":100,"maxHoldCallNum":5,"maxWaitTime":60,"maxAnswerWaitTime":30,"maxTalkTime":86400,"maxRestAgentNum":1,"maxA gentWrapupTime":0}]}</pre>

Error Code

- 000-002
- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Bulk Querying the Detailed Statistics of Skill Queues

Interface Description

The interface is used to bulk query the detailed statistics of skill queues.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - The skills to be queried exist.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/skill/stateinfo
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclId	int	No	Indicates the contact center ID. The default value is 0 .
vdnId	int	No	Indicates the VDN ID. The default value is 0 .
skillIds	array	Yes	Indicates an array of skill queue IDs. The array contains a maximum of 1000 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
skillId	int	Indicates the ID of a skill queue.
connectedCallNumIn20	long	Indicates the number of calls that are connected within 20s.
allCallNumIn20	long	Indicates the total number of calls within 20s.
agentLoginNums	long	Indicates the number of agents who have signed in.
agentTalkingNums	long	Indicates the number of talking agents.
agentIdleNums	long	Indicates the number of idle agents.
agentAvailableNums	long	Indicates the number of available agents. If agents are in one-to-many mode, this value may differ from the number of idle agents.
agentSetbusyNums	long	Indicates the number of busy agents.

Parameter	Data Type	Description
agentRestNums	long	Indicates the number of resting agents.
agentMaxIdleTimeIn5	long	Indicates the longest idle duration among all agents in the last five minutes.
agentWorkNums	long	Indicates the number of agents in the wrap-up state.
agentStudyNums	long	Indicates the number of agents in the study state.
agentOccupyNums	long	Indicates the number of agents in the occupied state.
agentPreOccupyNums	long	Indicates the number of agents in the preoccupied state.
totalCallNums	long	Indicates the number of calls that are processed, including the calls that are being processed.
processingCallNums	long	Indicates the number of calls that are being processed.
maxCallWaitTimesIn5	long	Indicates the longest call waiting time in the last five minutes.
callWaitNums	long	Indicates the number of queuing calls (or waiting calls).
evenCallTimeIn5	long	Indicates the average call duration in the last five minutes.
evenWaitTimeIn5	long	Indicates the average call waiting time in the last five minutes.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/skill/stateinfo HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1,"skillIds":[1, 2]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":0,"result": [{"skillId":1,"connectedCallNumIn20":0,"allCallNumIn20":0,"agentLoginNums":1,"agentTalkingNums":0,"agentIdleNums":0,"agentAvailableNums":0,"agentSetbusyNums":1, "agentRestNums":0,"agentMaxIdleTimeIn5":0,"agentWorkNums":0, "agentStudyNums":0,"agentOccupyNums":0,"agentPreOccupyNums":0,"totalCallNums":0,"processingCallNums":0,"maxCallWaitTimesIn5":0,"callWaitNums":0,"evenCallTimeIn5":0,"evenWaitTimeIn5":0}, {"skillId":2,"connectedCallNumIn20":0,"allCallNumIn20":0,"agentLoginNums":0,"agentTalkingNums":0,"agentIdleNums":0,"agentAvailableNums":0,"agentSetbusyNums":0, "agentRestNums":0,"agentMaxIdleTimeIn5":0,"agentWorkNums":0,"agentStudyNums":0,"agentOccupyNums":0,"agentPreOccupyNums":0,"totalCallNums":0,"processingCallNums":0,"maxCallWaitTimesIn5":0,"callWaitNums":0,"evenCallTimeIn5":0,"evenWaitTimeIn5":0}]}</pre>

Error Code

- 000-002
- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Querying the Information About All Skill Queues of a Specified VD

Interface Description

The interface is used to query the information about all skill queues of a specified VDN.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/skill/totalskill
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
id	int	Indicates the ID of a skill queue.
mediaType	int	Indicates the media type. For details, see Media Types .
serviceType	int	Indicates the ID of a service type.
realFlag	int	Indicates the queue type. The options are as follows: 1 : real queue 0 : virtual queue
name	string	Indicates the description of the skill queue.

Interface Example

Example Type	Reference Format
Example of a request packet	POST /cmsgateway/resource/real/skill/totalskill HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8

Example Type	Reference Format
	Host: 192.168.0.0:9248 { "ccId":1,"vdnId":1 }
Example of a response packet	HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 { "message":"","retcode":"0","result":[{"id":1,"mediaType":1,"serviceType":1,"realFlag":1,"name":"text chat 1"}, {"id":10,"mediaType":1,"serviceType":1,"realFlag":1,"name":"text chat 2"}]}

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Bulk Querying All Queuing Calls in Skill Queues

Interface Description

The interface is used to bulk query all queuing calls in skill queues.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - The skills to be queried exist.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/skill/batchmultiskill
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclId	int	No	Indicates the contact center ID. The default value is 0 .
vdnId	int	No	Indicates the VDN ID. The default value is 0 .
skillIds	array	Yes	Indicates an array of skill queue IDs. The array contains a maximum of 1000 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
skillId	int	Indicates the ID of a skill queue.
callPropertyExs	array	Indicates an array of queuing calls in the skill queue. For the parameter description of callPropertyExs , see Table 4 .

Table 4 Parameter description of callPropertyExs

Parameter	Data Type	Description
callId	string	Indicates the ID of a call.
customerLevel	int	Indicates the customer level of the call.
requestType	int	Indicates the call feature. For details, see Call Features .

Parameter	Data Type	Description
callPriority	long	Indicates the priority of the call.
waitTime	long	Indicates the waiting time of the call in the skill queue.
callQueueFlag	long	Indicates whether the skill queue is the primary queue of the call. The options are as follows: 1 : Yes 0 : No

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/skill/batchmultiskill HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1,"skillIds":[1, 25]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":0,"result":[{"skillId":1,"callPropertyExs":[]}, {"skillId":25,"callPropertyExs":[{"callId":"1453792909-591","customerLevel":1,"requestType":0, "callPriority":1,"waitTime":3,"callQueueFlag":1}]}]}</pre>

Error Code

- 000-002
- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Bulk Querying the Number of Calls that a Skill Queue Picks Up from Other Skill Queues in the Case that Multiple Skill Queues Have Waiting Calls

Interface Description

When each call can queue up in multiple skill queues through the IVR flow, the interface is used to query the number of calls that a skill queue picks up from other skill queues in the case that multiple skill queues have waiting calls.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - The skills to be queried exist.
 - Each call can queue up in multiple skill queues through the IVR flow.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions

None
3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/skill/batchskilloverload
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnId	int	No	Indicates the VDN ID. The default value is 0 .
skillIds	array	Yes	Indicates an array of skill queue IDs. The array contains a maximum of 1000 IDs.

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
cclid	int	Indicates the contact center ID.
vdnId	int	Indicates the VDN ID.
skillId	int	Indicates the ID of a skill queue.
overloadDetails	array	Indicates the detailed call information of other skill queues. For the parameter description of overloadDetails , see Table 4 .

Table 4 Parameter description of overloadDetails

Parameter	Data Type	Description
-----------	-----------	-------------

Parameter	Data Type	Description
queueId	int	Indicates the ID of a skill queue.
callNum	long	Indicates the number of calls that are answered.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /msgateway/resource/real/skill/batchskilloverload HTTP/1.1 msgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1,"skillIds":[1, 2]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"ccId":1,"vdnId":1,"skillId":1,"overloadDetails":[]}, {"ccId":1,"vdnId":1,"skillId":2,"overloadDetails":[]}]}</pre>

Error Code

- 000-002
- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Querying the Service Type Information of a Specified VDN

Interface Description

The interface is used to query the service type information of a specified VDN.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/sys/servicetype
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
id	int	Indicates the ID of a service type.
description	int	Indicates the description of the service type.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/sys/servicetype HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"id":1,"description":"Text chat"}, {"id":10,"description":"ddd High-level incident reception & Common incident reception"}]}</pre>

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying the Server Time of the CTI Platform

Interface Description

The interface is used to query the server time of the CTI platform.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/sys/ctiservertime
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	long	Indicates the UTC time stamp of the server where the CTI platform is configured.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/sys/ctiservertime HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":1453808611000}</pre>

Error Code

- 300-008
- 300-009
- 300-010
- 300-013

Parent topic: [Real-Time Interfaces](#)

Querying the Current License Usage Condition of the System

Interface Description

The interface is used to query the current license usage condition of the system.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/sys/systemlicense
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
licenseMaxAgentNum	long	Indicates the maximum number of agents who have signed in, which can be supported by the license.
licenseMaxVideoAgentNum	long	Indicates the maximum number of video agents who have signed in, which can be supported by the license.
licenseMaxVdnNum	long	Indicates the maximum number of VDNs that can be supported by the license.
licenseMaxIvrCallNum	long	Indicates the maximum number of IVR calls that can be supported by the license.
licenseMaxVoiceCallNum	long	Indicates the maximum number of voice calls that can be supported by the license.
licenseMaxWebCallNum	long	Indicates the maximum number of web calls that can be supported by the license.
loginAgentNum	long	Indicates the number of agents who have signed in at present.
loginVideoAgentNum	long	Indicates the number of video agents who have signed in at present.
vdnNum	long	Indicates the number of VDNs that have been configured at present.
ivrCallNum	long	Indicates the number of IVR calls at present.
voiceCallNum	long	Indicates the number of voice calls at present.

Parameter	Data Type	Description
webCallNum	long	Indicates the number of web calls at present.
historyMaxAgentNum	long	Indicates the maximum number of agents who have signed in to the system in history.
historyMaxVideoAgentNum	long	Indicates the maximum number of video agents who have signed in to the system in history.
historyMaxIvrCallNum	long	Indicates the maximum number of IVR calls in history.
historyMaxVoiceCallNum	long	Indicates the maximum number of voice calls in history.
historyMaxWebCallNum	long	Indicates the maximum number of web calls in history.
licenseStartDate	long	Indicates the UTC time stamp corresponding to the start time of the license.
licenseEndDate	long	Indicates the UTC time stamp corresponding to the end time of the license.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /msgateway/resource/real/sys/systemlicense HTTP/1.1 msgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"licenseMaxAgentNum":10000,"licenseMaxVideoAgentNum":4294967295,"licenseMaxVdnNum":300,"licenseMaxIvrCallNum":20000, "licenseMaxVoiceCallNum":20000,"licenseMaxWebCallNum":4294967295,"loginAgentNum":25,"loginVideoAgentNum":4294967295,"vdnNum":5,"ivrCal lNum":0,"voiceCallNum":1,"webCallNum":4294967295, "historyMaxAgentNum":4294967295,"historyMaxVideoAgentNum":4294967295,"historyMaxIvrCallNum":4294967295, "historyMaxVoiceCallNum":4294967295,"historyMaxWebCallNum":4294967295,"licenseStartDate":1450886400000,"licenseEndDate":1458748799000} }</pre>

Error Code

- 300-008
- 300-009
- 300-010
- 300-013

Parent topic: [Real-Time Interfaces](#)

Querying the Current License Usage Condition of a Specified VDN

Interface Description

The interface is used to query the current license usage condition of a specified VDN.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/sys/vdnlicense
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
maxVoiceCallNum	long	Indicates the maximum number of voice calls that can be supported by the VDN.
voiceCallNum	long	Indicates the number of voice calls under the VDN at present.
historyMaxVoiceCallNum	long	Indicates the maximum number of voice calls under the VDN in history.
maxIvrCallNum	long	Indicates the maximum number of IVR calls that can be supported by the VDN.
ivrCallNum	long	Indicates the number of IVR calls under the VDN at present.
historyMaxIvrCallNum	long	Indicates the maximum number of IVR calls under the VDN in history.
maxLoginAgentNum	long	Indicates the maximum number of agents who have signed in, which can be supported by the VDN.
loginAgentNum	long	Indicates the number of agents who have signed in under the VDN at present.
historyMaxLoginAgentNum	long	Indicates the maximum number of agents who have signed in under the VDN in history.
maxVideoLoginAgentNum	long	Indicates the maximum number of video agents who have signed in, which can be supported by the VDN.

Parameter	Data Type	Description
videoLoginAgentNum	long	Indicates the number of video agents who have signed in under the VDN at present.
historyMaxVideoLoginAgentNum	long	Indicates the maximum number of video agents who have signed in under the VDN in history.
maxWebCallNum	long	Indicates the maximum number of web calls that can be supported by the VDN.
webCallNum	long	Indicates the number of web calls under the VDN at present.
historyMaxWebCallNum	long	Indicates the maximum number of web calls under the VDN in history.
maxOutboundCallNum	long	Indicates the maximum number of outgoing calls that can be supported by the VDN.
outboundCallNum	long	Indicates the number of outgoing calls under the VDN at present.
historyMaxOutboundCallNum	long	Indicates the maximum number of outgoing calls under the VDN in history.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /msgateway/resource/real/sys/vdnlicense HTTP/1.1 msgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"maxVoiceCallNum":2500,"voiceCallNum":1,"historyMaxVoiceCallNum":4294967295,"maxIvrCallNum":2500, "ivrCallNum":0,"historyMaxIvrCallNum":4294967295,"maxLoginAgentNum":6000,"loginAgentNum":24,"historyMaxLoginAgentNum":4294967295, "maxVideoLoginAgentNum":4294967295,"videoLoginAgentNum":4294967295,"historyMaxVideoLoginAgentNum":4294967295,"maxWebCallNum":4294967295, "webCallNum":4294967295,"historyMaxWebCallNum":4294967295, "maxOutboundCallNum":4294967295,"outboundCallNum":4294967295,"historyMaxOutboundCallNum":4294967295}}</pre>

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Querying the Agent Resting Reason Codes of a Specified VDN

Interface Description

The interface is used to query the agent resting reason codes of a specified VDN.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/vdn/restreasons
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
code	int	Indicates the code of a resting reason.
reasonInfo	string	Indicates the description of the resting reason.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/vdn/restreasons HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccId":1,"vdnId":1}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"code":5,"reasonInfo":"123456789"}]}</pre>

Error Code

- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying All VDNs in a Specified Call Center

Interface Description

The interface is used to query the information about all VDNs of a specified contact center.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights.
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/vdn/vdninfos
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
ccld	int	No	Indicates the contact center ID. The default value is 0 .

Response Message

Table 2 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
vdnId	int	Indicates the VDN ID.
vdnName	string	Indicates the VDN name.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/real/vdn/vdninfos HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"ccld":1}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":[{"vdnId":1,"vdnName":"social cc"}, {"vdnId":2,"vdnName":"Credit card"}, {"vdnId":3,"vdnName":"95558_2"}, {"vdnId":4,"vdnName":"VDN4"}, {"vdnId":5,"vdnName":"Test VDN"}]}</pre>

Error Code

- 300-008

- 300-009
- 300-010
- 300-013

Parent topic: [Real-Time Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying the Number of Agents in Different States in Agent Groups

Interface Description

The interface is used to query the number of agents in different states in agent groups.

Usage Description

1. Prerequisites

- The CMS Gateway is properly connected to the CCS.
- This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights. (During VDN authentication, information only under the local VDN can be queried)

2. Precautions

None

3. Use restrictions

None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/complex/agent/agentstatusbyteam
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
agentList	array	Yes	Indicates an array of agent group IDs. For the parameter description of agentList , see Table 2 .

Table 2 Parameter description of agentList

Parameter	Data Type	Mandatory (Yes/No)	Description
ccld	int	No	Indicates the contact center ID. The default value is 0 .
vdnld	int	No	Indicates the VDN ID. The default value is 0 .
agentlds	array	Yes	Indicates an array of agent work IDs. The array contains a maximum of 20000 IDs.

Response Message

Table 3 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 4 .

Table 4 Parameter description of result

Parameter	Data Type	Description
logged	int	Indicates the number of agents who have signed in.
talking	int	Indicates the number of talking agents.
idle	int	Indicates the number of idle agents.
usable	int	Indicates the number of available agents.
setbusy	int	Indicates the number of agents in the busy state.

Parameter	Data Type	Description
workSubstateBegin	int	Indicates the number of agents in the ACW state.
rest	int	Indicates the number of resting agents.
studing	int	Indicates the number of agents in the study state.
occupy	int	Indicates the number of agents in the occupied state.
preoccupy	int	Indicates the number of agents in the preoccupied state.
answering	int	Indicates the number of answering agents.
lateAdjust	int	Indicates the number of agents in the wrap-up state.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/complex/agent/agentstatusbyteam HTTP/1.1 cmsgateway-token:d2976bce-3f5f-422b-bb8b-79e987c53fe8 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"agentList": [{"ccId": 1, "vdnId": 1, "agentIds": [102, 103, 104]}, {"ccId": 1, "vdnId": 1, "agentIds": [292, 106, 107]}]}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result":{"logged":1,"talking":0,"idle":1,"usable":1,"setbusy":0,"workSubstateBegin":0,"rest":0,"studing":0,"occupy":0,"preoccupy":0,"answering":0,"lateAdjust":0}}</pre>

Error Code

- 000-002
- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Querying the Number of Agents in Different States in Skill Queues

Interface Description

The interface is used to query the number of agents in different states in skill queues.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights. (During VDN authentication, information only under the local VDN can be queried)
2. Precautions
 - None
3. Use restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/complex/skill/agentstatusbyskill
Request Method	POST

Request Message

Table 1 Request message description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	Yes	Indicates the IP address of the CMS Gateway.
port	int	Yes	Indicates the HTTP or HTTPS port number of the CMS Gateway.
Request Header			
Content-Type	string	Yes	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	Yes	Indicates the interface authentication information.
Request Body			
skillList	array	Yes	Indicates an array of skill queue IDs. The array contains a maximum of 1000 IDs. For the parameter description of skillList , see Table 2 .
isSkillAllMatch	boolean	No	Indicates whether the entered skills completely match with the skills configured in the system. This parameter is valid only if there is a single VDN. The default value is true . When there are multiple VDNs, the value must be false .

Table 2 Parameter description of skillList

Parameter	Data Type	Mandatory (Yes/No)	Description
cclid	int	No	Indicates the contact center ID. The default value is 0 .
vdnId	int	No	Indicates the VDN ID. The default value is 0 .
skillId	int	No	Indicates the skill queue ID. The default value is 0 .

Response Message

Table 3 Response message description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 4 .

Table 4 Parameter description of result

Parameter	Data Type	Description
logged	int	Indicates the number of agents who have signed in.
talking	int	Indicates the number of talking agents.
idle	int	Indicates the number of idle agents.

Parameter	Data Type	Description
usable	int	Indicates the number of available agents.
setbusy	int	Indicates the number of agents in the busy state.
workSubstateBegin	int	Indicates the number of agents in the ACW state.
rest	int	Indicates the number of resting agents.
studing	int	Indicates the number of agents in the study state.
occupy	int	Indicates the number of agents in the occupied state.
preoccupy	int	Indicates the number of agents in the preoccupied state.
answering	int	Indicates the number of answering agents.
lateAdjust	int	Indicates the number of agents in the wrap-up state.

Interface Example

Example Type	Reference Format
Example of a request packet	<pre>POST /cmsgateway/resource/complex/skill/agentstatusbyskill HTTP/1.1 cmsgateway-token:590b218cdcd61aad2e86de127f420cf9.AgentGateway1 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248 {"skillList" : [{"ccId" : 1, "vdnId" : 1, "skillId" :1}, {"ccId" : 1, "vdnId" : 1, "skillId" :2}], "isSkillAllMatch" : false}</pre>
Example of a response packet	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 {"message":"","retcode":"0","result": {"logged":1,"talking":0,"idle":1,"usable":1,"setbusy":0,"workSubstateBegin":0,"rest":0,"studing":0,"occupy":0,"preoccupy":0,"answering":0,"lateAdjust":0}}</pre>

Error Code

- 000-002
- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Querying the Agent Status Change Reason in a Specified VDN

Interface Description

This interface is used to query the reason why the agent status changes to busy or offline in a specified VDN.

Usage Description

1. Prerequisites
 - The CMS Gateway is properly connected to the CCS.
 - The database is connected properly.
 - This interface can be invoked only when the user is a system administrator or a VDN user who has the inspection rights. (During VDN authentication, information only under the local VDN can be queried)
2. Precautions
 - None
3. Usage Restrictions
 - None

Interface Prototype

Request URL	http(s)://ip:port/cmsgateway/resource/real/statusreasons/{ccld}/{vdnId}
Request Method	GET

Request

Table 1 Request description

Parameter	Data Type	Mandatory (Yes/No)	Description
Request URI			
ip	string	M	Indicates the IP address of the CMS Gateway.
port	int	M	Indicates the HTTP or HTTPS port number of the CMS Gateway.
ccld	int	M	Indicates the contact center ID.
vdnId	int	M	Indicates the VDN ID.
Request Header			
Content-Type	string	M	The fixed value is application/json; charset=UTF-8 .
cmsgateway-token	string	M	Indicates the interface authentication information.

Response

Table 2 Response description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the description.
retcode	string	Indicates the error code. The options are as follows: 0 : success Others: failure
result	array	Indicates the return result of a successful query. (Note: The return result contains the public status change reason with both ccld and vdnId set to 0 .) For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
ccld	int	Indicates the contact center ID.
vdnId	int	Indicates the VDN ID.
state	int	Agent status. For details, see Agent status .
reasonCode	string	Indicates the status change reason code.
reasonInfo	string	Indicates the status change reason description.

Interface Example

Example Type	Reference Format
Request example	<pre>GET /cmsgateway/resource/real/statusreasons/1/2 HTTP/1.1 cmsgateway-token:506bc7e7f04dd5bcc483983ddc3faa0532c0f756cf47fb85.AgentGateway1 Content-Type:application/json;charset=UTF-8 Host: 192.168.0.0:9248</pre>

Example Type	Reference Format
Response example	<pre>HTTP/1.1 200 OK Content-Type:application/json;charset=UTF-8 { "result": [{ "ccId": 0, "vdnId": 0, "state": 7, "reasonCode": 1, "reasonInfo": null }, { "ccId": 0, "vdnId": 0, "state": 7, "reasonCode": 2, "reasonInfo": "Long no answer" }, { "ccId": 0, "vdnId": 0, "state": 7, "reasonCode": 3, "reasonInfo": "Forced busy by QC inspector" }, { "ccId": 0, "vdnId": 0, "state": 7, "reasonCode": 4, "reasonInfo": "Rest" }, { "ccId": 0, "vdnId": 0, "state": 7, "reasonCode": 5, "reasonInfo": "Agent phone unavailable" }, { "ccId": 0, "vdnId": 0, "state": 7, "reasonCode": 7, "reasonInfo": "Agent rejects a call" }, { "ccId": 1, "vdnId": 2, "state": 7, "reasonCode": 223, "reasonInfo": "reason223_en" }], "message": "", "retcode": "0" }</pre>

Error Codes

- 000-002
- 200-001
- 300-008
- 300-009
- 300-010

Parent topic: [Real-Time Interfaces](#)

Report interface

[Downloading Voice Call CDRs of a VDN](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Downloading Voice Call CDRs of a VDN

Prerequisites

- The CMS Gateway is properly connected to the CCS.
- The latest CMS script has been executed in the database.
- This interface can be invoked only after system administrator authentication.

Interface Description

This interface is used to download voice call CDRs. In the query conditions, the **WAITBEGIN** field is used as the filter items of the start time and end time. The results are sorted in descending order by **CALLEDN**. Concurrent download is not supported for performance reasons. In the query conditions, the maximum interval between the start time and end time is 24 hours, and the minimum interval is 5 seconds. The start and end time format is yyyy-MM-dd HH:mm:ss. The query result contains **CALLID** (unique call ID), **CALLIDNUM** (

CDR sequence number), **CALLERNO** (calling number), **CALLEENO** (called number), **WAITBEGIN** (waiting start time), and **WAITEND** (waiting end time), **ACKBEGIN** (answer start time), **ACKEND** (answer end time), **CALLBEGIN** (call start time), **CALLEND** (call end time), **DEVICETYPE** (device type), **DEVICENO** (device number), **DEVICEIN** (access device), **WAITCAUSE** (reason why the call is waiting on the current device), **RELEASECAUSE** (reason why the call leaves the device), **CALLTYPE** (call type), **UCENTERREASON** (reason why the call enters the device), and **UCLEAVEAREASON** (reason why the call leaves the device).

Request Method

POST. This interface supports only POST, but not PUT, GET, DELETE, or other methods.

Request URL

http(s)://ip:port/cmsgateway/resource/reports/vdnvoicecalldetail

In the URL, *ip* indicates the IP address of the CMS Gateway server, and *port* indicates the HTTP or HTTPS port number of the CMS Gateway server.

Request Message

- Message header

Content-Type:application/json; charset=UTF-8

- Message body

The following provides an example of the request message body of this interface:

```
{
  "ccld" : 1,
  "vdnld" : 1,
  "startTime" : "2018-1-1 00:00:00",
  "endTime" : "2018-1-1 23:00:00"
}
```

[Table 1](#) describes the parameters in the request message body of this interface.

Table 1 Parameters in the message body

Parameter	Data Type	Mandatory (Yes/No)	Description
ccld	int	No	Indicates the contact center ID. The default value is 1.
vdnld	int	No	Indicates the VDN ID. The default value is 1.
startTime	String	Yes	Indicates the start time. The value format is yyyy-MM-dd HH:mm:ss.
endTime	String	Yes	Indicates the end time. The value format is yyyy-MM-dd HH:mm:ss.

Response Message

The following is an example of the response message header:

Content-Disposition → attachment; filename=bill_2018-1-1 00:00:00_2018-1-1 23:00:00.csv

Content-Type → application/csv; charset=UTF-8

result → {message=get report success, retcode=0}

The following provides an example of the response message body of this interface:

CALLID,CALLIDNUM,CALLERNO,CALLEENO,WAITBEGIN,WAITEND,ACKBEGIN,ACKEND,CALLBEGIN,CALLEND,DEVICETYPE,DEVICENO,DEVICEIN,WAITCAUSE,RELEASECAUSE,UCENTERREASON,UCLEAVEAREASON
1533893930-10,-1,86091,10010,2018-08-10 17:38:50,2018-08-10 17:38:50,2018-08-10 17:38:50,2018-08-10 17:39:06,2018-08-10 17:39:06,2018-08-10 17:39:17,2,117,DEVICE_AGENT,0,531,0

[Table 2](#) describes the parameters in the response message header of this interface.

Table 2 Parameters in the message header

Parameter	Description
filename in Content-Disposition	Indicates the name of the downloaded file.
Content-Type → application/csv; charset=UTF-8	The file format is CSV and the encoding format is UTF-8.
Retcode in result	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
Message in the result	Indicates the detailed information about the error.

[Table 3](#) describes the parameters in the response message body of this interface.

Table 3 Parameters in the message body

Parameter	Data Type	Description
CALLID	String	Indicates the unique call ID.

Parameter	Data Type	Description
CALLIDNUM	String	Indicates the serial number of a CDR. The serial numbers are used to identify multiple CDRs generated for one call. The value 1 indicates the first CDR for a call and -1 indicates the last CDR for the call.
CALLERNO	String	Indicates the calling number. It can be a telephone number, email address, web page, and so on.
CALLEENO	String	Indicates the called number. It can be a telephone number, email address, web page, and so on.
WAITBEGIN	String	Indicates the start time of call waiting, that is, the time when the call accesses the device.
WAITEND	String	Indicates the end time of call waiting, that is, the time when the call waiting ends.
ACKBEGIN	String	Indicates the start time when the call is answered on the device. AckBegin = WaitEnd
ACKEND	String	Indicates the end time when the call is ended on the device.
CALLBEGIN	String	Indicates the time when the conversation starts on the device. CallBegin = AckEnd
CALLEND	String	Indicates the time when the conversation ends on the device.
DEVICETYPE	String	Indicates the type of the device processing the call.
DEVICENO	String	Indicates the ID of the device processing the call. - For agent, the device number is the agent ID. - For the queue or virtual device, the device number is the queue ID or ID of the network shared device to which the virtual device corresponds (the ID is configured on the web configuration console). - For other devices, the device number is the internal ID.
DEVICEIN	String	Indicates the device description. - Skill queue: The value is DEVICE_QUEUE. - Agent: The value is DEVICE_AGENT. - If the value of DeviceType is 3 (IVR process), the value of this parameter is the access code of the corresponding IVR process. - Call: The value is the corresponding telephone number. - Temporary routing device: The value is DEVICE_ROUTE. - Virtual device: The value is DEVICE_VNR. - If the value of DeviceType is 10 (CDN device), the value of this parameter is a CDN number. - If the value of DeviceType is 14 (PGR), the value of this parameter is the PGR access code.
WAITCAUSE	String	Indicates the reason for call waiting on the device. 0: no waiting 2: waiting in a queue 3: waiting offline (The service instructs the current call to queue offline.)
RELEASECAUSE	String	Indicates the reason for call release. Call Release Cause Codes describes the reasons. When CallIDNUM is set to -1 , this field indicates the call release reason. In other cases, the field is meaningless.
CALLTYPE	String	Indicates the type of a call. See Call Type .
UCENTERREASON	String	Indicates the reason why a call accesses the device. See Cause Why a Call Accesses or Leaves the Device .
UCLEAVEREASON	String	Indicates the reason why a call is disconnected from a device. See Cause Why a Call Accesses or Leaves the Device .

Error Code

- 300-008
- 300-009
- 300-013
- 300-015
- 300-016
- 300-017

Parent topic: [Report interface](#)

Interface for Managing Inspection User Groups

[Adding an Agent to an Inspector Group](#)

[Querying All Inspector Groups of a Specified VDN](#)

Parent topic: [Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Adding an Agent to an Inspector Group

Prerequisites

- The CMS Gateway is properly connected to the CCS.
- This interface can be invoked only when the CMS service administrator is authenticated if authentication is enabled.

Interface Description

The interface is used to add an agent to an inspector group on the CMS.

NOTE

If the agent to be added to the inspector group cannot be found, the CMS automatically triggers VDN synchronization. If the invoking party receives the error code 300-016 (the agent does not exist under the VDN), check the agent ID. If the agent exists, try again one minute later

Request Method

POST. This interface supports only POST, but not PUT, GET, DELETE, or other methods.

Request URL

http(s)://ip:port/cmsgateway/resource/spvgroup/join

In the URL, *ip* indicates the IP address of the CMS Gateway server, and *port* indicates the HTTP or HTTPS port number of the CMS Gateway server.

Request Message

- Message header

Content-Type:application/json; charset=UTF-8

cmsgateway-token:80c0ae42-32e7-4f20-9526-644b526b5a93

- Message body

The following provides an example of the request message body of this interface:

```
{"ccld":1, "vdnId":1, "agentId":189, "groupId":"0000000051", "groupName":"test33"}
```

[Table 1](#) describes the parameters in the request message body of this interface.

Table 1 Parameter description

Parameter	Data Type	Mandatory (Yes/No)	Description
ccld	int	Yes	Indicates the contact center ID.
vdnId	int	Yes	Indicates the VDN ID.
agentId	int	Yes	Indicates the ID of the agent to be added to the inspector group.
groupId	string	No	Indicates the ID of the inspector group. If the group ID is not carried, an inspector group is created using the name specified by groupName , and then the agent is added to the new group. If the agent already exists in another group, the agent is automatically removed from it. If the group ID is carried, the groupName parameter is ignored, and the agent is added to the inspector group corresponding to groupId . If the agent already exists in another inspector group, the agent is automatically removed from it.
groupName	string	No	Indicates the name of the inspector group. The system normalizes the group name and deletes the leading and ending spaces.

Response Message

The following provides an example of the response message body of this interface:

```
{"message":"","retcode":"0","result":{"groupId":"0000000051", "groupName": "test33"}}
```

[Table 2](#) describes the parameters in the response message body of this interface.

Table 2 Parameter description

Parameter	Data Type	Description
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	object	Indicates the return result of a successful addition. For the parameter description of result , see the following table.

Table 3 Parameter description of result

Parameter	Data Type	Description
groupId	string	Indicates the ID of the inspector group.
groupName	string	Indicates the name of the inspector group.

Error Code

- 300-008
- 300-009

- 300-010
- 300-015
- 300-016
- 300-017
- 300-018
- 300-019
- 300-020

Parent topic: [Interface for Managing Inspection User Groups](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Querying All Inspector Groups of a Specified VDN

Prerequisites

- The CMS Gateway is properly connected to the CCS.
- This interface can be invoked only when the CMS service administrator is authenticated if authentication is enabled.

Interface Description

The interface is used to query all inspector groups of a specified VDN.

Request Method

POST. This interface supports only POST, but not PUT, GET, DELETE, or other methods.

Request URL

http(s)://ip:port/cmsgateway/resource/spvgroup/query

In the URL, *ip* indicates the IP address of the CMS Gateway server, and *port* indicates the HTTP or HTTPS port number of the CMS Gateway server.

Request Message

- Message header

Content-Type:application/json; charset=UTF-8

cmsgateway-token:80c0ae42-32e7-4f20-9526-644b526b5a93

- Message body

The following provides an example of the request message body of this interface:

```
{"ccld":1, "vdnId":1}
```

[Table 1](#) describes the parameters in the request message body of this interface.

Table 1 Parameter description

Parameter	Data Type	Mandatory (Yes/No)	Description
ccld	int	Yes	Indicates the contact center ID.
vdnId	int	Yes	Indicates the VDN ID.

Response Message

The following provides an example of the response message body of this interface:

```
{"message":"","retcode":"0","result":[{"groupId":"0000000001", "groupName": "Voice skill group 1"}, {"groupId":"0000000051", "groupName": "test33"}]}
```

[Table 2](#) describes the parameters in the response message body of this interface.

Table 2 Parameter description

Parameter	Data Type	Description
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0 : Succeed Other values: Fail
result	array	Indicates the return result of a successful query. For the parameter description of result , see Table 3 .

Table 3 Parameter description of result

Parameter	Data Type	Description
groupId	string	Indicates the inspector group ID.
groupName	string	Indicates the inspector group name.

Error Code

- 300-008
- 300-009
- 300-010
- 300-015
- 300-020

Parent topic: [Interface for Managing Inspection User Groups](#)

Secondary Development Guide

[Voice CDR Development Guide](#)
Parent topic: [CMS Server Interface \(RESTful\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Voice CDR Development Guide

Overview

Platform call information is saved to the media CDR table after CDRs are imported to the database. The platform UIDB database CDR table is not directly opened to users. Users need to invoke the interface provided by the CMS Server to obtain CDR data. The CMS Server obtains CDR data from the platform database and sends the CDR data in CSV files to users. After obtaining data, users can refer to the following cases for secondary development.

Prerequisites

Voice CDRs have been obtained using the interface [Downloading Voice Call CDRs of a VDN](#).

Scenario Example

1. A user invokes the interface to obtain the CDRs of all incoming calls of a VDN in a specified period.

```
SELECT CALLID, CALLIDNUM, CALLERNO, CALLEENO, WAITBEGIN, WAITEND, ACKBEGIN, ACKEND, CALLBEGIN, CALLEND, DEVICETYPE, DEVICENO,
DEVICEIN, WAITCAUSE, RELEASECAUSE, CALLTYPE
FROM tableName
WHERE WAITBEGIN between to_date(startTime, 'yyyy-mm-dd hh24:mi:ss') AND to_date(endTime, 'yyyy-mm-dd hh24:mi:ss')
AND CALLTYPE IN(0, 5, 13, 15, 20, 21, 22, 23, 46)
ORDER BY CALLEND DESC;
```
2. The user invokes the interface to obtain the CDRs of all outgoing calls of the VDN in a specified period.

```
SELECT CALLID, CALLIDNUM, CALLERNO, CALLEENO, WAITBEGIN, WAITEND, ACKBEGIN, ACKEND, CALLBEGIN, CALLEND, DEVICETYPE, DEVICENO,
DEVICEIN, WAITCAUSE, RELEASECAUSE, CALLTYPE
FROM tableName
WHERE WAITBEGIN between to_date(startTime, 'yyyy-mm-dd hh24:mi:ss') AND to_date(endTime, 'yyyy-mm-dd hh24:mi:ss')
AND CALLTYPE IN (7, 8, 9, 10, 12, 14, 16, 17, 41, 43, 44)
ORDER BY CALLEND DESC;
```
3. The user invokes the interface to obtain all call CDRs on a device of the VDN in a specified period.

```
SELECT CALLID, CALLIDNUM, CALLERNO, CALLEENO, WAITBEGIN, WAITEND, ACKBEGIN, ACKEND, CALLBEGIN, CALLEND, DEVICETYPE, DEVICENO,
DEVICEIN, WAITCAUSE, RELEASECAUSE, CALLTYPE
FROM tableName
WHERE WAITBEGIN between to_date(startTime, 'yyyy-mm-dd hh24:mi:ss') AND to_date(endTime, 'yyyy-mm-dd hh24:mi:ss')
AND DeviceNo=XXX
ORDER BY CALLEND DESC;
```
4. The user invokes the interface to obtain the CDRs of all calls released on the device of the VDN in a specified period.

```
SELECT CALLID, CALLIDNUM, CALLERNO, CALLEENO, WAITBEGIN, WAITEND, ACKBEGIN, ACKEND, CALLBEGIN, CALLEND, DEVICETYPE, DEVICENO,
DEVICEIN, WAITCAUSE, RELEASECAUSE, CALLTYPE
FROM tableName
WHERE WAITBEGIN between to_date(startTime, 'yyyy-mm-dd hh24:mi:ss') AND to_date(endTime, 'yyyy-mm-dd hh24:mi:ss')
AND DeviceNo=XXX
AND CALLIDNUM=-1
ORDER BY CALLEND DESC;
```
5. The user invokes the interface to obtain the calls that have the same release cause code of the VDN in a specified period.

```
SELECT CALLID, CALLIDNUM, CALLERNO, CALLEENO, WAITBEGIN, WAITEND, ACKBEGIN, ACKEND, CALLBEGIN, CALLEND, DEVICETYPE, DEVICENO,
DEVICEIN, WAITCAUSE, RELEASECAUSE, CALLTYPE
FROM tableName
WHERE WAITBEGIN between to_date(startTime, 'yyyy-mm-dd hh24:mi:ss') AND to_date(endTime, 'yyyy-mm-dd hh24:mi:ss')
AND ReleaseCause = xxx
ORDER BY CALLEND DESC;
```
6. The user invokes the interface to obtain all CDRs of a call on the platform.

```
SELECT CALLID, CALLIDNUM, CALLERNO, CALLEENO, WAITBEGIN, WAITEND, ACKBEGIN, ACKEND, CALLBEGIN, CALLEND, DEVICETYPE, DEVICENO,
DEVICEIN, WAITCAUSE, RELEASECAUSE, CALLTYPE
FROM tableName
WHERE WAITBEGIN between to_date(startTime, 'yyyy-mm-dd hh24:mi:ss') AND to_date(endTime, 'yyyy-mm-dd hh24:mi:ss')
AND CALLID = XXX
ORDER BY CALLEND DESC;
```
7. The user invokes the interface to obtain all call CDRs of a calling number of the VDN in a specified period.

```
SELECT CALLID, CALLIDNUM, CALLERNO, CALLEENO, WAITBEGIN, WAITEND, ACKBEGIN, ACKEND, CALLBEGIN, CALLEND, DEVICETYPE, DEVICENO,
DEVICEIN, WAITCAUSE, RELEASECAUSE, CALLTYPE
FROM tableName
WHERE WAITBEGIN between to_date(startTime, 'yyyy-mm-dd hh24:mi:ss') AND to_date(endTime, 'yyyy-mm-dd hh24:mi:ss')
AND CALLERNO=XXX
ORDER BY CALLEND DESC;
```

Parent topic: [Secondary Development Guide](#)

Appendix

[Error Codes](#)

[WAS Synchronization Data Tables](#)

[WAS Synchronization Status](#)

[Media Types](#)

[Device Types](#)

[Historical Monitoring Indexes](#)

[Real-Time Monitoring Indexes](#)

[Agent Status](#)

[Operating Status of Agents](#)

[Call Status](#)

[Call Features](#)

[Agent Permission Values](#)

[Call Type](#)

[Call Release Cause Codes](#)

[Cause Why a Call Accesses or Leaves the Device](#)

Parent topic: [CMS Server Interface \(RESTful\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Error Codes

Table 1 Error codes

Error Code	Description
000-002	The parameters transmitted using the URL are incorrect, the IP address is incorrect, or the interface parameters are invalid and do not comply with relevant definitions.
100-001	Failed to connect to the WAS when synchronizing the CTI or VDN. The possible causes are that the user name or password is incorrect, or the IP address or port number is incorrect.
100-006	The CTI synchronization fails as the VDN synchronization interface or the CTI synchronization interface is being invoked. Or the VDN synchronization fails as the CTI synchronization interface or the current VDN synchronization interface is being invoked.
100-007	The synchronization fails.
200-001	The VDN does not exist.
200-002	The index IDs entered for querying historical indexes or real-time indexes are invalid.
300-001	The value of AgentId is incorrect.
300-002	Parameters carried in the user login request are incorrect.
300-003	The value of TOKEN is incorrect.
300-004	The value of AgentId or password is incorrect.
300-005	When the agentId parameter is used, the corresponding agent cannot be found.
300-006	An exception occurs during user login authentication.
300-007	The account corresponding to the agent ID is locked.
300-008	The token specified by cmsgateway-token in the HTTP request does not exist.
300-009	The token can match no user information.
300-010	The call center ID and virtual call center ID of the VDN user do not match each other.
300-011	The agent ID and password do not match each other.
300-012	The agent does not have the inspection permission.
300-013	The VDN user does not have the rights to invoke the interface that supports only system administrator authentication.
300-014	The security level is high. When the password needs to be changed upon initial login, the initial login authentication fails.
300-015	Database query fails.
300-016	The agent does not exist under the VDN.
300-017	The inspector group name already exists.
300-018	The inspector group name cannot be empty.
300-019	The inspector group does not exist.
300-020	The invoker does not have the CMS service administrator permission.

Parent topic: [Appendix](#)

WAS Synchronization Data Tables

Table 1 Agent information table T_CMSGW_WAS_AGENT

Field	Data Type	Description
CCID	VARCHAR2	Indicates the contact center ID.
VDNID	VARCHAR2	Indicates the VDN ID.
AGENTNO	VARCHAR2	Indicates the work ID of an agent.
AGENTNAME	VARCHAR2	Indicates the name of an agent.
SKILLGROUPID	VARCHAR2	Indicates a group of skill group IDs. Multiple skill group IDs are separated from each other using a semicolon (;).
SKILLID	VARCHAR2	Indicates a group of skill IDs. Multiple skill IDs are separated from each other using a semicolon (;).
GROUPID	VARCHAR2	Indicates the ID of an agent group.
ROLEID	VARCHAR2	Indicates the role ID. The options are as follows: 2: configuration administrator 3: inspector 4: common agent 5: report administrator

Table 2 Called configuration information table T_CMSGW_WAS_CALLED

Field	Data Type	Description
CCID	VARCHAR2	Indicates the contact center ID.
VDNID	VARCHAR2	Indicates the VDN ID.
ACCESSCODE	VARCHAR2	Indicates the access code.
SUBCODE	VARCHAR2	Indicates the subsequent access code.
DEVICETYPE	VARCHAR2	Indicates the device type. For details, see Device Types .
DEVICENAME	VARCHAR2	Indicates the device name.
DEVICENO	VARCHAR2	Indicates the device ID.
CLIENTLEVEL	VARCHAR2	Indicates the customer level.

Table 3 Agent group information table T_CMSGW_WAS_GROUP

Field	Data Type	Description
CCID	VARCHAR2	Indicates the contact center ID.
VDNID	VARCHAR2	Indicates the VDN ID.
GROUPID	VARCHAR2	Indicates the ID of an agent group.
GROUPNAME	VARCHAR2	Indicates the name of an agent group.
MONITORID	VARCHAR2	Indicates the work ID of a supervisor.

Table 4 Agent resting reason information table T_CMSGW_WAS_REST_REASON

Field	Data Type	Description
CCID	VARCHAR2	Indicates the contact center ID.
VDNID	VARCHAR2	Indicates the VDN ID.
REASON_CODE	VARCHAR2	Indicates the code of a resting reason.
REASON_INFO	VARCHAR2	Indicates the description of the resting reason.

Table 5 Service type information table T_CMSGW_WAS_SERVICE_TYPE

Field	Data Type	Description
CCID	VARCHAR2	Indicates the contact center ID.
VDNID	VARCHAR2	Indicates the VDN ID.
SERVICEID	VARCHAR2	Indicates the ID of a service type.
SERVICENAME	VARCHAR2	Indicates the name of the service type.

Table 6 Skill queue information table T_CMSGW_WAS_SKILL

Field	Data Type	Description
CCID	VARCHAR2	Indicates the contact center ID.
VDNID	VARCHAR2	Indicates the VDN ID.

Field	Data Type	Description
SKILLID	VARCHAR2	Indicates the ID of a skill queue.
SKILLNAME	VARCHAR2	Indicates the name of the skill queue.
REALFLAG	VARCHAR2	Indicates whether it is in a real queue. The options are as follows: 1 : real queue 0 : virtual queue
SERVICEID	VARCHAR2	Indicates the ID of a service type.
MEDIATYPE	VARCHAR2	Indicates the media type. For details, see Media Types .

Table 7 Skill group information table T_CMSGW_WAS_SKILLGROUP

Field	Data Type	Description
CCID	VARCHAR2	Indicates the contact center ID.
VDNID	VARCHAR2	Indicates the VDN ID.
SKILLGROUPID	VARCHAR2	Indicates the ID of a skill group.
SKILLGROUPNAME	VARCHAR2	Indicates the name of the skill group.
SKILLS	VARCHAR2	Indicates a group of skill IDs. Multiple skill IDs are separated from each other using a semicolon (;).

Table 8 VDN information table T_CMSGW_WAS_VDN

Field	Data Type	Description
CCID	VARCHAR2	Indicates the contact center ID.
VDNID	VARCHAR2	Indicates the VDN ID.
VDNNAME	VARCHAR2	Indicates the VDN name.

Table 9 Synchronization task information table T_CMSGW_WAS_SYN_TASK

Field	Data Type	Description
TASK_TYPE	NUMBER	Indicates the synchronization task type. The options are as follows: 0 : CTI synchronization task 1 : VDN synchronization task
TASK_OBJECT_ID	VARCHAR2	Indicates the synchronization object. If TASK_TYPE is set to 1 , this parameter indicates the ID of a VDN.
TASK_STATUS	NUMBER	Indicates the status of the synchronization task. For details, see WAS Synchronization Status .
START_TIME	DATE	Indicates the start time of the synchronization task.
END_TIME	DATE	Indicates the end time of the synchronization task.
VERSION	NUMBER	Indicates the version information.
CLUSTER_ID	VARCHAR2	Indicates the cluster ID of the CMS Gateway that performs the synchronization task.
CLUSTER_NAME	VARCHAR2	Indicates the cluster name of the CMS Gateway that performs the synchronization task.

Parent topic: [Appendix](#)

WAS Synchronization Status

Table 1 WAS synchronization status description

Value	Description
0	The synchronization is in the initial state.
1	The synchronization is in progress.
2	The synchronization succeeds.
3	The synchronization fails.

Parent topic: [Appendix](#)

Media Types

Table 1 Media types

Value	Description
1	Text chat
2	Click to dial
3	Escorted browsing and form sharing
4	Callback request call
5	Common voice call
6	Email call
7	Fax call
8	IP video call (H.323)
9	Electronic whiteboard
10	Application sharing
11	File transfer
12	2B+D ISDN video call
13	6B+D ISDN video call
14	OPS call
15	Predictive outgoing call
16	Previewed outgoing call
17	Message media
18	Video click to dial
19	Common video call
20	Web message leaving call

Parent topic: [Appendix](#)

Device Types

Table 1 Device types

Value	Description
0	None
1	Skill queue
2	Agent
3	IVR
4	Conference site resource
5	Paired calls
6	Agent queue
7	Route script
8	Common phone
9	Agent private queue
10	Network call shared device
11	Network agent

Parent topic: [Appendix](#)

Historical Monitoring Indexes

[Agent](#)

[Skill](#)

[IVR](#)

[VDN](#)

[Return Result of the Daily Statistics About the Trend Traffic at an Interval of 15, 30, or 60 Minutes](#)

Parent topic: [Appendix](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Table 1 Daily statistics about agent activities

Index	Index Description	Data Type
IDX_04_02_001	Indicates the times that the agent signs in.	string
IDX_04_02_002	Indicates the duration that the agent signs in.	string
IDX_04_02_003	Indicates the number of incoming calls.	string
IDX_04_02_004	Indicates the duration of incoming calls.	string
IDX_04_02_005	Indicates the average duration of incoming calls.	string
IDX_04_02_006	Indicates the number of outgoing calls.	string
IDX_04_02_007	Indicates the duration of outgoing calls.	string
IDX_04_02_008	Indicates the average duration of outgoing calls.	string
IDX_04_02_009	Indicates the times that the agent is in the wrap-up state.	string
IDX_04_02_010	Indicates the duration that the agent is in the wrap-up state.	string
IDX_04_02_011	Indicates the average duration that the agent is in the wrap-up state.	string
IDX_04_02_012	Indicates the times that the agent rests.	string
IDX_04_02_013	Indicates the duration that the agent rests.	string
IDX_04_02_014	Indicates the average duration that the agent rests.	string
IDX_04_02_015	Indicates the times that the agent is on hold.	string
IDX_04_02_016	Indicates the duration that the agent is on hold.	string
IDX_04_02_017	Indicates the average duration that the agent is on hold.	string
IDX_04_02_018	Indicates the times that the agent is in the busy state.	string
IDX_04_02_019	Indicates the duration that the agent is in the busy state.	string
IDX_04_02_020	Indicates the average duration that the agent is in the busy state.	string
IDX_04_02_021	Indicates the duration that the agent answers calls.	string
IDX_04_02_022	Indicates the duration that the agent is idle.	string
IDX_04_02_023	Indicates the times of internal transfer.	string
IDX_04_02_024	Indicates the times of transfer-out.	string
IDX_04_02_025	Indicates the number of calls that are blocked and then transferred to IVR calls.	string
IDX_04_02_026	Indicates the number of third-party calls.	string
IDX_04_02_027	Indicates the number of internal calls.	string
IDX_04_02_028	Indicates the times of internal help.	string

The following provides an example of the return result for the query of the daily statistics about agent activities for the agent work ID of 291:

```
{
  "message": "",
  "retcode": "0",
  "result": [
    {
      "id": "291",
      "idxs": [
        {
          "id": "IDX_04_02_001",
          "val": "1",
          "id": "IDX_04_02_002",
          "val": "10771",
          "id": "IDX_04_02_003",
          "val": "1",
          "id": "IDX_04_02_004",
          "val": "0",
          "id": "IDX_04_02_005",
          "val": "4",
          "id": "IDX_04_02_006",
          "val": "1",
          "id": "IDX_04_02_007",
          "val": "0",
          "id": "IDX_04_02_008",
          "val": "12",
          "id": "IDX_04_02_009",
          "val": "0",
          "id": "IDX_04_02_010",
          "val": "0",
          "id": "IDX_04_02_011",
          "val": "0",
          "id": "IDX_04_02_012",
          "val": "0",
          "id": "IDX_04_02_013",
          "val": "0",
          "id": "IDX_04_02_014",
          "val": "0",
          "id": "IDX_04_02_015",
          "val": "0",
          "id": "IDX_04_02_016",
          "val": "0",
          "id": "IDX_04_02_017",
          "val": "0",
          "id": "IDX_04_02_018",
          "val": "1",
          "id": "IDX_04_02_019",
          "val": "12",
          "id": "IDX_04_02_020",
          "val": "12",
          "id": "IDX_04_02_021",
          "val": "0",
          "id": "IDX_04_02_022",
          "val": "10759.0",
          "id": "IDX_04_02_023",
          "val": "0",
          "id": "IDX_04_02_024",
          "val": "0",
          "id": "IDX_04_02_025",
          "val": "0",
          "id": "IDX_04_02_026",
          "val": "0",
          "id": "IDX_04_02_027",
          "val": "0",
          "id": "IDX_04_02_028",
          "val": "0"
        }
      ]
    }
  ]
}
```

Table 2 Daily statistics about the agent login and logout conditions

Index	Index Description	Data Type	Index Value Description
IDX_04_03_001	Indicates the daily statistics about the agent sign-in and sign-out conditions.	array	For the index value description of IDX_04_03_001 , see Table 3 .

The following provides an example of the return result for the query of the daily statistics about the agent sign-in and sign-out conditions for the agent work ID of 291:

```
{
  "message": "",
  "retcode": "0",
  "result": [
    {
      "id": "291",
      "idxs": [
        {
          "id": "IDX_04_03_001",
          "val": [
            {
              "inTime": "2016-01-28 02:27:18",
              "outTime": "2016-01-28 02:27:18",
              "duration": "14399"
            }
          ]
        }
      ]
    }
  ]
}
```

Table 3 Agent sign-in and sign-out conditions at a time

Field	Data Type	Description
inTime	string	Indicates the time when the agent signs in to the system. The value is in the format of YYYY-MM-DD HH:MM:SS.
outTime	string	Indicates the time when the agent signs out of the system. The value is in the format of YYYY-MM-DD HH:MM:SS.
duration	string	Indicates the duration that the agent signs in.

Table 4 Agent traffic statistics

Index	Index Description	Data Type
IDX_04_04_001	Indicates the number of requests.	string
IDX_04_04_002	Indicates the number of calls.	string
IDX_04_04_003	Indicates the number of call losses.	string
IDX_04_04_004	Indicates the call completion rate.	string
IDX_04_04_005	Indicates the number of calls that ring and wait to be answered.	string
IDX_04_04_006	Indicates the number of calls that ring but are not answered.	string
IDX_04_04_007	Indicates the number of calls that wait for a long time but are not answered.	string
IDX_04_04_008	Indicates the number of calls that are hung up after being answered.	string
IDX_04_04_009	Indicates the average duration that the agent answers calls.	string
IDX_04_04_010	Indicates the average call duration.	string
IDX_04_04_011	Indicates the longest call duration.	string
IDX_04_04_012	Indicates the shortest call duration.	string

The following provides an example of the return result for the query of the agent traffic statistics for the agent work ID of 291:

```
{
  "message": "",
  "retcode": "0",
  "result": [
    {
      "id": "291",
      "idxs": [
        {
          "id": "IDX_04_04_001",
          "val": "2"
        },
        {
          "id": "IDX_04_04_002",
          "val": "1"
        },
        {
          "id": "IDX_04_04_003",
          "val": "1"
        },
        {
          "id": "IDX_04_04_004",
          "val": "50.00"
        },
        {
          "id": "IDX_04_04_005",
          "val": "2"
        },
        {
          "id": "IDX_04_04_006",
          "val": "1"
        },
        {
          "id": "IDX_04_04_007",
          "val": "0"
        },
        {
          "id": "IDX_04_04_008",
          "val": "0"
        },
        {
          "id": "IDX_04_04_009",
          "val": "4"
        },
        {
          "id": "IDX_04_04_010",
          "val": "4"
        },
        {
          "id": "IDX_04_04_011",
          "val": "4"
        },
        {
          "id": "IDX_04_04_012",
          "val": "4"
        }
      ]
    }
  ]
}
```

Table 5 Agent multimedia service statistics

Index	Index Description	Data Type
IDX_04_07_001	Indicates the number of requests.	string
IDX_04_07_002	Indicates the number of successful calls.	string
IDX_04_07_003	Indicates the call duration.	string

The following provides an example of the return result for the query of the agent multimedia service statistics for the agent work ID of 291:

```
{
  "message": "",
  "retcode": "0",
  "result": [
    {
      "id": "291",
      "idxs": [
        {
          "id": "IDX_04_07_001",
          "val": "2"
        },
        {
          "id": "IDX_04_07_002",
          "val": "2"
        },
        {
          "id": "IDX_04_07_003",
          "val": "200"
        }
      ]
    }
  ]
}
```

Parent topic: [Historical Monitoring Indexes](#)

Skill

Table 1 Daily accumulated statistics about calls

Index	Index Description	Data Type	Index Value Description
IDX_03_04_001	Indicates the number of call requests in skill queues.	string	-
IDX_03_04_002	Indicates the number of calls.	string	-
IDX_03_04_003	Indicates the number of call losses.	string	-
IDX_03_04_004	Indicates the number of queuing calls that are disconnected.	string	-
IDX_03_04_005	Indicates the number of calls that are hung up by agents.	string	-
IDX_03_04_006	Indicates the number of calls that are dropped by users.	string	Including the number of queuing calls and the number of ringing calls that are actively dropped by users.
IDX_03_04_007	Indicates the number of calls that are interrupted by the platform.	string	-
IDX_03_04_008	Indicates the number of calls that are waiting to be answered.	string	-
IDX_03_04_009	Indicates the number of calls that are transferred to other queues due to overflows.	string	-
IDX_03_04_010	Indicates the number of calls that are transferred to other agents due to overflows.	string	-

The following provides an example of the return result for the query of the daily accumulated statistics about calls for the skill queue ID of 25:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "25",
    "idxs": {
      "id": "IDX_03_04_001", "val": "3"},
      {"id": "IDX_03_04_002", "val": "1"},
      {"id": "IDX_03_04_003", "val": "2"},
      {"id": "IDX_03_04_004", "val": "0"},
      {"id": "IDX_03_04_005", "val": "0"},
      {"id": "IDX_03_04_006", "val": "1"},
      {"id": "IDX_03_04_007", "val": "1"},
      {"id": "IDX_03_04_008", "val": "1"},
      {"id": "IDX_03_04_009", "val": "0"},
      {"id": "IDX_03_04_010", "val": "0"}
    }
  }
}
```

Table 2 Daily accumulated statistics about the calling rate

Index	Index Description	Data Type
IDX_03_05_001	Indicates the call completion rate.	string
IDX_03_05_002	Indicates the call loss rate.	string
IDX_03_05_003	Indicates the call connection rate.	string

The following provides an example of the return result for the query of the daily accumulated statistics about the calling rate for the skill queue ID of 25:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "25",
    "idxs": {
      "id": "IDX_03_05_001", "val": "33.33"},
      {"id": "IDX_03_05_002", "val": "66.67"},
      {"id": "IDX_03_05_003", "val": "50.00"}
    }
  }
}
```

Table 3 Daily accumulated statistics about the average values of calls

Index	Index Description	Data Type
IDX_03_06_001	Indicates the average waiting time of queuing calls.	string
IDX_03_06_002	Indicates the average waiting time of queuing lost calls.	string
IDX_03_06_003	Indicates the average waiting time before calls are answered.	string
IDX_03_06_004	Indicates the average waiting time before lost calls are answered.	string
IDX_03_06_005	Indicates the average call duration.	string
IDX_03_06_006	Indicates the average waiting time.	string
IDX_03_06_007	Indicates the longest waiting time.	string
IDX_03_06_008	Indicates the shortest waiting time.	string

The following provides an example of the return result for the query of the daily accumulated statistics about the average values of calls for the skill queue ID of 25:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "25",
    "idxs": {
      "id": "IDX_03_06_001", "val": "5"},
      {"id": "IDX_03_06_002", "val": "2"},
      {"id": "IDX_03_06_003", "val": "7"},
      {"id": "IDX_03_06_004", "val": "0"},
      {"id": "IDX_03_06_005", "val": "4"},
      {"id": "IDX_03_06_006", "val": "5"},
      {"id": "IDX_03_06_007", "val": "12"},
      {"id": "IDX_03_06_008", "val": "0"}
    }
  }
}
```

Table 4 Daily statistics about the timeout transfer in 24 hours

Index	Index Description	Data Type
IDX_03_07_003	Indicates the number of calls that are transferred from one queue to another due to a queuing timeout.	string
IDX_03_07_004	Indicates the number of calls that are transferred from one agent to another due to a queuing timeout.	string

The following provides an example of the return result for the query of the daily statistics about the timeout transfer for the skill queue ID of 25:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "25",
    "idxs": {
      "id": "IDX_03_07_003", "val": "0"},
      {"id": "IDX_03_07_004", "val": "0"}
    }
  }
}
```

Table 5 Daily statistics about the trend traffic at an interval of 15 minutes in 24 hours

Index	Index Description	Data Type	Index Value Description
-------	-------------------	-----------	-------------------------

Index	Index Description	Data Type	Index Value Description
IDX_03_10_001	Indicates the number of call requests in skill queues.	map	For details, see Return Result of the Daily Statistics About the Trend Traffic at an Interval of 15, 30, or 60 Minutes . This also applies to the following indexes.
IDX_03_10_002	Indicates the number of calls.	map	-
IDX_03_10_003	Indicates the number of call losses.	map	-
IDX_03_10_004	Indicates the number of queuing calls that are disconnected.	map	-
IDX_03_10_005	Indicates the number of calls that are hung up by agents after being answered.	map	-
IDX_03_10_006	Indicates the number of calls that are dropped by users.	map	Including the number of queuing calls and the number of ringing calls that are actively dropped by users.
IDX_03_10_007	Indicates the number of calls that are interrupted by the platform.	map	-
IDX_03_10_008	Indicates the number of calls that are waiting to be answered.	map	-
IDX_03_10_009	Indicates the number of calls that are transferred to other queues due to overflows.	map	-
IDX_03_10_010	Indicates the number of calls that are transferred to other agents due to overflows.	map	-
IDX_03_10_011	Indicates the call completion rate.	map	-
IDX_03_10_012	Indicates the call loss rate.	map	-
IDX_03_10_013	Indicates the call connection rate.	map	-
IDX_03_10_014	Indicates the average waiting time of queuing calls.	map	-
IDX_03_10_015	Indicates the average waiting time of queuing lost calls.	map	-
IDX_03_10_016	Indicates the average waiting time before calls are answered.	map	-
IDX_03_10_017	Indicates the average waiting time before lost calls are answered.	map	-
IDX_03_10_018	Indicates the average call duration.	map	-
IDX_03_10_019	Indicates the average waiting time.	map	-
IDX_03_10_020	Indicates the longest waiting time.	map	-
IDX_03_10_021	Indicates the shortest waiting time.	map	-
IDX_03_10_024	Indicates the number of calls that are transferred from one queue to another due to a queuing timeout.	map	-
IDX_03_10_025	Indicates the number of calls that are transferred from one agent to another due to a queuing timeout.	map	-

The following provides an example of the return result for the query of the daily statistics about the trend traffic at an interval of 15 minutes for the skill queue ID of 25:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "25",
    "idxs": {
      "IDX_03_10_001": {
        "val": {
          "2016-01-28 06:15:00": "1",
          "2016-01-28 03:15:00": "3"
        }
      },
      "IDX_03_10_002": {
        "val": {
          "2016-01-28 06:15:00": "1",
          "2016-01-28 03:15:00": "1"
        }
      },
      "IDX_03_10_003": {
        "val": {
          "2016-01-28 06:15:00": "0",
          "2016-01-28 03:15:00": "2"
        }
      },
      "IDX_03_10_004": {
        "val": {
          "2016-01-28 06:15:00": "0",
          "2016-01-28 03:15:00": "0"
        }
      },
      "IDX_03_10_005": {
        "val": {
          "2016-01-28 06:15:00": "0",
          "2016-01-28 03:15:00": "0"
        }
      },
      "IDX_03_10_006": {
        "val": {
          "2016-01-28 06:15:00": "0",
          "2016-01-28 03:15:00": "1"
        }
      },
      "IDX_03_10_007": {
        "val": {
          "2016-01-28 06:15:00": "0",
          "2016-01-28 03:15:00": "1"
        }
      },
      "IDX_03_10_008": {
        "val": {
          "2016-01-28 06:15:00": "0",
          "2016-01-28 03:15:00": "0"
        }
      },
      "IDX_03_10_009": {
        "val": {
          "2016-01-28 06:15:00": "0",
          "2016-01-28 03:15:00": "0"
        }
      },
      "IDX_03_10_010": {
        "val": {
          "2016-01-28 06:15:00": "0",
          "2016-01-28 03:15:00": "0"
        }
      },
      "IDX_03_10_011": {
        "val": {
          "2016-01-28 06:15:00": "100.00",
          "2016-01-28 03:15:00": "33.33"
        }
      },
      "IDX_03_10_012": {
        "val": {
          "2016-01-28 06:15:00": "0.00",
          "2016-01-28 03:15:00": "66.67"
        }
      },
      "IDX_03_10_013": {
        "val": {
          "2016-01-28 06:15:00": "100.00",
          "2016-01-28 03:15:00": "50.00"
        }
      },
      "IDX_03_10_014": {
        "val": {
          "2016-01-28 06:15:00": "0",
          "2016-01-28 03:15:00": "5"
        }
      },
      "IDX_03_10_015": {
        "val": {
          "2016-01-28 06:15:00": "0",
          "2016-01-28 03:15:00": "0"
        }
      },
      "IDX_03_10_016": {
        "val": {
          "2016-01-28 06:15:00": "3",
          "2016-01-28 03:15:00": "7"
        }
      },
      "IDX_03_10_017": {
        "val": {
          "2016-01-28 06:15:00": "0",
          "2016-01-28 03:15:00": "2"
        }
      },
      "IDX_03_10_018": {
        "val": {
          "2016-01-28 06:15:00": "913",
          "2016-01-28 03:15:00": "4"
        }
      },
      "IDX_03_10_019": {
        "val": {
          "2016-01-28 06:15:00": "3",
          "2016-01-28 03:15:00": "5"
        }
      },
      "IDX_03_10_020": {
        "val": {
          "2016-01-28 06:15:00": "3",
          "2016-01-28 03:15:00": "3"
        }
      },
      "IDX_03_10_021": {
        "val": {
          "2016-01-28 06:15:00": "0",
          "2016-01-28 03:15:00": "0"
        }
      },
      "IDX_03_10_024": {
        "val": {
          "2016-01-28 06:15:00": "0",
          "2016-01-28 03:15:00": "0"
        }
      },
      "IDX_03_10_025": {
        "val": {
          "2016-01-28 06:15:00": "0",
          "2016-01-28 03:15:00": "0"
        }
      }
    }
  }
}
```

Table 6 Daily statistics about the trend traffic at an interval of 30 minutes in 24 hours

Index	Index Description	Data Type	Index Value Description
IDX_03_11_001	Indicates the number of call requests in skill queues.	map	-
IDX_03_11_002	Indicates the number of calls.	map	-
IDX_03_11_003	Indicates the number of call losses.	map	-
IDX_03_11_004	Indicates the number of queuing calls that are disconnected.	map	-
IDX_03_11_005	Indicates the number of calls that are hung up by agents after being answered.	map	-

Index	Index Description	Data Type	Index Value Description
IDX_03_11_006	Indicates the number of calls that are dropped by users.	map	Including the number of queuing calls and the number of ringing calls that are actively dropped by users.
IDX_03_11_007	Indicates the number of calls that are interrupted by the platform.	map	-
IDX_03_11_008	Indicates the number of calls that are waiting to be answered.	map	-
IDX_03_11_009	Indicates the number of calls that are transferred to other queues due to overflows.	map	-
IDX_03_11_010	Indicates the number of calls that are transferred to other agents due to overflows.	map	-
IDX_03_11_011	Indicates the call completion rate.	map	-
IDX_03_11_012	Indicates the call loss rate.	map	-
IDX_03_11_013	Indicates the call connection rate.	map	-
IDX_03_11_014	Indicates the average waiting time of queuing calls.	map	-
IDX_03_11_015	Indicates the average waiting time of queuing lost calls.	map	-
IDX_03_11_016	Indicates the average waiting time before calls are answered.	map	-
IDX_03_11_017	Indicates the average waiting time before lost calls are answered.	map	-
IDX_03_11_018	Indicates the average call duration.	map	-
IDX_03_11_019	Indicates the average waiting time.	map	-
IDX_03_11_020	Indicates the longest waiting time.	map	-
IDX_03_11_021	Indicates the shortest waiting time.	map	-
IDX_03_11_024	Indicates the number of calls that are transferred from one queue to another due to a queuing timeout.	map	-
IDX_03_11_025	Indicates the number of calls that are transferred from one agent to another due to a queuing timeout.	map	-

The following provides an example of the return result for the query of the daily statistics about the trend traffic at an interval of 30 minutes for the skill queue ID of 25:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "25",
    "idxs": {
      "IDX_03_11_001": {
        "val": {
          "2016-01-28 03:00:00": "3",
          "2016-01-28 06:00:00": "1"
        },
        "id": "IDX_03_11_002",
        "val": {
          "2016-01-28 03:00:00": "1",
          "2016-01-28 06:00:00": "1"
        },
        "id": "IDX_03_11_003",
        "val": {
          "2016-01-28 03:00:00": "2",
          "2016-01-28 06:00:00": "0"
        },
        "id": "IDX_03_11_004",
        "val": {
          "2016-01-28 03:00:00": "0",
          "2016-01-28 06:00:00": "0"
        },
        "id": "IDX_03_11_005",
        "val": {
          "2016-01-28 03:00:00": "0",
          "2016-01-28 06:00:00": "0"
        },
        "id": "IDX_03_11_006",
        "val": {
          "2016-01-28 03:00:00": "1",
          "2016-01-28 06:00:00": "0"
        },
        "id": "IDX_03_11_007",
        "val": {
          "2016-01-28 03:00:00": "1",
          "2016-01-28 06:00:00": "0"
        },
        "id": "IDX_03_11_008",
        "val": {
          "2016-01-28 03:00:00": "1",
          "2016-01-28 06:00:00": "0"
        },
        "id": "IDX_03_11_009",
        "val": {
          "2016-01-28 03:00:00": "0",
          "2016-01-28 06:00:00": "0"
        },
        "id": "IDX_03_11_010",
        "val": {
          "2016-01-28 03:00:00": "0",
          "2016-01-28 06:00:00": "0"
        },
        "id": "IDX_03_11_011",
        "val": {
          "2016-01-28 03:00:00": "33.33",
          "2016-01-28 06:00:00": "100.00"
        },
        "id": "IDX_03_11_012",
        "val": {
          "2016-01-28 03:00:00": "66.67",
          "2016-01-28 06:00:00": "0.00"
        },
        "id": "IDX_03_11_013",
        "val": {
          "2016-01-28 03:00:00": "50.00",
          "2016-01-28 06:00:00": "100.00"
        },
        "id": "IDX_03_11_014",
        "val": {
          "2016-01-28 03:00:00": "5",
          "2016-01-28 06:00:00": "0"
        },
        "id": "IDX_03_11_015",
        "val": {
          "2016-01-28 03:00:00": "0",
          "2016-01-28 06:00:00": "0"
        },
        "id": "IDX_03_11_016",
        "val": {
          "2016-01-28 03:00:00": "7",
          "2016-01-28 06:00:00": "3"
        },
        "id": "IDX_03_11_017",
        "val": {
          "2016-01-28 03:00:00": "2",
          "2016-01-28 06:00:00": "0"
        },
        "id": "IDX_03_11_018",
        "val": {
          "2016-01-28 03:00:00": "4",
          "2016-01-28 06:00:00": "913"
        },
        "id": "IDX_03_11_019",
        "val": {
          "2016-01-28 03:00:00": "5",
          "2016-01-28 06:00:00": "3"
        },
        "id": "IDX_03_11_020",
        "val": {
          "2016-01-28 03:00:00": "12",
          "2016-01-28 06:00:00": "3"
        },
        "id": "IDX_03_11_021",
        "val": {
          "2016-01-28 03:00:00": "0",
          "2016-01-28 06:00:00": "3"
        },
        "id": "IDX_03_11_024",
        "val": {
          "2016-01-28 03:00:00": "0",
          "2016-01-28 06:00:00": "0"
        },
        "id": "IDX_03_11_025",
        "val": {
          "2016-01-28 03:00:00": "0",
          "2016-01-28 06:00:00": "0"
        }
      }
    }
  }
}
```

Table 7 Daily statistics about the trend traffic at an interval of 60 minutes in 24 hours

Index	Index Description	Data Type	Index Value Description
IDX_03_12_001	Indicates the number of call requests in skill queues.	map	-
IDX_03_12_002	Indicates the number of calls.	map	-
IDX_03_12_003	Indicates the number of call losses.	map	-
IDX_03_12_004	Indicates the number of queuing calls that are disconnected.	map	-
IDX_03_12_005	Indicates the number of calls that are hung up by agents after being answered.	map	-
IDX_03_12_006	Indicates the number of calls that are dropped by users.	map	Including the number of queuing calls and the number of ringing calls that are actively dropped by users.
IDX_03_12_007	Indicates the number of calls that are interrupted by the platform.	map	-
IDX_03_12_008	Indicates the number of calls that are waiting to be answered.	map	-
IDX_03_12_009	Indicates the number of calls that are transferred to other queues due to overflows.	map	-
IDX_03_12_010	Indicates the number of calls that are transferred to other agents due to	map	-

Index	Index Description	Data Type	Index Value Description
	overflows.		
IDX_03_12_011	Indicates the call completion rate.	map	-
IDX_03_12_012	Indicates the call loss rate.	map	-
IDX_03_12_013	Indicates the call connection rate.	map	-
IDX_03_12_014	Indicates the average waiting time of queuing calls.	map	-
IDX_03_12_015	Indicates the average waiting time of queuing lost calls.	map	-
IDX_03_12_016	Indicates the average waiting time before calls are answered.	map	-
IDX_03_12_017	Indicates the average waiting time before lost calls are answered.	map	-
IDX_03_12_018	Indicates the average call duration.	map	-
IDX_03_12_019	Indicates the average waiting time.	map	-
IDX_03_12_020	Indicates the longest waiting time.	map	-
IDX_03_12_021	Indicates the shortest waiting time.	map	-
IDX_03_12_024	Indicates the number of calls that are transferred from one queue to another due to a queuing timeout.	map	-
IDX_03_12_025	Indicates the number of calls that are transferred from one agent to another due to a queuing timeout.	map	-

The following provides an example of the return result for the query of the daily statistics about the trend traffic at an interval of 60 minutes for the skill queue ID of 25:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "25",
    "idxs": {
      "id": "IDX_03_12_001", "val": {
        "2016-01-28 03:00:00": "3",
        "2016-01-28 06:00:00": "1"
      },
      "id": "IDX_03_12_002", "val": {
        "2016-01-28 03:00:00": "1",
        "2016-01-28 06:00:00": "1"
      },
      "id": "IDX_03_12_003", "val": {
        "2016-01-28 03:00:00": "2",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_03_12_004", "val": {
        "2016-01-28 03:00:00": "0",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_03_12_005", "val": {
        "2016-01-28 03:00:00": "0",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_03_12_006", "val": {
        "2016-01-28 03:00:00": "1",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_03_12_007", "val": {
        "2016-01-28 03:00:00": "1",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_03_12_008", "val": {
        "2016-01-28 03:00:00": "1",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_03_12_009", "val": {
        "2016-01-28 03:00:00": "0",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_03_12_010", "val": {
        "2016-01-28 03:00:00": "0",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_03_12_011", "val": {
        "2016-01-28 03:00:00": "33.33",
        "2016-01-28 06:00:00": "100.00"
      },
      "id": "IDX_03_12_012", "val": {
        "2016-01-28 03:00:00": "66.67",
        "2016-01-28 06:00:00": "0.00"
      },
      "id": "IDX_03_12_013", "val": {
        "2016-01-28 03:00:00": "50.00",
        "2016-01-28 06:00:00": "100.00"
      },
      "id": "IDX_03_12_014", "val": {
        "2016-01-28 03:00:00": "5",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_03_12_015", "val": {
        "2016-01-28 03:00:00": "0",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_03_12_016", "val": {
        "2016-01-28 03:00:00": "7",
        "2016-01-28 06:00:00": "3"
      },
      "id": "IDX_03_12_017", "val": {
        "2016-01-28 03:00:00": "2",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_03_12_018", "val": {
        "2016-01-28 03:00:00": "4",
        "2016-01-28 06:00:00": "913"
      },
      "id": "IDX_03_12_019", "val": {
        "2016-01-28 03:00:00": "5",
        "2016-01-28 06:00:00": "3"
      },
      "id": "IDX_03_12_020", "val": {
        "2016-01-28 03:00:00": "12",
        "2016-01-28 06:00:00": "3"
      },
      "id": "IDX_03_12_021", "val": {
        "2016-01-28 03:00:00": "0",
        "2016-01-28 06:00:00": "3"
      },
      "id": "IDX_03_12_024", "val": {
        "2016-01-28 03:00:00": "0",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_03_12_025", "val": {
        "2016-01-28 03:00:00": "0",
        "2016-01-28 06:00:00": "0"
      }
    }
  }
}
```

Table 8 Statistics about the number of call requests that are connected within n seconds in skill queues

Index	Index Description	Data Type
IDX_03_09_001	Indicates the number of call requests that are connected within 5s.	string
IDX_03_09_002	Indicates the number of call requests that are connected within 10s.	string
IDX_03_09_003	Indicates the number of call requests that are connected within 15s.	string
IDX_03_09_004	Indicates the number of call requests that are connected within 20s.	string
IDX_03_09_005	Indicates the number of call requests that are connected within 25s.	string
IDX_03_09_006	Indicates the number of call requests that are connected within 30s.	string
IDX_03_09_007	Indicates the number of call requests that are connected within 35s.	string
IDX_03_09_008	Indicates the number of call requests that are connected within 40s.	string
IDX_03_09_009	Indicates the number of call requests that are connected within 45s.	string
IDX_03_09_010	Indicates the number of call requests that are connected within 50s.	string

The following provides an example of the return result for the query of the statistics about the number of call requests that are connected within n seconds for the skill queue ID of 25:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "25",
    "idxs": {
      "id": "IDX_03_09_001", "val": "1",
      "id": "IDX_03_09_002", "val": "1",
      "id": "IDX_03_09_003", "val": "2",
      "id": "IDX_03_09_004", "val": "2",
      "id": "IDX_03_09_005", "val": "2",
      "id": "IDX_03_09_006", "val": "2",
      "id": "IDX_03_09_007", "val": "2",
      "id": "IDX_03_09_008", "val": "2",
      "id": "IDX_03_09_009", "val": "2",
      "id": "IDX_03_09_010", "val": "2"
    }
  }
}
```

Table 9 Statistics about the number of call requests that are dropped within n seconds in skill queues

Index	Index Description	Data Type
IDX_03_09_011	Indicates the number of call requests that are dropped within 5s.	string

Index	Index Description	Data Type
IDX_03_09_012	Indicates the number of call requests that are dropped within 10s.	string
IDX_03_09_013	Indicates the number of call requests that are dropped within 15s.	string
IDX_03_09_014	Indicates the number of call requests that are dropped within 20s.	string
IDX_03_09_015	Indicates the number of call requests that are dropped within 25s.	string
IDX_03_09_016	Indicates the number of call requests that are dropped within 30s.	string
IDX_03_09_017	Indicates the number of call requests that are dropped within 35s.	string
IDX_03_09_018	Indicates the number of call requests that are dropped within 40s.	string
IDX_03_09_019	Indicates the number of call requests that are dropped within 45s.	string
IDX_03_09_020	Indicates the number of call requests that are dropped within 50s.	string

The following provides an example of the return result for the query of the statistics about the number of call requests that are dropped within n seconds for the skill queue ID of 25:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "25",
    "idxs": [
      { "id": "IDX_03_09_011", "val": "2" },
      { "id": "IDX_03_09_012", "val": "2" },
      { "id": "IDX_03_09_013", "val": "2" },
      { "id": "IDX_03_09_014", "val": "2" },
      { "id": "IDX_03_09_015", "val": "2" },
      { "id": "IDX_03_09_016", "val": "2" },
      { "id": "IDX_03_09_017", "val": "2" },
      { "id": "IDX_03_09_018", "val": "2" },
      { "id": "IDX_03_09_019", "val": "2" },
      { "id": "IDX_03_09_020", "val": "2" }
    ]
  }
}
```

Table 10 Statistics about the number of call requests that are connected beyond n seconds in skill queues

Index	Index Description	Data Type
IDX_03_09_021	Indicates the number of call requests that are connected beyond 5s.	string
IDX_03_09_022	Indicates the number of call requests that are connected beyond 10s.	string
IDX_03_09_023	Indicates the number of call requests that are connected beyond 15s.	string
IDX_03_09_024	Indicates the number of call requests that are connected beyond 20s.	string
IDX_03_09_025	Indicates the number of call requests that are connected beyond 25s.	string
IDX_03_09_026	Indicates the number of call requests that are connected beyond 30s.	string
IDX_03_09_027	Indicates the number of call requests that are connected beyond 35s.	string
IDX_03_09_028	Indicates the number of call requests that are connected beyond 40s.	string
IDX_03_09_029	Indicates the number of call requests that are connected beyond 45s.	string
IDX_03_09_030	Indicates the number of call requests that are connected beyond 50s.	string

The following provides an example of the return result for the query of the statistics about the number of call requests that are connected beyond n seconds for the skill queue ID of 25:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "25",
    "idxs": [
      { "id": "IDX_03_09_021", "val": "1" },
      { "id": "IDX_03_09_022", "val": "1" },
      { "id": "IDX_03_09_023", "val": "0" },
      { "id": "IDX_03_09_024", "val": "0" },
      { "id": "IDX_03_09_025", "val": "0" },
      { "id": "IDX_03_09_026", "val": "0" },
      { "id": "IDX_03_09_027", "val": "0" },
      { "id": "IDX_03_09_028", "val": "0" },
      { "id": "IDX_03_09_029", "val": "0" },
      { "id": "IDX_03_09_030", "val": "0" }
    ]
  }
}
```

Table 11 Statistics about the number of call requests that are dropped beyond n seconds in skill queues

Index	Index Description	Data Type
IDX_03_09_031	Indicates the number of call requests that are dropped beyond 5s.	string
IDX_03_09_032	Indicates the number of call requests that are dropped beyond 10s.	string
IDX_03_09_033	Indicates the number of call requests that are dropped beyond 15s.	string
IDX_03_09_034	Indicates the number of call requests that are dropped beyond 20s.	string
IDX_03_09_035	Indicates the number of call requests that are dropped beyond 25s.	string
IDX_03_09_036	Indicates the number of call requests that are dropped beyond 30s.	string
IDX_03_09_037	Indicates the number of call requests that are dropped beyond 35s.	string
IDX_03_09_038	Indicates the number of call requests that are dropped beyond 40s.	string
IDX_03_09_039	Indicates the number of call requests that are dropped beyond 45s.	string
IDX_03_09_040	Indicates the number of call requests that are dropped beyond 50s.	string

The following provides an example of the return result for the query of the statistics about the number of call requests that are dropped beyond n seconds for the skill queue ID of 25:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "25",
    "idxs": {
      "id": "IDX_03_09_031", "val": "0",
      "id": "IDX_03_09_032", "val": "0",
      "id": "IDX_03_09_033", "val": "0",
      "id": "IDX_03_09_034", "val": "0",
      "id": "IDX_03_09_035", "val": "0",
      "id": "IDX_03_09_036", "val": "0",
      "id": "IDX_03_09_037", "val": "0",
      "id": "IDX_03_09_038", "val": "0",
      "id": "IDX_03_09_039", "val": "0",
      "id": "IDX_03_09_040", "val": "0"
    }
  }
}
```

Table 12 Statistics about the rate of call connection within n seconds in skill queues

Index	Index Description	Data Type
IDX_03_09_041	Indicates the rate of call connection within 5s.	string
IDX_03_09_042	Indicates the rate of call connection within 10s.	string
IDX_03_09_043	Indicates the rate of call connection within 15s.	string
IDX_03_09_044	Indicates the rate of call connection within 20s.	string
IDX_03_09_045	Indicates the rate of call connection within 25s.	string
IDX_03_09_046	Indicates the rate of call connection within 30s.	string
IDX_03_09_047	Indicates the rate of call connection within 35s.	string
IDX_03_09_048	Indicates the rate of call connection within 40s.	string
IDX_03_09_049	Indicates the rate of call connection within 45s.	string
IDX_03_09_050	Indicates the rate of call connection within 50s.	string

The following provides an example of the return result for the query of the statistics about the rate of call connection within n seconds for the skill queue ID of 25:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "25",
    "idxs": {
      "id": "IDX_03_09_041", "val": "25.00",
      "id": "IDX_03_09_042", "val": "25.00",
      "id": "IDX_03_09_043", "val": "50.00",
      "id": "IDX_03_09_044", "val": "50.00",
      "id": "IDX_03_09_045", "val": "50.00",
      "id": "IDX_03_09_046", "val": "50.00",
      "id": "IDX_03_09_047", "val": "50.00",
      "id": "IDX_03_09_048", "val": "50.00",
      "id": "IDX_03_09_049", "val": "50.00",
      "id": "IDX_03_09_050", "val": "50.00"
    }
  }
}
```

Table 13 Statistics about the rate of call drop within n seconds in skill queues

Index	Index Description	Data Type
IDX_03_09_051	Indicates the rate of call drop within 5s.	string
IDX_03_09_052	Indicates the rate of call drop within 10s.	string
IDX_03_09_053	Indicates the rate of call drop within 15s.	string
IDX_03_09_054	Indicates the rate of call drop within 20s.	string
IDX_03_09_055	Indicates the rate of call drop within 25s.	string
IDX_03_09_056	Indicates the rate of call drop within 30s.	string
IDX_03_09_057	Indicates the rate of call drop within 35s.	string
IDX_03_09_058	Indicates the rate of call drop within 40s.	string
IDX_03_09_059	Indicates the rate of call drop within 45s.	string
IDX_03_09_060	Indicates the rate of call drop within 50s.	string

The following provides an example of the return result for the query of the statistics about the rate of call drop within n seconds for the skill queue ID of 25:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "25",
    "idxs": {
      "id": "IDX_03_09_051", "val": "50.00",
      "id": "IDX_03_09_052", "val": "50.00",
      "id": "IDX_03_09_053", "val": "50.00",
      "id": "IDX_03_09_054", "val": "50.00",
      "id": "IDX_03_09_055", "val": "50.00",
      "id": "IDX_03_09_056", "val": "50.00",
      "id": "IDX_03_09_057", "val": "50.00",
      "id": "IDX_03_09_058", "val": "50.00",
      "id": "IDX_03_09_059", "val": "50.00",
      "id": "IDX_03_09_060", "val": "50.00"
    }
  }
}
```

Table 14 Historical monitoring statistics about multimedia services

Index	Index Description	Data Type
IDX_03_13_001	Indicates the number of requests.	string
IDX_03_13_002	Indicates the number of successful calls.	string
IDX_03_13_003	Indicates the call duration.	string
IDX_03_13_004	Indicates the waiting time in queues.	string
IDX_03_13_005	Indicates the number of queuing failures.	string
IDX_03_13_006	Indicates the number of queuing drops.	string
IDX_03_13_007	Indicates the number of calls that are answered within n seconds.	string

The following provides an example of the return result for the query of the historical monitoring statistics about multimedia services for the skill queue ID of 25:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "1",
    "idxs": {
      "id": "IDX_03_13_001", "val": "10",
      "id": "IDX_03_13_002", "val": "10",
      "id": "IDX_03_13_003", "val": "2445",
      "id": "IDX_03_13_004", "val": "50",
      "id": "IDX_03_13_005", "val": "0",
      "id": "IDX_03_13_006", "val": "0",
      "id": "IDX_03_13_007", "val": "10"
    }
  }
}
```

Parent topic: [Historical Monitoring Indexes](#)

Table 1 Daily statistics about the IVR traffic

Index	Index Description	Data Type
IDX_02_02_001	Indicates the number of requests.	string
IDX_02_02_002	Indicates the number of calls.	string
IDX_02_02_003	Indicates the number of call losses.	string
IDX_02_02_004	Indicates the number of calls transferred out.	string
IDX_02_02_005	Indicates the number of released calls.	string
IDX_02_02_006	Indicates the call completion rate.	string
IDX_02_02_007	Indicates the average call duration.	string

The following provides an example of the return result for the query of the statistics about the current IVR traffic for the service type ID of 17:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "17",
    "idxs": {
      "IDX_02_02_001": "1",
      "IDX_02_02_002": "1",
      "IDX_02_02_003": "0",
      "IDX_02_02_004": "0",
      "IDX_02_02_005": "1",
      "IDX_02_02_006": "100.00",
      "IDX_02_02_007": "4"
    }
  }
}
```

Table 2 Daily statistics about the trend traffic at an interval of 15 minutes in 24 hours

Index	Index Description	Data Type	Index Value Description
IDX_02_03_001	Indicates the number of requests.	map	For details, see Return Result of the Daily Statistics About the Trend Traffic at an Interval of 15, 30, or 60 Minutes . This also applies to the following indexes.
IDX_02_03_002	Indicates the number of calls.	map	-
IDX_02_03_003	Indicates the number of call losses.	map	-
IDX_02_03_004	Indicates the number of calls transferred out.	map	-
IDX_02_03_005	Indicates the number of released calls.	map	-
IDX_02_03_006	Indicates the call completion rate.	map	-
IDX_02_03_007	Indicates the average call duration.	map	-

The following provides an example of the return result for the query of the daily statistics about the trend traffic at an interval of 15 minutes for the service type ID of 17:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "17",
    "idxs": {
      "IDX_02_03_001": {"2016-01-28 06:45:00": "2"},
      "IDX_02_03_002": {"2016-01-28 06:45:00": "1"},
      "IDX_02_03_003": {"2016-01-28 06:45:00": "1"},
      "IDX_02_03_004": {"2016-01-28 06:45:00": "0"},
      "IDX_02_03_005": {"2016-01-28 06:45:00": "2"},
      "IDX_02_03_006": {"2016-01-28 06:45:00": "50.00"},
      "IDX_02_03_007": {"2016-01-28 06:45:00": "4"}
    }
  }
}
```

Table 3 Daily statistics about the trend traffic at an interval of 30 minutes in 24 hours

Index	Index Description	Data Type
IDX_02_04_001	Indicates the number of requests.	map
IDX_02_04_002	Indicates the number of calls.	map
IDX_02_04_003	Indicates the number of call losses.	map
IDX_02_04_004	Indicates the number of calls transferred out.	map
IDX_02_04_005	Indicates the number of released calls.	map
IDX_02_04_006	Indicates the call completion rate.	map
IDX_02_04_007	Indicates the average call duration.	map

The following provides an example of the return result for the query of the daily statistics about the trend traffic at an interval of 30 minutes for the service type ID of 17:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "17",
    "idxs": {
      "IDX_02_04_001": {"2016-01-28 06:30:00": "3"},
      "IDX_02_04_002": {"2016-01-28 06:30:00": "2"},
      "IDX_02_04_003": {"2016-01-28 06:30:00": "1"},
      "IDX_02_04_004": {"2016-01-28 06:30:00": "1"},
      "IDX_02_04_005": {"2016-01-28 06:30:00": "2"},
      "IDX_02_04_006": {"2016-01-28 06:30:00": "66.67"},
      "IDX_02_04_007": {"2016-01-28 06:30:00": "2"}
    }
  }
}
```

Table 4 Daily statistics about the trend traffic at an interval of 60 minutes in 24 hours

Index	Index Description	Data Type
IDX_02_05_001	Indicates the number of requests.	map
IDX_02_05_002	Indicates the number of calls.	map
IDX_02_05_003	Indicates the number of call losses.	map
IDX_02_05_004	Indicates the number of calls transferred out.	map
IDX_02_05_005	Indicates the number of released calls.	map
IDX_02_05_006	Indicates the call completion rate.	map
IDX_02_05_007	Indicates the average call duration.	map

The following provides an example of the return result for the query of the daily statistics about the trend traffic at an interval of 60 minutes for the service type ID of 17:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "17",
    "idxs": {
      "IDX_02_05_001": {"2016-01-28 06:00:00": "3"},
      "IDX_02_05_002": {"2016-01-28 06:00:00": "2"},
      "IDX_02_05_003": {"2016-01-28 06:00:00": "1"},
      "IDX_02_05_004": {"2016-01-28 06:00:00": "1"},
      "IDX_02_05_005": {"2016-01-28 06:00:00": "2"},
      "IDX_02_05_006": {"2016-01-28 06:00:00": "66.67"},
      "IDX_02_05_007": {"2016-01-28 06:00:00": "2"}
    }
  }
}
```


Table 1 Statistics about the trend traffic of calls under a VDN

Index	Index Description	Data Type	Index Value Description
IDX_01_01_001	Indicates the total number of calls at an interval of 15 minutes.	map	= Total number of incoming calls + Total number of outgoing calls For details, see Return Result of the Daily Statistics About the Trend Traffic at an Interval of 15_30_or 60 Minutes . This also applies to the following indexes.
IDX_01_01_002	Indicates the total number of connected calls at an interval of 15 minutes.	map	= Total number of connected incoming calls + Total number of connected outgoing calls
IDX_01_01_003	Indicates the total number of lost calls at an interval of 15 minutes.	map	= Total number of calls – Total number of connected calls
IDX_01_01_004	Indicates the total number of calls at an interval of 30 minutes.	map	= Total number of incoming calls + Total number of outgoing calls
IDX_01_01_005	Indicates the total number of connected calls at an interval of 30 minutes.	map	= Total number of connected incoming calls + Total number of connected outgoing calls
IDX_01_01_006	Indicates the total number of lost calls at an interval of 30 minutes.	map	= Total number of calls – Total number of connected calls
IDX_01_01_007	Indicates the total number of calls at an interval of 60 minutes.	map	= Total number of incoming calls + Total number of outgoing calls
IDX_01_01_008	Indicates the total number of connected calls at an interval of 60 minutes.	map	= Total number of connected incoming calls + Total number of connected outgoing calls
IDX_01_01_009	Indicates the total number of lost calls at an interval of 60 minutes.	map	= Total number of calls – Total number of connected calls

The following provides an example of the return result for the query of the statistics about the trend traffic of calls under a VDN for the VDN ID of 1:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "1",
    "idxs": {
      "id": "IDX_01_01_001",
      "val": {
        "2016-01-28 05:45:00": "1",
        "2016-01-28 06:45:00": "3",
        "2016-01-28 06:15:00": "1",
        "2016-01-28 03:15:00": "2"
      }
    },
    "id": "IDX_01_01_002",
    "val": {
      "2016-01-28 05:45:00": "0",
      "2016-01-28 06:45:00": "1",
      "2016-01-28 06:15:00": "1",
      "2016-01-28 03:15:00": "2"
    },
    "id": "IDX_01_01_003",
    "val": {
      "2016-01-28 05:45:00": "1",
      "2016-01-28 06:45:00": "2",
      "2016-01-28 06:15:00": "0",
      "2016-01-28 03:15:00": "1"
    },
    "id": "IDX_01_01_004",
    "val": {
      "2016-01-28 06:30:00": "3",
      "2016-01-28 05:30:00": "1",
      "2016-01-28 03:00:00": "3",
      "2016-01-28 06:00:00": "1"
    },
    "id": "IDX_01_01_005",
    "val": {
      "2016-01-28 06:30:00": "1",
      "2016-01-28 05:30:00": "2",
      "2016-01-28 06:00:00": "2",
      "2016-01-28 03:00:00": "1"
    },
    "id": "IDX_01_01_006",
    "val": {
      "2016-01-28 06:30:00": "2",
      "2016-01-28 05:30:00": "1",
      "2016-01-28 03:00:00": "1",
      "2016-01-28 06:00:00": "0"
    },
    "id": "IDX_01_01_007",
    "val": {
      "2016-01-28 05:00:00": "1",
      "2016-01-28 03:00:00": "3",
      "2016-01-28 06:00:00": "4"
    },
    "id": "IDX_01_01_008",
    "val": {
      "2016-01-28 05:00:00": "0",
      "2016-01-28 03:00:00": "2",
      "2016-01-28 06:00:00": "2"
    },
    "id": "IDX_01_01_009",
    "val": {
      "2016-01-28 05:00:00": "1",
      "2016-01-28 03:00:00": "1",
      "2016-01-28 06:00:00": "2"
    }
  }
}
```

Table 2 Daily monitoring statistics about incoming calls under a VDN

Index	Index Description	Data Type	Index Value Description
IDX_01_02_001	Indicates the total number of incoming calls.	string	-
IDX_01_02_002	Indicates the total number of connected incoming calls.	string	-
IDX_01_02_003	Indicates the call completion rate of incoming calls.	string	-
IDX_01_02_004	Indicates the number of incoming IVR calls.	string	-
IDX_01_02_005	Indicates the number of connected incoming IVR calls.	string	-
IDX_01_02_006	Indicates the call completion rate of incoming IVR calls.	string	-
IDX_01_02_007	Indicates the number of incoming manual calls.	string	-
IDX_01_02_008	Indicates the number of connected incoming manual calls.	string	-
IDX_01_02_009	Indicates the call completion rate of incoming manual calls.	string	-
IDX_01_02_010	Indicates the average duration that the VDN is occupied by incoming calls.	string	-
IDX_01_02_011	Indicates the number of dropped incoming calls in one day.	string	= Number of incoming calls in one day – Number of answered incoming calls in one day
IDX_01_02_012	Indicates the average call duration.	string	= Total call duration in all skill queues / Total number of calls in all skill queues
IDX_01_02_013	Indicates the average waiting time.	string	= Total waiting time in all skill queues / Total number of call requests in all skill queues

The following provides an example of the return result for the query of the daily monitoring statistics about incoming calls under a VDN for the VDN ID of 1:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "1",
    "idxs": {
      "id": "IDX_01_02_001",
      "val": "7",
      "id": "IDX_01_02_002",
      "val": "3",
      "id": "IDX_01_02_003",
      "val": "42.86",
      "id": "IDX_01_02_004",
      "val": "3",
      "id": "IDX_01_02_005",
      "val": "1",
      "id": "IDX_01_02_006",
      "val": "42.86",
      "id": "IDX_01_02_007",
      "val": "4",
      "id": "IDX_01_02_008",
      "val": "2",
      "id": "IDX_01_02_009",
      "val": "50.00",
      "id": "IDX_01_02_010",
      "val": "189",
      "id": "IDX_01_02_011",
      "val": "4",
      "id": "IDX_01_02_012",
      "val": "458",
      "id": "IDX_01_02_013",
      "val": "3"
    }
  }
}
```

Table 3 Daily monitoring statistics about outgoing calls under a VDN

Index	Index Description	Data Type
-------	-------------------	-----------

Index	Index Description	Data Type
IDX_01_03_001	Indicates the total number of outgoing calls.	string
IDX_01_03_002	Indicates the total number of connected outgoing calls.	string
IDX_01_03_003	Indicates the call completion rate of outgoing calls.	string
IDX_01_03_004	Indicates the number of connected outgoing IVR calls.	string
IDX_01_03_005	Indicates the number of connected outgoing manual calls.	string
IDX_01_03_006	Indicates the average duration that the VDN is occupied by outgoing calls.	string

The following provides an example of the return result for the query of the daily monitoring statistics about outgoing calls under a VDN for the VDN ID of 1:

```
{
  "message": "",
  "retcode": "0",
  "result": [
    {
      "id": "1",
      "idxs": [
        {
          "id": "IDX_01_03_001",
          "val": "1"
        },
        {
          "id": "IDX_01_03_002",
          "val": "1"
        },
        {
          "id": "IDX_01_03_003",
          "val": "100.00"
        },
        {
          "id": "IDX_01_03_004",
          "val": "0"
        },
        {
          "id": "IDX_01_03_005",
          "val": "1"
        },
        {
          "id": "IDX_01_03_006",
          "val": "14"
        }
      ]
    }
  ]
}
```

Table 4 Daily statistics about the VDN service level

Index	Index Description	Data Type	Index Value Description
IDX_01_05_001	Indicates the call drop rate of incoming manual calls in one day.	string	= (Number of incoming manual calls – Number of connected incoming manual calls) / Number of incoming manual calls
IDX_01_05_002	Indicates the call drop rate of incoming calls in one day.	string	= Number of incoming calls in one day – Number of answered incoming calls in one day / Number of incoming calls in one day

The following provides an example of the return result for the query of the daily statistics about the VDN service level for the VDN ID of 1:

```
{
  "message": "",
  "retcode": "0",
  "result": [
    {
      "id": "1",
      "idxs": [
        {
          "id": "IDX_01_05_001",
          "val": "50.00"
        },
        {
          "id": "IDX_01_05_002",
          "val": "71.43"
        }
      ]
    }
  ]
}
```

Table 5 Statistics about the rate of call connection within n seconds in skill queues

Index	Index Description	Data Type	Index Value Description
IDX_01_06_041	Indicates the rate of call connection within 5s.	string	= Statistics about all skill queues under a VDN for the corresponding n seconds This also applies to the following indexes.
IDX_01_06_042	Indicates the rate of call connection within 10s.	string	-
IDX_01_06_043	Indicates the rate of call connection within 15s.	string	-
IDX_01_06_044	Indicates the rate of call connection within 20s.	string	-
IDX_01_06_045	Indicates the rate of call connection within 25s.	string	-
IDX_01_06_046	Indicates the rate of call connection within 30s.	string	-
IDX_01_06_047	Indicates the rate of call connection within 35s.	string	-
IDX_01_06_048	Indicates the rate of call connection within 40s.	string	-
IDX_01_06_049	Indicates the rate of call connection within 45s.	string	-
IDX_01_06_050	Indicates the rate of call connection within 50s.	string	-

The following provides an example of the return result for the query of the statistics about the rate of call connection within n seconds for the VDN ID of 1:

```
{
  "message": "",
  "retcode": "0",
  "result": [
    {
      "id": "1",
      "idxs": [
        {
          "id": "IDX_01_06_041",
          "val": "20.00"
        },
        {
          "id": "IDX_01_06_042",
          "val": "20.00"
        },
        {
          "id": "IDX_01_06_043",
          "val": "40.00"
        },
        {
          "id": "IDX_01_06_044",
          "val": "40.00"
        },
        {
          "id": "IDX_01_06_045",
          "val": "40.00"
        },
        {
          "id": "IDX_01_06_046",
          "val": "40.00"
        },
        {
          "id": "IDX_01_06_047",
          "val": "40.00"
        },
        {
          "id": "IDX_01_06_048",
          "val": "40.00"
        },
        {
          "id": "IDX_01_06_049",
          "val": "40.00"
        },
        {
          "id": "IDX_01_06_050",
          "val": "40.00"
        }
      ]
    }
  ]
}
```

Table 6 Statistics about the rate of call drop within n seconds in skill queues

Index	Index Description	Data Type	Index Value Description
IDX_01_06_051	Indicates the rate of call drop within 5s.	string	= Statistics about all skill queues under a VDN for the corresponding n seconds This also applies to the following indexes.
IDX_01_06_052	Indicates the rate of call drop within 10s.	string	-
IDX_01_06_053	Indicates the rate of call drop within 15s.	string	-
IDX_01_06_054	Indicates the rate of call drop within 20s.	string	-
IDX_01_06_055	Indicates the rate of call drop within 25s.	string	-
IDX_01_06_056	Indicates the rate of call drop within 30s.	string	-
IDX_01_06_057	Indicates the rate of call drop within 35s.	string	-
IDX_01_06_058	Indicates the rate of call drop within 40s.	string	-
IDX_01_06_059	Indicates the rate of call drop within 45s.	string	-

Index	Index Description	Data Type	Index Value Description
IDX_01_06_060	Indicates the rate of call drop within 50s.	string	-

The following provides an example of the return result for the query of the statistics about the rate of call drop within n seconds for the VDN ID of 1:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "1",
    "idxs": {
      "id": "IDX_01_06_051", "val": "40.00",
      "id": "IDX_01_06_052", "val": "40.00",
      "id": "IDX_01_06_053", "val": "40.00",
      "id": "IDX_01_06_054", "val": "40.00",
      "id": "IDX_01_06_055", "val": "40.00",
      "id": "IDX_01_06_056", "val": "40.00",
      "id": "IDX_01_06_057", "val": "40.00",
      "id": "IDX_01_06_058", "val": "40.00",
      "id": "IDX_01_06_059", "val": "40.00",
      "id": "IDX_01_06_060", "val": "40.00"
    }
  }
}
```

Table 7 Statistics about the rate of call connection beyond n seconds in skill queues

Index	Index Description	Data Type	Index Value Description
IDX_01_06_061	Indicates the rate of call connection beyond 5s.	string	= Statistics about all skill queues under a VDN for the corresponding n seconds This also applies to the following indexes.
IDX_01_06_062	Indicates the rate of call connection beyond 10s.	string	-
IDX_01_06_063	Indicates the rate of call connection beyond 15s.	string	-
IDX_01_06_064	Indicates the rate of call connection beyond 20s.	string	-
IDX_01_06_065	Indicates the rate of call connection beyond 25s.	string	-
IDX_01_06_066	Indicates the rate of call connection beyond 30s.	string	-
IDX_01_06_067	Indicates the rate of call connection beyond 35s.	string	-
IDX_01_06_068	Indicates the rate of call connection beyond 40s.	string	-
IDX_01_06_069	Indicates the rate of call connection beyond 45s.	string	-
IDX_01_06_070	Indicates the rate of call connection beyond 50s.	string	-

The following provides an example of the return result for the query of the statistics about the rate of call connection beyond n seconds for the VDN ID of 1:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "1",
    "idxs": {
      "id": "IDX_01_06_061", "val": "20.00",
      "id": "IDX_01_06_062", "val": "20.00",
      "id": "IDX_01_06_063", "val": "0.00",
      "id": "IDX_01_06_064", "val": "0.00",
      "id": "IDX_01_06_065", "val": "0.00",
      "id": "IDX_01_06_066", "val": "0.00",
      "id": "IDX_01_06_067", "val": "0.00",
      "id": "IDX_01_06_068", "val": "0.00",
      "id": "IDX_01_06_069", "val": "0.00",
      "id": "IDX_01_06_070", "val": "0.00"
    }
  }
}
```

Table 8 Daily monitoring statistics about the trend traffic of incoming calls at an interval of 15 minutes under a VDN

Index	Index Description	Data Type	Index Value Description
IDX_01_07_001	Indicates the total number of incoming calls.	map	For details, see Return Result of the Daily Statistics About the Trend Traffic at an Interval of 15, 30, or 60 Minutes . This also applies to the following indexes.
IDX_01_07_002	Indicates the total number of connected incoming calls.	map	-
IDX_01_07_003	Indicates the call completion rate of incoming calls.	map	-
IDX_01_07_004	Indicates the number of incoming IVR calls.	map	-
IDX_01_07_005	Indicates the number of connected incoming IVR calls.	map	-
IDX_01_07_006	Indicates the call completion rate of incoming IVR calls.	map	-
IDX_01_07_007	Indicates the number of incoming manual calls.	map	-
IDX_01_07_008	Indicates the number of connected incoming manual calls.	map	-
IDX_01_07_009	Indicates the call completion rate of incoming manual calls.	map	-
IDX_01_07_010	Indicates the average duration that the VDN is occupied by incoming calls.	map	-

The following provides an example of the return result for the query of the daily monitoring statistics about the trend traffic of incoming calls at an interval of 15 minutes under a VDN for the VDN ID of 1:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "1",
    "idxs": {
      "id": "IDX_01_07_001", "val": {
        "2016-01-28 05:45:00": "1", "2016-01-28 06:45:00": "3", "2016-01-28 06:15:00": "1", "2016-01-28 03:15:00": "2"},
      "id": "IDX_01_07_002", "val": {
        "2016-01-28 05:45:00": "0", "2016-01-28 06:45:00": "1", "2016-01-28 06:15:00": "1", "2016-01-28 03:15:00": "1"},
      "id": "IDX_01_07_003", "val": {
        "2016-01-28 05:45:00": "0.00", "2016-01-28 06:45:00": "33.33", "2016-01-28 06:15:00": "100.00", "2016-01-28 03:15:00": "50.00"},
      "id": "IDX_01_07_004", "val": {
        "2016-01-28 05:45:00": "1", "2016-01-28 06:45:00": "2", "2016-01-28 06:15:00": "0", "2016-01-28 03:15:00": "0"},
      "id": "IDX_01_07_005", "val": {
        "2016-01-28 05:45:00": "0", "2016-01-28 06:45:00": "1", "2016-01-28 06:15:00": "0", "2016-01-28 03:15:00": "0"},
      "id": "IDX_01_07_006", "val": {
        "2016-01-28 05:45:00": "0.00", "2016-01-28 06:45:00": "50.00", "2016-01-28 06:15:00": "0.00", "2016-01-28 03:15:00": "0.00"},
      "id": "IDX_01_07_007", "val": {
        "2016-01-28 05:45:00": "0", "2016-01-28 06:45:00": "1", "2016-01-28 06:15:00": "1", "2016-01-28 03:15:00": "1"},
      "id": "IDX_01_07_008", "val": {
        "2016-01-28 05:45:00": "0", "2016-01-28 06:45:00": "0", "2016-01-28 06:15:00": "1", "2016-01-28 03:15:00": "1"},
      "id": "IDX_01_07_009", "val": {
        "2016-01-28 05:45:00": "0.00", "2016-01-28 06:45:00": "0.00", "2016-01-28 06:15:00": "100.00", "2016-01-28 03:15:00": "50.00"},
      "id": "IDX_01_07_010", "val": {
        "2016-01-28 05:45:00": "0", "2016-01-28 06:45:00": "4", "2016-01-28 06:15:00": "916", "2016-01-28 03:15:00": "10"}
    }
  }
}
```

Table 9 Daily monitoring statistics about the trend traffic of outgoing calls at an interval of 15 minutes under a VDN

Index	Index Description	Data Type
IDX_01_07_012	Indicates the total number of outgoing calls.	map
IDX_01_07_013	Indicates the total number of connected outgoing calls.	map
IDX_01_07_014	Indicates the call completion rate of outgoing calls.	map
IDX_01_07_015	Indicates the number of connected outgoing IVR calls.	map
IDX_01_07_016	Indicates the number of connected outgoing manual calls.	map
IDX_01_07_017	Indicates the average duration that the VDN is occupied by outgoing calls.	map

The following provides an example of the return result for the query of the daily monitoring statistics about the trend traffic of outgoing calls at an interval of 15 minutes under a VDN for the VDN ID of 1:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "1",
    "idxs": {
      "id": "IDX_01_07_012",
      "val": {
        "2016-01-28 05:45:00": "0",
        "2016-01-28 06:45:00": "0",
        "2016-01-28 06:15:00": "0",
        "2016-01-28 03:15:00": "1"
      },
      "id": "IDX_01_07_013",
      "val": {
        "2016-01-28 05:45:00": "0",
        "2016-01-28 06:45:00": "0",
        "2016-01-28 06:15:00": "0",
        "2016-01-28 03:15:00": "1"
      },
      "id": "IDX_01_07_014",
      "val": {
        "2016-01-28 05:45:00": "0.00",
        "2016-01-28 06:45:00": "0.00",
        "2016-01-28 06:15:00": "0.00",
        "2016-01-28 03:15:00": "100.00"
      },
      "id": "IDX_01_07_015",
      "val": {
        "2016-01-28 05:45:00": "0",
        "2016-01-28 06:45:00": "0",
        "2016-01-28 06:15:00": "0",
        "2016-01-28 03:15:00": "0"
      },
      "id": "IDX_01_07_016",
      "val": {
        "2016-01-28 05:45:00": "0",
        "2016-01-28 06:45:00": "0",
        "2016-01-28 06:15:00": "0",
        "2016-01-28 03:15:00": "1"
      },
      "id": "IDX_01_07_017",
      "val": {
        "2016-01-28 05:45:00": "0",
        "2016-01-28 06:45:00": "0",
        "2016-01-28 06:15:00": "0",
        "2016-01-28 03:15:00": "14"
      }
    }
  }
}
```

Table 10 Daily monitoring statistics about the trend traffic of incoming calls at an interval of 30 minutes under a VDN

Index	Index Description	Data Type
IDX_01_08_001	Indicates the total number of incoming calls.	map
IDX_01_08_002	Indicates the total number of connected incoming calls.	map
IDX_01_08_003	Indicates the call completion rate of incoming calls.	map
IDX_01_08_004	Indicates the number of incoming IVR calls.	map
IDX_01_08_005	Indicates the number of connected incoming IVR calls.	map
IDX_01_08_006	Indicates the call completion rate of incoming IVR calls.	map
IDX_01_08_007	Indicates the number of incoming manual calls.	map
IDX_01_08_008	Indicates the number of connected incoming manual calls.	map
IDX_01_08_009	Indicates the call completion rate of incoming manual calls.	map
IDX_01_08_010	Indicates the average duration that the VDN is occupied by incoming calls.	map

The following provides an example of the return result for the query of the daily monitoring statistics about the trend traffic of incoming calls at an interval of 30 minutes under a VDN for the VDN ID of 1:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "1",
    "idxs": {
      "id": "IDX_01_08_001",
      "val": {
        "2016-01-28 06:30:00": "3",
        "2016-01-28 05:30:00": "1",
        "2016-01-28 03:00:00": "2",
        "2016-01-28 06:00:00": "1"
      },
      "id": "IDX_01_08_002",
      "val": {
        "2016-01-28 06:30:00": "1",
        "2016-01-28 05:30:00": "0",
        "2016-01-28 03:00:00": "1",
        "2016-01-28 06:00:00": "1"
      },
      "id": "IDX_01_08_003",
      "val": {
        "2016-01-28 06:30:00": "33.33",
        "2016-01-28 05:30:00": "0.00",
        "2016-01-28 03:00:00": "50.00",
        "2016-01-28 06:00:00": "100.00"
      },
      "id": "IDX_01_08_004",
      "val": {
        "2016-01-28 06:30:00": "2",
        "2016-01-28 05:30:00": "1",
        "2016-01-28 03:00:00": "0",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_01_08_005",
      "val": {
        "2016-01-28 06:30:00": "1",
        "2016-01-28 05:30:00": "0",
        "2016-01-28 03:00:00": "0",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_01_08_006",
      "val": {
        "2016-01-28 06:30:00": "50.00",
        "2016-01-28 05:30:00": "0.00",
        "2016-01-28 03:00:00": "0.00",
        "2016-01-28 06:00:00": "0.00"
      },
      "id": "IDX_01_08_007",
      "val": {
        "2016-01-28 06:30:00": "1",
        "2016-01-28 05:30:00": "0",
        "2016-01-28 03:00:00": "2",
        "2016-01-28 06:00:00": "1"
      },
      "id": "IDX_01_08_008",
      "val": {
        "2016-01-28 06:30:00": "0",
        "2016-01-28 05:30:00": "0",
        "2016-01-28 03:00:00": "0",
        "2016-01-28 06:00:00": "1"
      },
      "id": "IDX_01_08_009",
      "val": {
        "2016-01-28 06:30:00": "0.00",
        "2016-01-28 05:30:00": "0.00",
        "2016-01-28 03:00:00": "50.00",
        "2016-01-28 06:00:00": "100.00"
      },
      "id": "IDX_01_08_010",
      "val": {
        "2016-01-28 06:30:00": "4",
        "2016-01-28 05:30:00": "0",
        "2016-01-28 03:00:00": "10",
        "2016-01-28 06:00:00": "916"
      }
    }
  }
}
```

Table 11 Daily monitoring statistics about the trend traffic of outgoing calls at an interval of 30 minutes under a VDN

Index	Index Description	Data Type
IDX_01_08_012	Indicates the total number of outgoing calls.	map
IDX_01_08_013	Indicates the total number of connected outgoing calls.	map
IDX_01_08_014	Indicates the call completion rate of outgoing calls.	map
IDX_01_08_015	Indicates the number of connected outgoing IVR calls.	map
IDX_01_08_016	Indicates the number of connected outgoing manual calls.	map
IDX_01_08_017	Indicates the average duration that the VDN is occupied by outgoing calls.	map

The following provides an example of the return result for the query of the daily monitoring statistics about the trend traffic of outgoing calls at an interval of 30 minutes under a VDN for the VDN ID of 1:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "1",
    "idxs": {
      "id": "IDX_01_08_012",
      "val": {
        "2016-01-28 06:30:00": "0",
        "2016-01-28 05:30:00": "0",
        "2016-01-28 03:00:00": "1",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_01_08_013",
      "val": {
        "2016-01-28 06:30:00": "0",
        "2016-01-28 05:30:00": "0",
        "2016-01-28 03:00:00": "1",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_01_08_014",
      "val": {
        "2016-01-28 06:30:00": "0.00",
        "2016-01-28 05:30:00": "0.00",
        "2016-01-28 03:00:00": "100.00",
        "2016-01-28 06:00:00": "0.00"
      },
      "id": "IDX_01_08_015",
      "val": {
        "2016-01-28 06:30:00": "0",
        "2016-01-28 05:30:00": "0",
        "2016-01-28 03:00:00": "0",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_01_08_016",
      "val": {
        "2016-01-28 06:30:00": "0",
        "2016-01-28 05:30:00": "0",
        "2016-01-28 03:00:00": "1",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_01_08_017",
      "val": {
        "2016-01-28 06:30:00": "0",
        "2016-01-28 05:30:00": "0",
        "2016-01-28 03:00:00": "14",
        "2016-01-28 06:00:00": "0"
      }
    }
  }
}
```

Table 12 Daily monitoring statistics about the trend traffic of incoming calls at an interval of 60 minutes under a VDN

Index	Index Description	Data Type
IDX_01_09_001	Indicates the total number of incoming calls.	map
IDX_01_09_002	Indicates the total number of connected incoming calls.	map

Index	Index Description	Data Type
IDX_01_09_003	Indicates the call completion rate of incoming calls.	map
IDX_01_09_004	Indicates the number of incoming IVR calls.	map
IDX_01_09_005	Indicates the number of connected incoming IVR calls.	map
IDX_01_09_006	Indicates the call completion rate of incoming IVR calls.	map
IDX_01_09_007	Indicates the number of incoming manual calls.	map
IDX_01_09_008	Indicates the number of connected incoming manual calls.	map
IDX_01_09_009	Indicates the call completion rate of incoming manual calls.	map
IDX_01_09_010	Indicates the average duration that the VDN is occupied by incoming calls.	map

The following provides an example of the return result for the query of the daily monitoring statistics about the trend traffic of incoming calls at an interval of 60 minutes under a VDN for the VDN ID of 1:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "1",
    "idxs": {
      "id": "IDX_01_09_001",
      "val": {
        "2016-01-28 03:00:00": "2",
        "2016-01-28 05:00:00": "1",
        "2016-01-28 06:00:00": "4"
      },
      "id": "IDX_01_09_002",
      "val": {
        "2016-01-28 03:00:00": "1",
        "2016-01-28 05:00:00": "0",
        "2016-01-28 06:00:00": "2"
      },
      "id": "IDX_01_09_003",
      "val": {
        "2016-01-28 03:00:00": "50.00",
        "2016-01-28 05:00:00": "0.00",
        "2016-01-28 06:00:00": "50.00"
      },
      "id": "IDX_01_09_004",
      "val": {
        "2016-01-28 03:00:00": "0",
        "2016-01-28 05:00:00": "1",
        "2016-01-28 06:00:00": "2"
      },
      "id": "IDX_01_09_005",
      "val": {
        "2016-01-28 03:00:00": "0",
        "2016-01-28 05:00:00": "0",
        "2016-01-28 06:00:00": "1"
      },
      "id": "IDX_01_09_006",
      "val": {
        "2016-01-28 03:00:00": "0.00",
        "2016-01-28 05:00:00": "0.00",
        "2016-01-28 06:00:00": "50.00"
      },
      "id": "IDX_01_09_007",
      "val": {
        "2016-01-28 03:00:00": "2",
        "2016-01-28 05:00:00": "0",
        "2016-01-28 06:00:00": "2"
      },
      "id": "IDX_01_09_008",
      "val": {
        "2016-01-28 03:00:00": "1",
        "2016-01-28 05:00:00": "0",
        "2016-01-28 06:00:00": "1"
      },
      "id": "IDX_01_09_009",
      "val": {
        "2016-01-28 03:00:00": "50.00",
        "2016-01-28 05:00:00": "0.00",
        "2016-01-28 06:00:00": "50.00"
      },
      "id": "IDX_01_09_010",
      "val": {
        "2016-01-28 03:00:00": "10",
        "2016-01-28 05:00:00": "0",
        "2016-01-28 06:00:00": "308"
      }
    }
  }
}
```

Table 13 Daily monitoring statistics about the trend traffic of outgoing calls at an interval of 60 minutes under a VDN

Index	Index Description	Data Type
IDX_01_09_012	Indicates the total number of outgoing calls.	map
IDX_01_09_013	Indicates the total number of connected outgoing calls.	map
IDX_01_09_014	Indicates the call completion rate of outgoing calls.	map
IDX_01_09_015	Indicates the number of connected outgoing IVR calls.	map
IDX_01_09_016	Indicates the number of connected outgoing manual calls.	map
IDX_01_09_017	Indicates the average duration that the VDN is occupied by outgoing calls.	map

The following provides an example of the return result for the query of the daily monitoring statistics about the trend traffic of outgoing calls at an interval of 60 minutes under a VDN for the VDN ID of 1:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "1",
    "idxs": {
      "id": "IDX_01_09_012",
      "val": {
        "2016-01-28 03:00:00": "1",
        "2016-01-28 05:00:00": "0",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_01_09_013",
      "val": {
        "2016-01-28 03:00:00": "1",
        "2016-01-28 05:00:00": "0",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_01_09_014",
      "val": {
        "2016-01-28 03:00:00": "100.00",
        "2016-01-28 05:00:00": "0.00",
        "2016-01-28 06:00:00": "0.00"
      },
      "id": "IDX_01_09_015",
      "val": {
        "2016-01-28 03:00:00": "0",
        "2016-01-28 05:00:00": "0",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_01_09_016",
      "val": {
        "2016-01-28 03:00:00": "1",
        "2016-01-28 05:00:00": "0",
        "2016-01-28 06:00:00": "0"
      },
      "id": "IDX_01_09_017",
      "val": {
        "2016-01-28 03:00:00": "14",
        "2016-01-28 05:00:00": "0",
        "2016-01-28 06:00:00": "0"
      }
    }
  }
}
```

Table 14 Monthly statistics about voice calls under a VDN

Index	Index Description	Data Type
IDX_01_10_001	Indicates the number of incoming calls.	string
IDX_01_10_002	Indicates the number of connected incoming calls.	string
IDX_01_10_003	Indicates the call completion rate of incoming calls.	string
IDX_01_10_004	Indicates the number of outgoing calls.	string
IDX_01_10_005	Indicates the number of connected outgoing calls.	string
IDX_01_10_006	Indicates the call completion rate of outgoing calls.	string
IDX_01_10_007	Indicates the number of incoming calls based on skills.	string
IDX_01_10_008	Indicates the number of connected incoming calls based on skills.	string
IDX_01_10_009	Indicates the call completion rate of incoming calls based on skills.	string
IDX_01_10_010	Indicates the number of connected outgoing calls based on skills.	string
IDX_01_10_011	Indicates the number of incoming IVR calls.	string
IDX_01_10_012	Indicates the number of connected incoming IVR calls.	string
IDX_01_10_013	Indicates the call completion rate of incoming IVR calls.	string
IDX_01_10_014	Indicates the number of connected outgoing IVR calls.	string
IDX_01_10_015	Indicates the average duration that the VDN is occupied by incoming calls.	string
IDX_01_10_016	Indicates the average duration that the VDN is occupied by outgoing calls.	string

The following provides an example of the return result for the query of the monthly statistics about voice calls under a VDN for the VDN ID of 1:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "1",
    "idxs": {
      "id": "IDX_01_10_001",
      "val": "201",
      "id": "IDX_01_10_002",
      "val": "119",
      "id": "IDX_01_10_003",
      "val": "59.20",
      "id": "IDX_01_10_004",
      "val": "49",
      "id": "IDX_01_10_005",
      "val": "44",
      "id": "IDX_01_10_006",
      "val": "89.80",
      "id": "IDX_01_10_007",
      "val": "194",
      "id": "IDX_01_10_008",
      "val": "113",

```

{ "id": "IDX_01_10_009", "val": "58.25"}, { "id": "IDX_01_10_010", "val": "44"}, { "id": "IDX_01_10_011", "val": "7"}, { "id": "IDX_01_10_012", "val": "6"}, { "id": "IDX_01_10_013", "val": "85.71"}, { "id": "IDX_01_10_014", "val": "0"}, { "id": "IDX_01_10_015", "val": "1612"}, { "id": "IDX_01_10_016", "val": "12693"}] }

Table 15 Daily statistics about multimedia services under a VDN

Index	Index Description	Data Type
IDX_01_11_001	Indicates the number of requests.	string
IDX_01_11_002	Indicates the number of successful calls.	string
IDX_01_11_003	Indicates the call duration.	string
IDX_01_11_004	Indicates the waiting time in queues.	string
IDX_01_11_005	Indicates the number of queuing failures.	string
IDX_01_11_006	Indicates the number of queuing drops.	string
IDX_01_11_007	Indicates the number of calls that are answered within <i>n</i> seconds.	string

The following provides an example of the return result for the query of the daily statistics about multimedia services under a VDN for the VDN ID of 1:

{ "message": "", "retcode": "0", "result": [{ "id": "1", "idxs": [{ "id": "IDX_01_11_001", "val": "10"}, { "id": "IDX_01_11_002", "val": "10"}, { "id": "IDX_01_11_003", "val": "78"}, { "id": "IDX_01_11_004", "val": "5"}, { "id": "IDX_01_11_005", "val": "0"}, { "id": "IDX_01_11_006", "val": "0"}, { "id": "IDX_01_11_007", "val": "10"}] }] }

Parent topic: [Historical Monitoring Indexes](#)

Return Result of the Daily Statistics About the Trend Traffic at an Interval of 15, 30, or 60 Minutes

This section uses the query of the `IDX_01_07_001` index as an example. The index indicates the total number of incoming calls at an interval of 15 minutes under a VDN. The following provides an example of the return result:

```
{
  "message": "",
  "retcode": "0",
  "result": [
    {
      "id": "1",
      "idxs": [
        {
          "id": "IDX_01_01_001",
          "val": [
            "2016-01-28 05:45:00": "1",
            "2016-01-28 06:45:00": "3",
            "2016-01-28 06:15:00": "1",
            "2016-01-28 03:15:00": "3"
          ]
        }
      ]
    }
  ]
}
```

 **NOTE**

If there is no call during an interval of 15 minutes, the return result does not provide the record of this interval.

Table 1 Description of the return result of the daily monitoring statistics about the trend traffic of incoming calls at an interval of 15 minutes under a VDN

Key	Value
The time is the UTC time in the format of yyyy-MM-dd HH:mm:ss and the interval is <i>n</i> minutes. For example, 2016-01-28 03:15:00.	Indicates the value of the index. Each index value is a string. For example, 2.

Parent topic: [Historical Monitoring Indexes](#)

Real-Time Monitoring Indexes

- [Agent](#)
- [Skill](#)
- [VDN](#)

Parent topic: [Appendix](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Table 1 Real-time information about an agent

Index	Index Description	Data Type	Index Value Description
IDX_04_01_003	Indicates a phone number.	string	-
IDX_04_01_007	Indicates the agent status.	string	For details, see Agent Status .
IDX_04_01_008	Indicates the duration of the current state.	string	-
IDX_04_01_010	Indicates a list of skill queues to which the agent has logged in.	array	The value is an array of skill queue IDs.
IDX_04_01_011	Indicates the reason for the rest or show-busy state.	string	-
IDX_04_01_045	Indicates the inspection status.	string	The value is in the format of being screen-recorded being monitored being intercepted. 1 : The agent is screen-recorded, monitored, or intercepted. 0 : The agent is not screen-recorded, monitored, or intercepted. For example: 0 0 0
IDX_04_01_050	Indicates the IP address of the agent.	string	-

The following provides an example of the return result for the query of the real-time information about an agent for the agent work ID of 291:

```
{"message":"","retcode":"0","result":[{"id":"291","idxs":[{"id":"IDX_04_01_003","val":"40101"}, {"id":"IDX_04_01_007","val":"1"}, {"id":"IDX_04_01_008","val":"9377"}, {"id":"IDX_04_01_010","val":["1,3,10,11,25,31,32,40"]}, {"id":"IDX_04_01_045","val":"0|0|0"}, {"id":"IDX_04_01_050","val":"192.168.0.0"}]}]}
```

Parent topic: [Real-Time Monitoring Indexes](#)

Skill

Table 1 Real-time call information of a skill queue

Index	Index Description	Data Type
IDX_03_01_002	Indicates the number of queuing calls.	string
IDX_03_01_003	Indicates the number of calls that are being processed.	string
IDX_03_01_004	Indicates the maximum waiting time for queuing.	string
IDX_03_01_005	Indicates the number of calls that are connected within 20s in the last five minutes.	string

The following provides an example of the return result for the query of the real-time call information of a skill queue for the skill queue ID of 25:

```
{"message":"","retcode":"0","result":[{"id":"25","idxs":[{"id":"IDX_03_01_002","val":"0"},{"id":"IDX_03_01_003","val":"1"},{"id":"IDX_03_01_004","val":"5"},{"id":"IDX_03_01_005","val":"0"}]}]}
```

Table 2 Real-time agent information of a skill queue

Index	Index Description	Data Type
IDX_03_02_001	Indicates the number of agents who have signed in.	string
IDX_03_02_002	Indicates the number of talking agents.	string
IDX_03_02_003	Indicates the number of idle agents.	string
IDX_03_02_004	Indicates the number of available agents.	string
IDX_03_02_005	Indicates the number of busy agents.	string
IDX_03_02_006	Indicates the number of agents in the wrap-up state.	string
IDX_03_02_007	Indicates the number of resting agents.	string
IDX_03_02_010	Indicates the number of agents in the study state.	string

The following provides an example of the return result for the query of the real-time agent information of a skill queue for the skill queue ID of 25:

```
{"message":"","retcode":"0","result":[{"id":"25","idxs":[{"id":"IDX_03_02_001","val":"1"},{"id":"IDX_03_02_002","val":"1"},{"id":"IDX_03_02_003","val":"0"},{"id":"IDX_03_02_004","val":"0"},{"id":"IDX_03_02_005","val":"0"},{"id":"IDX_03_02_006","val":"0"},{"id":"IDX_03_02_007","val":"0"},{"id":"IDX_03_02_010","val":"0"}]}]}
```

Parent topic: [Real-Time Monitoring Indexes](#)

Table 1 Real-time monitoring statistics about a VDN

Index	Index Description	Data Type	Index Value Description
IDX_01_04_001	Indicates the number of connected calls under the VDN.	string	= Number of IVR calls + Total number of calls in all skill queues
IDX_01_04_009	Indicates the total number of calls under the VDN.	string	= Number of IVR calls + Total number of calls in all skill queues + Total number of queuing calls in all skill queues
IDX_01_04_002	Indicates the number of IVR calls.	string	-
IDX_01_04_004	Indicates the number of queuing calls.	string	= Total number of queuing calls in all skill queues
IDX_01_04_005	Indicates the number of agents who have signed in.	string	= Total number of agents not in the sign-out state
IDX_01_04_006	Indicates the number of idle agents.	string	= Total number of agents in the idle state
IDX_01_04_007	Indicates the number of busy agents.	string	= Total number of agents in the busy state
IDX_01_04_008	Indicates the number of talking agents.	string	= Total number of agents in the talk state
IDX_01_04_010	Indicates the number of agents in the study state.	string	= Total number of agents in the study state
IDX_01_04_011	Indicates the number of agents in the wrap-up state.	string	= Total number of agents in the wrap-up state
IDX_01_04_012	Indicates the number of answering agents.	string	= Total number of agents in the answering state
IDX_01_04_013	Indicates the number of preoccupied agents.	string	= Total number of agents in the preoccupied state
IDX_01_04_014	Indicates the number of occupied agents.	string	= Total number of agents in the occupied state
IDX_01_04_015	Indicates the number of agents who have not signed in.	string	= Total number of agents in the unsigned state
IDX_01_04_016	Indicates the number of resting agents.	string	= Total number of agents in the resting state

The following provides an example of the return result for the query of the real-time monitoring statistics about a VDN for the VDN ID of 1:

```
{
  "message": "",
  "retcode": "0",
  "result": {
    "id": "1",
    "idxs": [
      {
        "id": "IDX_01_04_001",
        "val": "2"
      },
      {
        "id": "IDX_01_04_009",
        "val": "2"
      },
      {
        "id": "IDX_01_04_002",
        "val": "0"
      },
      {
        "id": "IDX_01_04_004",
        "val": "0"
      },
      {
        "id": "IDX_01_04_005",
        "val": "33"
      },
      {
        "id": "IDX_01_04_006",
        "val": "20"
      },
      {
        "id": "IDX_01_04_007",
        "val": "4"
      },
      {
        "id": "IDX_01_04_008",
        "val": "3"
      },
      {
        "id": "IDX_01_04_010",
        "val": "0"
      },
      {
        "id": "IDX_01_04_011",
        "val": "6"
      },
      {
        "id": "IDX_01_04_012",
        "val": "0"
      },
      {
        "id": "IDX_01_04_013",
        "val": "0"
      },
      {
        "id": "IDX_01_04_014",
        "val": "0"
      },
      {
        "id": "IDX_01_04_015",
        "val": "772"
      },
      {
        "id": "IDX_01_04_016",
        "val": "0"
      }
    ]
  }
}
```

Parent topic: [Real-Time Monitoring Indexes](#)

Agent Status

Table 1 Agent status

Value	Description
0	Unsigned
1	Idle
2	Preoccupied
3	Occupied
4	Answering
5	Talk
6	Adjust after call
7	Busy
8	Resting
9	Study

Parent topic: [Appendix](#)

Operating Status of Agents

Table 1 Agent operating status description

Value	Description
0	Unsigned
1	Study
2	Idle
3	Busy
4	Talk
5	Answering
6	Wrap-up
9	Ringing
10	Three-party call
13	Manual service transfer to voice self-service and the agent is in the blocked state
14	Enter the working state
15	Adjust
16	Exit the working state
20	Inserted by interception
22	Announcement playing
26	Resting
27	Working
28	Call inserted by interception
29	Mute
30	On hold
31	Freeze image
32	Mute and freeze image

Parent topic: [Appendix](#)

Call Status

Table 1 Call status

Value	Description
0	The call object is idle and there is no call.
1	The call object is occupied.
2	The call is waiting in a skill queue.
3	The call is waiting in a private queue.
4	The call is ringing and waiting to be answered.
5	The calling party and called party are talking or interacting with others.
6	The call is placed on hold.
7	The call is blocked.
8	The call is muted.
9	The call is a third-party call.

Parent topic: [Appendix](#)

Call Features

Table 1 Call features

Value	Description
0	Common incoming call
6	Internal call
7	Common outgoing call
40	Reserved outgoing call
41	Preemptive outgoing call
43	Predictive outgoing call
44	Previewed outgoing call
45	Reserved callback
51	Internal two-party consulting
52	Internal three-party consulting
53	Multi-party call

Parent topic: [Appendix](#)

Agent Permission Values

Table 1 Agent permission values

Bit	Description
1	Showing busy/idle
2	Muting/Unmuting
3	Holding/Unholding
4	Connecting a held call
5	Common outgoing call
6	Internal call
7	Internal transfer
8	Answering a transferred call
9	Three-party call
10	Transfer-out
11	Transfer from agents to IVR
12	Not to answer an incoming call
13	Listening/Barge/Whisper
14	Interception
15	Forcible logout/forcible busy-showing/forcible idle-showing
16	Quality inspection recording/Quality inspection voice playback
17	Quality inspection monitoring
18	Appraise administrator
19	Ordinary appraiser
20	Alarm console
21	Report handler
22	Not used and reserved
23	Monitoring console
24	Configuration administrator
25	Report administrator
26	National outgoing toll call
27	International outgoing toll call
28	Outgoing call using the call center access code
29	Full screen quality inspection
30	Group pickup
31	Not used and reserved
32	Configuration agent
33~256	Not used and reserved

Parent topic: [Appendix](#)

Call Type

Table 1 Call Type

ID	Call Type	Description
0	SP_CALL_NORMAL	Common incoming call
5	SP_CALL_LONG	Incoming toll call
6	INTER_CALL	Internal call It refers to a call made by an agent to another agent. An internal call cannot be forwarded, or muted.
7	SP_CALL_OUT	Common outgoing call It refers to an outgoing call made by agents.
8	OP_CALL_OUT	Agent outgoing call type
9	OP_PRI_OUT	Outgoing call in the PRI mode
10	IVR_CALL_OUT	Outgoing call through IVR
11	SELF_CALLOUT	Outgoing call made by a Phone agent
12	IVR_PRI_CALL	Outgoing call in the PRI mode through IVR
13	NIRC_CALL_IN	Incoming call to a networked call center
14	NIRC_CALL_OUT	Outgoing call of a networked call center
15	NIRC_SPY_CALL_IN	QC incoming call to a networked call center
16	NIRC_SPY_CALL_OUT	QC outgoing call of a networked call center
17	NIRC_INTER_CALL_IN	Internal incoming network call to a virtual agent
18	NIRC_INTER_CALL_OUT	Internal outgoing network call of a virtual agent
20	ICD_SP_OPS_AIDERCALL	Aid call
21	ICD_SP_OPS_INCALL	Incoming call (international agent)
22	ICD_SP_OPS_PASSCALL	Relay call
23	ICD_SP_OPS_GIVECALL	Outgoing call (international agent)
40	OUTBOUND_CALL_OUT	Reserving an outgoing call The system queries the reserved outgoing call database regularly. After obtaining the reserved calls whose time is earlier than the current computer time, the system forcibly makes the calls.
41	ICD_SP_OUTBOUND_PRE_OCCUPY	Pre-occupied an outgoing call The system occupies an idle agent and then makes an outgoing call. If making the outgoing call succeeds, the idle agent handles the call.
42	ICD_SP_OUTBOUND_PRE_CONNECT	Pre-connecting an outgoing call The system makes an outgoing call to a user. If making the call succeeds, the system connects the call to an agent when the phone of the user rings.
43	ICD_SP_OUTBOUND_VIRTUAL_CALLIN	Predicting an outgoing call The system makes an outgoing call to a user. If making the call succeeds, the system connects the call to an agent after the user hooks off.
44	ICD_SP_OUTBOUND_PREVIEW	Previewing an outgoing call It refers to a call that is made by an agent after the agent previews the outgoing call information.
45	ICD_SP_OUTBOUND_CALLBACK	Callback request If a Web user needs to contact a call center when browsing Web pages on Internet, the Web user can use the callback request service. An agent in the call center then dials the phone number specified by the Web user. After the call is connected, the web user follows the voice instruction of the agent and at the same time enjoy other services such as escorted browsing.
46	ICD_SP_IDD	International incoming toll call
50	ICD_SP_CBRT_CALL	RBT call
51	ICD_SP_INTERNAL_TWO_HELP	Two-party help call When answering an incoming call, an agent can ask for internal help. In the case of a two-party help, the call of the customer is held, and the agent talks with the asked-for-help agent.
52	ICD_SP_INTERNAL_THREE_HELP	Three-party help call When answering an incoming call, an agent can ask for internal help. In the case of a three-party help, the customer, agent, and asked-for-help agent can talk with each other. In the case of a two-party help, a three-party help can be initiated to form a three-party conversation.
60	ICD_SP_OUTBOUND_PRE_OCCUPY_PRI_CALL	Pre-occupied an outgoing call in the PRI mode
61	ICD_SP_OUTBOUND_PRE_CONNECT_PRI_CALL	Pre-connecting an outgoing call in the PRI mode
62	ICD_SP_OUTBOUND_VIRTUAL_CALLIN_PRI_CALL	Virtual incoming and outgoing calls in the PRI mode
63	ICD_SP_OUTBOUND_PREVIEW_PRI_CALL	Previewing an outgoing call in the PRI mode

ID	Call Type	Description
64	ICD_SP_OUTBOUND_CALLBACK_PRI_C ALL	Callback request in the PRI mode

Parent topic: [Appendix](#)

Call Release Cause Codes

Table 1

Release Source	Cause Code	Type	Description
User release	501	VOICE_CALL_RELEASE_CAUSE_GENERAL	Default call release cause. The routing result from the CCS is not received after a call accesses the platform. As a result, the call is disconnected.
	502	CALL_RELEASE_CAUSE_ACD_NO_ACK	The called party does not answer the call for a long time, and the call is released.
	518	CALL_RELEASE_CAUSE_UIS_DISCONNECT	The client releases the call.
	537	CALL_RELEASE_CAUSE_CALLED_BUSY	The ACD disconnects the call because the called party is busy.
	538	CALL_RELEASE_CAUSE_NO_SUCH_NUMBER	The ACD disconnects the call because the called number does not exist.
	548	CALL_RELEASE_CAUSE_GSM_CLD_USER_NOT_ACTIVE	The ACD disconnects the call because the called party is powered off.
	549	CALL_RELEASE_CAUSE_GSM_CLD_USER_NOT_REACHABLE	The ACD disconnects the call because the called party is out of the service area.
	551	CALL_RELEASE_CAUSE_ACD_FAULT_DISCONNECT	The ACD disconnects the call for another reason.
	601	CALL_RELEASE_ACD_BEFORE_ANSWER	The ACD disconnects the call because the calling party hooks on before the call is answered.
	603	CALL_RELEASE_ACD_NO_RESPOND	The ACD disconnects the call because the called party does not answer the call.
	604	CALL_RELEASE_ACD_CALLED_REJECTED	The ACD disconnects the call because the called party rejects the call.
	800	DISC_CAUSE_USERHOOK_QUEUE	The user hangs up in the queue.
	1138	ICD_ERR_CTISVR_OC_CALLED_RELEASE	The called party hangs up.
	1163	ICD_ERR_CTISVR_OC_DISCONNECT_ACDRELEASE_CAUSE_NO_SUCH_NUMBER	The called number does not exist.
	1164	ICD_ERR_CTISVR_OC_DISCONNECT_ACDRELEASE_CAUSE_CALLED_BUSY	The called party is busy.
	1165	ICD_ERR_CTISVR_OC_DISCONNECT_ACDRELEASE_CAUSE_GSM_CLD_USER_NOT_ACTIVE	The mobile phone is powered off.
	1166	ICD_ERR_CTISVR_OC_DISCONNECT_ACDRELEASE_CAUSE_GSM_CLD_USER_NOT_REACHABLE	The mobile phone is out of the service area.
	1168	ICD_ERR_CTISVR_OC_DISCONNECT_ACDRELEASE_CAUSE_NO_RESPOND	The call is disconnected on no reply.
	1169	ICD_ERR_CTISVR_OC_DISCONNECT_ACDRELEASE_CAUSE_CALLED_REJECTED	The called party rejects the call.
	1170	ICD_ERR_CTISVR_OC_DISCONNECT_ACDRELEASE_CAUSE_LINE_BUSY	The line is busy.
	1261	ICD_ERR_CTISVR_OC_DISCONNECT011	The user hangs up during a three-party conversation.
	1262	ICD_ERR_CTISVR_OC_DISCONNECT012	The user hangs up during a three-party conversation.
	1263	ICD_ERR_CTISVR_OC_DISCONNECT013	The user hangs up when the phone rings.
Agent release	1346	ICD_ERR_CTISVR_OC_DISCONNECT096	1. The resource connection fails during three-party help, and the current call is disconnected. 2. When the agent answers the call, the call does not exist.
	1353	ICD_ERR_CTISVR_OC_DISCONNECT112	When the called party picks up the phone and finds that the current call does not exist, the system releases the outgoing call.
	521	CALL_RELEASE_CAUSE_REDIRECT	The agent initiates call redirection.
	531	CALL_RELEASE_CAUSE_ACD_DISCONNECT	The ACD disconnects the call and therefore the call is normally released.
	532	CALL_RELEASE_CAUSE_CCC_DISCONNECT	OC release
	534	CALL_RELEASE_CAUSE_ACD_MODULE_DISCONNECT	After disconnecting from an ACD module, the CTI Server releases all the calls on the module.
	536	CALL_RELEASE_CAUSE_CANCELQUEUE_FAILURE	Waiting for the ACD to release the call times out when queuing is canceled. The platform releases the call.
	602	CALL_RELEASE_ACD_NO_RESOURCE	The ACD disconnects the call because no resource is available.
	605	CALL_RELEASE_ACD_LINE_BUSY	The ACD disconnects the call because the system is busy.
	606	CALL_RELEASE_ACD_TIMEOUT	The ACD disconnects the call because the call times out.
	1118	ICD_ERR_CTISVR_OC_AGENT_SELF_CALL_RELEASE	When the user picks up the phone, the phone agent hangs up.

Release Source	Cause Code	Type	Description
	1122	ICD_ERR_CTISVR_OC_AGENT_RELEASE	The agent hangs up when waiting for the resource connection result or waiting for the response.
	1153	ICD_ERR_CTISVR_OC_AGENT_HUNGUP_PHONE	The phone agent hangs up.
	1167	ICD_ERR_CTISVR_OC_DISCONNECT_ACDRELEASE_CAUSE_NO_RESOURCE	The ACD disconnects the call because no resource is available.
	1171	ICD_ERR_CTISVR_OC_DISCONNECT_ACDRELEASE_CAUSE_TIMEOUT	The ACD disconnects the call because the call times out.
	1254	ICD_ERR_CTISVR_OC_DISCONNECT004	1. The called party is in invalid state after off-hook. 2. The agent who creates the conference deletes itself from the conference.
	1255	ICD_ERR_CTISVR_OC_DISCONNECT005	The called party is in invalid state after picking up the phone.
	1332	ICD_ERR_CTISVR_OC_DISCONNECT082	The agent is logged out, or the agent disconnects the call when detecting that the agent is abnormal.
	1333	ICD_ERR_CTISVR_OC_DISCONNECT083	When the phone agent receives a response from the client, the phone of the agent hangs up. The current call is disconnected.
	1334	ICD_ERR_CTISVR_OC_DISCONNECT084	During the internal help of a phone agent, if the agent hangs up but the transfer fails, the current call is disconnected.
	1335	ICD_ERR_CTISVR_OC_DISCONNECT085	During the internal help of a phone agent, if the agent hangs up but the transfer fails, the call is disconnected.
	1336	ICD_ERR_CTISVR_OC_DISCONNECT086	When a phone agent makes a three-party call, the call of the agent does not exist. The call is disconnected.
	1347	ICD_ERR_CTISVR_OC_DISCONNECT097	When a three-party call is transferred, the resource connection fails and the current call is disconnected.
	1351	ICD_ERR_CTISVR_OC_DISCONNECT110	A resource disconnection notification is received, and the current call is disconnected.
	1354	ICD_ERR_CTISVR_OC_DISCONNECT113	Wait for the agent to make a call, or the call of the agent is ringing, or the call of the agent is picked up or times out. The call of the agent is disconnected.
	1355	ICD_ERR_CTISVR_OC_DISCONNECT114	When the call is transferred out, the resource connection fails, and the outgoing call is disconnected.
	1360	ICD_ERR_CTISVR_OC_DISCONNECT119	The original agent releases the help call in the two-party help process.
	1363	ICD_ERR_CTISVR_OC_DISCONNECT122	When an agent logs out or an agent is abnormal, the system releases the VP call resources.
	1450	ICD_ERR_CTISVR_RES_DIS_CAUSE30	1. When an agent receives a call transfer response, the agent initiates a resource disconnection. 2. When an agent initiates a call, the agent initiates a resource disconnection. 3. When an agent is waiting for restoration after hang-up transfer, the call is disconnected. 4. The agent disconnects the call.
	1451	ICD_ERR_CTISVR_RES_DIS_CAUSE31	During a three-party conversation, the agent releases the call and the resources are disconnected.
	1452	ICD_ERR_CTISVR_RES_DIS_CAUSE32	During a three-party conversation, the agent releases the call.
	1453	ICD_ERR_CTISVR_RES_DIS_CAUSE33	When waiting for the resource connection result, the agent releases the current call.
	1481	ICD_ERR_CTISVR_RES_DIS_CAUSE61	When a call is transferred out, the outgoing call of the agent is disconnected and resources are disconnected.
	35020	ICD_ERR_CTISVR_OC_ASP_IDLE	The agent hangs up.
	35021	ICD_ERR_CTISVR_OC_ASP_ACTIVE	The agent picks up the phone.
	35022	ICD_ERR_CTISVR_OC_ASP_ALERTING	The phone of the agent rings.
	35023	ICD_ERR_CTISVR_OC_ASP_OTHER	Other status of the agent's phone
	35028	ICD_ERR_CTISVR_AGENT_PHONE_RELEASE	If the agent releases the call, other operations are not allowed.
	35032	ICD_ERR_CTISVR_OC_SELF_CALL_IS_NOT_VALID	The agent fails to initiate a call to their own phone.
Process release	522	CALL_RELEASE_CAUSE_REDIRECT2	An IVR flow initiates call redirection.
	533	CALL_RELEASE_CAUSE_CCC_DISCONNECT2	When a flow transfers a call to another flow, the flow releases the call before ringing.
	540	CALL_RELEASE_CAUSE_RELEASE_REPORT	The call is released after voice playing.
	1119	ICD_ERR_CTISVR_OC_AGENT_NOT_IDLE	The agent is not in the idle state.
	1120	ICD_ERR_CTISVR_OC_AGENT_NOT_ACTIVE	The agent is not in conversation state.
	1121	ICD_ERR_CTISVR_OC_ALREADY_HOLD_CALL	During call hold, the index of the held call already exists.
	1157	ICD_ERR_CTISVR_OC_AGENT_DISCONNECT_SELF_PHONE1	Removing an agent's phone number

Release Source	Cause Code	Type	Description
	1356	ICD_ERR_CTISVR_OC_DISCONNECT115	Success transfer, call transfer, three-party call transfer, failed to receive the transfer result.
	1359	ICD_ERR_CTISVR_OC_DISCONNECT118	Disconnecting an outgoing call from an agent when the call is transferred out
	1414	ICD_ERR_CTISVR_IVR_DISCONNECT24	The IVR logs out of the CTI Server.
	1415	ICD_ERR_CTISVR_IVR_DISCONNECT25	The CTI Server is switched from the active node to the standby node.
	1421	ICD_ERR_CTISVR_RES_DIS_CAUSE1	1. Save the call to the private call queue of the agent. 2. Add the device to the conference.
	1428	ICD_ERR_CTISVR_RES_DIS_CAUSE8	Cancel QC VP Call During QC Recording
	1429	ICD_ERR_CTISVR_RES_DIS_CAUSE9	Cancel QC VP call during QC voice playing
	1430	ICD_ERR_CTISVR_RES_DIS_CAUSE10	During agent recording, the agent VP call is canceled.
	1431	ICD_ERR_CTISVR_RES_DIS_CAUSE11	During agent announcement playing, the agent VP call is canceled.
	1432	ICD_ERR_CTISVR_RES_DIS_CAUSE12	The listening on the called party is canceled.
	1480	ICD_ERR_CTISVR_RES_DIS_CAUSE60	1. The network call is disconnected and the resource is disconnected. 2. When the call is released, the resource is disconnected.
	35002	ICD_ERR_CTISVR_OC_NOT_VIDEO_ABILITY	The current call does not have the video capability.
	35007	ICD_ERR_CTISVR_OC_NOTEXIST_PLAY_VIDEO	No video is played.
	35008	ICD_ERR_CTISVR_OC_SELFPLAY_EXIST	This operation is not allowed because self-play exists.
	35009	ICD_ERR_RP_TASK_NOTEXIST	The current (playback or recording) task does not exist.
	35011	ICD_ERR_CTISVR_OC_MODE_MUTE_NOTSUPPORT	The operation is not allowed because the device is in the mute or image-frozen state.
	35012	ICD_ERR_CTISVR_OC_NOT_MUTEVIDEO	The operation is not allowed because it is not in the image-frozen state.
	35013	ICD_ERR_CTISVR_OC_NOT_MUTEVOICE	The operation is not allowed because it is not in the mute state.
	35015	ICD_ERR_CTISVR_OC_PLAY_MMFILE_TO_AGENT_NOTSUPPORT	The b310 version does not support the function of playing multimedia files to agents.
	35016	ICD_ERR_CTISVR_NOT_SUPPORT_MEDIAINFO	The media type is not supported.
	35017	ICD_ERR_CTISVR_IVR_INVALID_SCPCB	Invalid control block.
	35018	ICD_ERR_RP_TASK_PLAY_DTMF_EXIST	The announcement playing and digit collection task already exists and cannot be delivered repeatedly.
Internal cause code of the platform.	503	CALL_RELEASE_CAUSE_ACD_SHAKEHAND_TIMEOUT	After the call is set up between the ACD and platform, the control blocks on the platform and the ACD time out in handshake. As a result, the platform disconnects the call.
	505	CALL_RELEASE_CAUSE_IVR_RESUMEACK_TIMEOUT	When a call is transferred back to the IVR after the IVR transfers the call to the agent console in blocked transfer mode, the IVR times out in responding to the blocked transfer message. As a result, the platform disconnects the call.
	506	CALL_RELEASE_CAUSE_CCS_REROUTEACK_TIMEOUT	When waiting for the CCS routing result times out, the platform disconnects the call.
	507	CALL_RELEASE_CAUSE_CCS_REROUTEACK_TIMEOUT2	After the call is connected to the platform, waiting for the CCS routing result times out.
	508	CALL_RELEASE_CAUSE_CCS_DOFORWARD_TIMEOUT	During call transfer, waiting for the CCS transfer notification times out, or waiting for the CCS notification to resume the suspended call times out.
	509	CALL_RELEASE_CAUSE_CCS_TRANSACTION_TIMEOUT	When an internal call is successfully transferred, the CCS times out in sending the call transfer message.
	510	CALL_RELEASE_CAUSE_ACD_SETUPACK_TIMEOUT	When the platform initiates an outgoing call, the ACD times out in sending the SETUP_ACK message.
	511	CALL_RELEASE_CAUSE_CCS_OCCUPYACK_TIMEOUT	When the platform initiates an outgoing call, the CCS times out in returning the OCCUPY_ACK message.
	512	CALL_RELEASE_CAUSE_CCS_QUEUE_TIMEOUT	Call queuing overflows or times out.
	513	CALL_RELEASE_CAUSE_CCS_QUEUE_TIMEOUT2	Call queuing overflows or times out.
	514	CALL_RELEASE_CAUSE_CCC_ROUTINGACK_TIMEOUT	When a call is transferred from an agent to an automatic flow, the automatic flow times out in responding.
	515	CALL_RELEASE_CAUSE_CCC_ROUTINGACK_TIMEOUT2	When a call is transferred, the transferred-to device times out in responding.
	516	CALL_RELEASE_CAUSE_CCS_ROUTE_TIMEOUT	Waiting for the routing response from the CCS times out.
	517	CALL_RELEASE_CAUSE_PROCEEDING_TIMEOUT	Waiting for the ringing or response of the destination device times out.

Release Source	Cause Code	Type	Description
	519	CALL_RELEASE_CAUSE_CCS_IND_ADDRESS_ERROR	During call transfer, the address sent by the CCS is incorrect.
	520	CALL_RELEASE_CAUSE_CCS_IND_ADDRESS_ERROR2	During call transfer, the address sent by the CCS is incorrect.
	523	CALL_RELEASE_CAUSE_OCCUPYACK_ERROR	When the platform initiates an outgoing call, the CCS fails to return the occupied device.
	525	CALL_RELEASE_CAUSE_ROUTE_ADDRESS_ERROR2	The destination address in the routing result returned by the CCS is incorrect.
	526	CALL_RELEASE_CAUSE_ROUTE_FAILURE	The CCS fails to return the routing result.
	528	CALL_RELEASE_CAUSE_CCS_PREVIEWCOMMITACK_FAILURE	The CCS fails to return the result of preview dialing.
	529	CALL_RELEASE_CAUSE_IVR_RESUMEACK_FAILURE	After a flow transfers a call to an agent in blocked mode, if the agent hooks on and transfers the call back to the IVR, the IVR fails to return the result.
	530	CALL_RELEASE_CAUSE_IVR_COMBINE	The control blocks to be combined are abnormal when the IVR sends a request to merge calls.
	535	CALL_RELEASE_CAUSE_CCS_ROUTEACK_FAILURE	The CCS fails to return the routing result.
	539	CALL_RELEASE_CAUSE_CCS_SWITCH	The call is released when the failover occurs between the active CCS and standby CCS.
	541	CALL_RELEASE_CAUSE_CCS_DEVICE_RESUME_ERROR	During call hang-up transfer, when the call is resumed in the suspended device after the transfer-to device is processed, the CCS sends an error.
	542	CALL_RELEASE_CAUSE_CCS_HUNG_RELEASE_ERROR	When the device to which a call is transferred in blocked mode processes the call and then releases the call, the CCS returns an error.
	543	CALL_RELEASE_CAUSE_CCS_DEVICERESUMEACK_TIMEOUT	After the device to which a call is transferred in blocked mode processes the call, the CCS times out in sending a message to notify the source device of call resuming.
	544	CALL_RELEASE_CAUSE_CCS_HUNGRELEASEACK_TIMEOUT	When the device to which a call is transferred in blocked mode processes the call and then releases the call, the CCS times out in returning the call release result.
	545	CALL_RELEASE_CAUSE_NRM_DISCONNECT	When a network call is released, the ACD returns a message indicating that the resource connection fails or an internal error occurs.
	547	CALL_RELEASE_CAUSE_NRM_NOT_NET_CALL	When a call is transferred, the re-routing result returned by the CCS is not a virtual device, but the transfer device indicator sent by the CCS is a virtual device.
	550	CALL_RELEASE_CAUSE_CCS_NET_HUNG_RELEASE_ERROR	When the device to which a network call is transferred in blocked mode processes the call and then releases the call, the CCS returns an error.
	706	DISC_CAUSE_SCP_OCCUPY_CB_FAIL	The SCP fails to occupy the control block.
	707	DISC_CAUSE_SCP_OCCUPY_CB_FAIL2	The SCP fails to occupy the control block.
	711	DISC_CAUSE_SCP_OCCUPY_CALL_FAIL	The SCP fails to occupy the call object.
	712	DISC_CAUSE_SCP_OCCUPY_CALL_FAIL2	The SCP fails to occupy the call object.
	714	DISC_CAUSE_SCP_ROUTE_FAIL	Routing failed.
	715	DISC_CAUSE_SCP_TIMEOUT	The call times out.
	725	DISC_CAUSE_VCP_RESOURCE_CONNECT_FAIL	Failed to connect to the resource.
	726	DISC_CAUSE_VCP_CB_ALLOCATION_ERROR1	Failed to allocate the control block.
	727	DISC_CAUSE_VCP_CB_ALLOCATION_ERROR2	Failed to allocate the control block.
	728	DISC_CAUSE_VCP_WRONG_ISDN_CALLNUM	Incorrect incoming video call number.
	729	DISC_CAUSE_VCP_EXCEED_ISDN_PATH_NUM_CONFIGED	The number of channels occupied by video calls reaches the maximum.
	781	DISC_CAUSE_SCP_ROUTETO_AGENT_WHEN_QUEUEIVR	The call is queued in the process, and the agent needs to notify the process to release the call when answering the call.
	1001	ICD_ERR_CTISVR_ISDN_AGENT_TYPE_INVALID=ICD_ERR_CTISVR_BEGIN	Invalid video agent type.
	1002	ICD_ERR_CTISVR_ISDN_TEL_INVALID	The phone number of the video agent is invalid.
	1003	ICD_ERR_CTISVR_ISDN_EXIST_AGENT	The video agent information already exists.
	1004	ICD_ERR_CTISVR_ISDN_EXIST_TEL	The same phone number exists in the agent information that has been signed in.
	1011	ICD_ERR_CTISVR_TRUNK_INVALID_VDN	When an outgoing call is initiated in the automatic startup process, the value of VDN is invalid.
	1012	ICD_ERR_CTISVR_TRUNK_NOT_ENOUGH_CB	The control block is insufficient during trunk interception.
	1013	ICD_ERR_CTISVR_TRUNK_CALLID_INVALID1	The CALLID is invalid when the trunk listening is started.
	1014	ICD_ERR_CTISVR_TRUNK_CALLID_INVALID2	The CALLID is invalid when the trunk monitoring is stopped.

Release Source	Cause Code	Type	Description
	1015	ICD_ERR_CTISVR_TRUNK_NO_SPY1	The trunk listening control block cannot be found when the trunk listening is started.
	1016	ICD_ERR_CTISVR_TRUNK_NO_SPY2	The trunk listening control block cannot be found when the trunk monitoring is stopped.
	1017	ICD_ERR_CTISVR_TRUNK_NO_SPY3	The trunk is not listened on.
	1018	ICD_ERR_CTISVR_TRUNK_INVALID_CB1	The control block ID is invalid. The number of control blocks is greater than the maximum number of trunks that can be listened on.
	1019	ICD_ERR_CTISVR_TRUNK_INVALID_CB2	Invalid control block. The control block number of the received message is inconsistent with that of the control block.
	1020	ICD_ERR_CTISVR_TRUNK_INVALID_STATE	The trunk listening status is invalid. When the trunk listening resource connection result is received, the trunk is not in the waiting for resource connection result state.
	1026	ICD_ERR_CTISVR_COMM_WRONG_MONITOR_ITEM_ID=ICD_ERR_CTISVR_BEGIN+25	The monitoring item ID is incorrect when the system monitoring information is obtained.
	1027	ICD_ERR_CTISVR_COMM_TOO_MANY_MONITOR_ITEM_NUM	When the system monitoring information is obtained, the maximum number of monitoring items allowed by the CTI is 6.
	1031	ICD_ERR_CTISVR_CFGMAN_INVALID_CONFIG=ICD_ERR_CTISVR_BEGIN+30	The configuration is invalid.
	1032	ICD_ERR_CTISVR_CFGMAN_TEMP_CFGTREE_NOT_EXIST	The temporary configuration tree does not exist.
	1033	ICD_ERR_CTISVR_CFGMAN_WORK_CFGTREE_ERROR	An error occurred when reading data from the work configuration tree.
	1034	ICD_ERR_CTISVR_CFGMAN_BACKUP_CFGDATA_BUSY	The standby node is busy during configuration backup.
	1036	ICD_ERR_CTISVR_OUTBOUND_NOT_ENOUGH_CB1	Failed to allocate control blocks when requesting the extended system to make outgoing calls.
	1037	ICD_ERR_CTISVR_OUTBOUND_NOT_ENOUGH_CB2	When a voice call is initiated, the control block fails to be allocated.
	1038	ICD_ERR_CTISVR_OUTBOUND_OUTTIME_WAITSETUPACK	Waiting for the SetupACK message times out during the automatic outgoing call.
	1039	ICD_ERR_CTISVR_OUTBOUND_OUTTIME_WAITALERTING	Waiting for the Alerting message times out during the automatic outgoing call.
	1040	ICD_ERR_CTISVR_OUTBOUND_OUTTIME_WAITCALLED OFFHOOK	Waiting for the off-hook message CALLED OFFHOOK times out during automatic outgoing call.
	1041	ICD_ERR_CTISVR_OUTBOUND_OUTTIME_WAITOCCUPYDEVICEACK	Waiting for the device response message OCCUPYDEVICEACK times out during automatic outgoing call.
	1042	ICD_ERR_CTISVR_OUTBOUND_OUTTIME_WAITPREVIEWACK	Waiting for the response to the preview outgoing call timed out during preview dialing.
	1043	ICD_ERR_CTISVR_OUTBOUND_OUTTIME_WAITRESULT	When the system notifies the device that the call arrives, waiting for the response message from the device times out.
	1044	ICD_ERR_CTISVR_OUTBOUND_INCORRECT_CALLBACK_ADDRESS_TYPE	When a voice callback is initiated, the destination party is not a phone number.
	1045	ICD_ERR_CTISVR_OUTBOUND_CAN_NOT_FIND_CALL	The call object cannot be found.
	1046	ICD_ERR_CTISVR_OUTBOUND_FAILED_OCCUPY_DEVICE	The agent fails to be occupied when a user previews an outgoing call or preoccupied an outgoing call.
	1047	ICD_ERR_CTISVR_OUTBOUND_FAILED1	The call object cannot be found when the call enters the queue.
	1048	ICD_ERR_CTISVR_OUTBOUND_LIMIT_CALL	The number of OBS calls is greater than the maximum number of OBS calls allowed by the VDN.
	1051	OUTBOUNDFAIL_CAUSE_SCP_NORMAL	The call object cannot be found based on the call ID when the call is in the waiting for release state.
	1056	ICD_ERR_SCP_OUTBOUND_RESOURCE_CONNECT_ERROR	The resource connection is incorrect when the preempted outgoing call is initiated.
	1101	ICD_ERR_CTISVR_OC_SPY_NO_ERROR	Inspection succeeded.
	1102	ICD_ERR_CTISVR_OC_AGENT_FAULT	The agent is invalid. 1. The inspector finds that the agent is not in the inspection operation state when the network inspection operation is stopped or the agent is switched. 2. During network QC inspection, the inspector finds that the inspector is waiting for the inspection result or the resource connection result. 3. During network interception, the inspector finds that the inspector is not in the listening or intruding state. 4. The agent is in the two-party help state, when a three-party help request is initiated, the target agent is not the target agent of the original two-party help. 5. When an agent releases a call, the agent finds that the agent is in an abnormal state.

Release Source	Cause Code	Type	Description
	1103	ICD_ERR_CTISVR_OC_CALL_FAULT	Invalid call 1. Transfer the outgoing call initiated by the platform. 2. When the agent releases a call, it is found that the incoming call ID is null (callID == CALLID_NO_USE). 3. When the agent mutes or stops the call, it is found that the call that requests to mute or unmute is not the current call. 4. When a user requests to preview an outgoing call, the system finds that the preview outgoing call does not exist or is not waiting for preview dialing. 5. During network QC, the QC call does not exist.
	1104	ICD_ERR_CTISVR_OC_STATE_FAULT	The status is incorrect. 1. Internal call. The called agent initiates a call. 2. The agent releases a call when the system is requesting announcement playing, waiting for the agent to answer the call, waiting for the response after call answer by the agent, waiting for answer voices, or waiting for the hookflash prompt tone. 3. The agent releases a call that does not exist.
	1105	ICD_ERR_CTISVR_OC_CONNECT_FAIL	Failed to connect to the resource. 1. During agent self-recording or QC recording, waiting for the resource connection result times out or the resource connection result fails to be received. 2. After the agent answers the call, waiting for the agent and call resource connection result times out. 3. The three-party resource connection fails. 4. When the two-party help or call is transferred out, failed to connect to the resource. 5. The resource connection fails when the mute mode is canceled. 6. During a network call, waiting for a call response, ringing, or off-hook message times out. 7. During network QC, waiting for the resource connection result times out or the resource connection fails.
	1109	ICD_ERR_CTISVR_OC_OCCUPY_FAIL	An error occurred when occupying the attendant.
	1111	ICD_ERR_CTISVR_OC_NO_CONF	Failed to apply for a conference.
	1112	ICD_ERR_CTISVR_OC_NO_RIGHT	No permission.
	1113	ICD_ERR_CTISVR_OC_AGENT_LOGINED	The agent has signed in repeatedly. 1. An agent repeatedly signs in and the agent types are different during the two sign-ins. 2. The agent control block fails to be allocated when the agent signs in.
	1114	ICD_ERR_CTISVR_OC_AGENT_NOT_LOGINED	The agent has not signed in.
	1115	ICD_ERR_CTISVR_OC_AGENTTYPE_NOTSUPPORT	When a network video agent signs in, the agent type is not video or network agent.
	1116	ICD_ERR_CTISVR_OC_AGENT_LOGINED_TOO_MUCH	The agent control block cannot be allocated because an excessive number of agents log in to the system.
	1124	ICD_ERR_CTISVR_OC_NO_TALKING_CALL	The agent has no call.
	1125	ICD_ERR_CTISVR_OC_NO_HOLDED_CALL	The agent does not hold the call.
	1126	ICD_ERR_CTISVR_OC_NO_SELF_CALL	During a three-party conversation, the phone agent finds that the call is released.
	1127	ICD_ERR_CTISVR_OC_CALL_NOT_EXIST	The call object does not exist.
	1128	ICD_ERR_CTISVR_OC_SPECIAL_CALL	Internal calls or special calls cannot be transferred, transferred out, internal help, mute, two-stage dialing, holding, or three-party conversation.
	1129	ICD_ERR_CTISVR_OC_HOLD_CALL_MAX	The number of held calls exceeds the maximum.
	1130	ICD_ERR_CTISVR_OC_KEEPCALL_TOO_MUCH	Too many calls are held.
	1132	ICD_ERR_CTISVR_OC_REPORT_NUM_TOO_LONG	The voice to be reported is too long.
	1133	ICD_ERR_CTISVR_OC_DOING_TALK_TRAN	The call that is being transferred cannot be internally asked.
	1134	ICD_ERR_CTISVR_OC_SKILL_QUEUE_PARAM_INCORRECT	When an announcement is played to a call, the voice is incorrect after the voice and phone number of the phone number are reported in the voice parameters of the queue.
	1135	ICD_ERR_CTISVR_OC_ADDRESS_TYPE_INCORRECT	1. The destination address is not a phone number during outgoing call and transfer-out. 2. When the call is transferred to the IVR, the called number is not the access code of the IVR.
	1136	ICD_ERR_CTISVR_OC_MODE_NOTSUPPORT	Unsupported mode
	1139	ICD_ERR_CTISVR_OC_ADD_ISDNAGENTINFO_ERROR	An error occurred when adding the ISDN agent information.
	1140	ICD_ERR_CTISVR_OC_PARAM_SIZE_INCORRECT1	ISND The parameter length is incorrect when the agent logs in.
	1141	ICD_ERR_CTISVR_OC_PARAM_SIZE_INCORRECT2	PCPhone The parameter length is incorrect when the agent logs in.

Release Source	Cause Code	Type	Description
	1142	ICD_ERR_CTISVR_OC_PARAM_SIZE_INCORRECT4	During preview dialing, the length of the phone number is greater than the maximum length of the restricted phone number.
	1143	ICD_ERR_CTISVR_OC_PARAM_SIZE_INCORRECT5	The parameter length is incorrect when the network or video agent logs in.
	1144	ICD_ERR_CTISVR_OC_PARAM_INCORRECT1	The site where the agent is located is unavailable.
	1145	ICD_ERR_CTISVR_OC_PARAM_INCORRECT2	When an agent device is added to a site, the agent cannot be found based on the agent ID.
	1146	ICD_ERR_CTISVR_OC_PARAM_INCORRECT3	The agent already exists when the agent device is added to the conference.
	1147	ICD_ERR_CTISVR_OC_PARAM_INCORRECT4	1. The destination type of the outgoing call is incorrect. 2. The PCPhone agent logs in repeatedly, and the channel is different from the original one. 3. When a user adds a phone user device to a conference, the user already exists.
	1149	ICD_ERR_CTISVR_OC_INNER_ERROR1	1. An agent who has joined another conference site cannot apply for a conference. 2. The agent fails to report voices. 3. The listening state and the barge state are switched to each other when there is no listening or barge.
	1154	ICD_ERR_CTISVR_OC_CANCEL_PREVIEW_CALL_OUT	Canceling preview dialing 1. When an agent initiates preview dialing, the called number is not a phone number or the length of the call number is 0. 2. When the OutBound initiates a preview outgoing call, the agent to be occupied does not exist.
	1155	ICD_ERR_CTISVR_OC_TIMEOUT_REQUEST_PREVIEW_CALL_OUT	Waiting for the agent to preview the outgoing call times out.
	1159	ICD_ERR_CTISVR_OC_AGENT_INVALID_LOGIN_PARAM	The parameter of the agent sign-in message is invalid. The phone number of the agent who signs in must be at least one digit and cannot be the system access code.
	1160	ICD_ERR_CTISVR_OC_NO_HOLDED_CALL1	In the three-party calls established during unhold, the current call is not empty but the held call is empty.
	1161	ICD_ERR_CTISVR_OC_NO_HOLDED_CALL_AND_TALKING_CALL	In the three-way calls established during unhold, the current call and held call are both empty or not.
	1162	ICD_ERR_CTISVR_OC_EXCEED_RESOURCE_CAPABILITY	Exceeded the resource capability. When an agent applies for a conference, the number of channels applied for is greater than 20.
	1201	ICD_ERR_CTISVR_OC_TIMEOUT01	Waiting for resource connection timed out during two-stage dialing.
	1202	ICD_ERR_CTISVR_OC_TIMEOUT02	Waiting for the CCS agent sign-in response times out.
	1203	ICD_ERR_CTISVR_OC_TIMEOUT03	Waiting for the CCS agent logout response times out.
	1204	ICD_ERR_CTISVR_OC_TIMEOUT04	Waiting for announcement result timed out.
	1205	ICD_ERR_CTISVR_OC_TIMEOUT05	When a call is transferred out or transferred out, waiting for the outgoing call result times out.
	1207	ICD_ERR_CTISVR_OC_TIMEOUT07	During a common outgoing call, waiting for the outgoing call result times out.
	1208	ICD_ERR_CTISVR_OC_TIMEOUT08	Waiting for off-hook timed out during internal help seeking.
	1209	ICD_ERR_CTISVR_OC_TIMEOUT09	During an internal call, waiting for off-hook times out.
	1210	ICD_ERR_CTISVR_OC_TIMEOUT10	During a common outgoing call, waiting for off-hook times out.
	1211	ICD_ERR_CTISVR_OC_TIMEOUT11	Waiting for off-hook times out during transfer-out.
	1212	ICD_ERR_CTISVR_OC_TIMEOUT12	Waiting for help or transfer-out times out.
	1213	ICD_ERR_CTISVR_OC_TIMEOUT13	The resource connection times out when the mute mode is canceled.
	1214	ICD_ERR_CTISVR_OC_TIMEOUT14	The resource connection times out when the call is muted.
	1215	ICD_ERR_CTISVR_OC_TIMEOUT15	During call unhold, resource connection times out.
	1216	ICD_ERR_CTISVR_OC_TIMEOUT16	When the connection is held, the resource connection times out.
	1217	ICD_ERR_CTISVR_OC_TIMEOUT17	During transfer-out, waiting for the resource connection result of the call between the subscriber and the transfer-out times out.
	1218	ICD_ERR_CTISVR_OC_TIMEOUT18	After the called party picks up the phone, the resource connection times out.
	1219	ICD_ERR_CTISVR_OC_TIMEOUT19	After the called party picks up the phone, the resource connection times out.
	1220	ICD_ERR_CTISVR_OC_TIMEOUT20	During two-stage dialing, the 1220 resource connection times out.

Release Source	Cause Code	Type	Description
	1221	ICD_ERR_CTISVR_OC_TIMEOUT21	Third-party resource connection timed out during transfer-out.
	1222	ICD_ERR_CTISVR_OC_TIMEOUT22	Third-party resource connection timed out during help seeking.
	1223	ICD_ERR_CTISVR_OC_TIMEOUT23	Third-party resource connection times out during a common three-party call.
	1257	ICD_ERR_CTISVR_OC_DISCONNECT007	The agent status is incorrect after the resource connection result is received during transfer-out.
	1258	ICD_ERR_CTISVR_OC_DISCONNECT008	The call is still held after the agent is checked out.
	1259	ICD_ERR_CTISVR_OC_DISCONNECT009	The status of the called party is invalid when the called party is ringing.
	1260	ICD_ERR_CTISVR_OC_DISCONNECT010	When the call is transferred out, the called party rings but the current call does not exist.
	1264	ICD_ERR_CTISVR_OC_DISCONNECT014	During internal help seeking or transfer-out, the agent actively releases the call.
	1265	ICD_ERR_CTISVR_OC_DISCONNECT015	When the agent is suspended and transferred to the automatic state, the call does not exist when the call is resumed to the man-hour.
	1266	ICD_ERR_CTISVR_OC_DISCONNECT016	The resource connection fails after two-stage dialing.
	1267	ICD_ERR_CTISVR_OC_DISCONNECT017	When the connection result of the mute resource is received, the current call does not exist.
	1268	ICD_ERR_CTISVR_OC_DISCONNECT018	When receiving the result of canceling the mute resource connection, the system finds that the current call does not exist.
	1269	ICD_ERR_CTISVR_OC_DISCONNECT019	During call unhold, resource connection fails.
	1270	ICD_ERR_CTISVR_OC_DISCONNECT020	The resource connection fails when the connection is held, and the current call is disconnected.
	1271	ICD_ERR_CTISVR_OC_DISCONNECT021	The resource connection fails when the connection is held, and the held call is disconnected.
	1272	ICD_ERR_CTISVR_OC_DISCONNECT022	The resource connection fails when an agent answers an incoming call.
	1273	ICD_ERR_CTISVR_OC_DISCONNECT023	When a resource connection is received during transfer-out, the current call is abnormal and the current call is disconnected.
	1274	ICD_ERR_CTISVR_OC_DISCONNECT024	When a resource connection is received during transfer-out, the held call is abnormal, and the held call is disconnected.
	1277	ICD_ERR_CTISVR_OC_DISCONNECT027	The resource connection fails after the user picks up the phone.
	1278	ICD_ERR_CTISVR_OC_DISCONNECT028	Failed to connect to the resource.
	1279	ICD_ERR_CTISVR_OC_DISCONNECT029	The resource connection fails after the three-party connection fails.
	1280	ICD_ERR_CTISVR_OC_DISCONNECT030	The agent is suspended and resumed, and the resource connection fails.
	1281	ICD_ERR_CTISVR_OC_DISCONNECT031	The agent is released during a call.
	1282	ICD_ERR_CTISVR_OC_DISCONNECT032	The three-party call releases the current call.
	1283	ICD_ERR_CTISVR_OC_DISCONNECT033	Releasing a Hold Call When a Three-Party Call Is Released
	1284	ICD_ERR_CTISVR_OC_DISCONNECT034	Disconnecting a Call from a Three-Party Call
	1285	ICD_ERR_CTISVR_OC_DISCONNECT035	Disconnecting a held call from a three-party conversation
	1286	ICD_ERR_CTISVR_OC_DISCONNECT036	The agent releases the call after the agent picks up the phone.
	1287	ICD_ERR_CTISVR_OC_DISCONNECT037	The agent releases the call when waiting for call answer during call-out or transfer-out.
	1288	ICD_ERR_CTISVR_OC_DISCONNECT038	The call is released when the resource connection result is waiting.
	1289	ICD_ERR_CTISVR_OC_DISCONNECT039	When waiting for the three-party resource connection result, the current or held call is null and the current call is disconnected.
	1290	ICD_ERR_CTISVR_OC_DISCONNECT040	When waiting for the three-party resource connection result, the current or held call is null and the held call is disconnected.
	1291	ICD_ERR_CTISVR_OC_DISCONNECT041	When waiting for the three-party resource connection result, the current call is disconnected.
	1292	ICD_ERR_CTISVR_OC_DISCONNECT042	When an agent releases a call, the call ID is invalid. The call is released.
	1293	ICD_ERR_CTISVR_OC_DISCONNECT043	The resource connection initiated by the two-stage dialing times out, and the call is released.

Release Source	Cause Code	Type	Description
	1294	ICD_ERR_CTISVR_OC_DISCONNECT044	1. Waiting for the response message times out. The call is released. 2. The call duration exceeds the maximum allowed duration.
	1295	ICD_ERR_CTISVR_OC_DISCONNECT045	The duration of the two-party help or call transfer exceeds the maximum duration allowed for the call.
	1296	ICD_ERR_CTISVR_OC_DISCONNECT046	The three-party call times out, and the current call is disconnected.
	1297	ICD_ERR_CTISVR_OC_DISCONNECT047	The three-party call times out, and the held call is disconnected.
	1298	ICD_ERR_CTISVR_OC_DISCONNECT048	Waiting for voice playing times out, and the corresponding call does not exist.
	1299	ICD_ERR_CTISVR_OC_DISCONNECT049	The call is released when waiting for the alerting message times out.
	1300	ICD_ERR_CTISVR_OC_DISCONNECT050	The call is an internal call or an outgoing call. Waiting for the alerting message times out. The call is released.
	1301	ICD_ERR_CTISVR_OC_DISCONNECT051	The intermediate status of successful transfer, three-party transfer, call transfer, resource connection, or off-hook notification times out. The current call is disconnected.
	1302	ICD_ERR_CTISVR_OC_DISCONNECT052	Success transfer, three-party transfer, or call transfer. The intermediate status of resource connection and off-hook notification times out. Failed to retrieve the held call. Release the held call.
	1305	ICD_ERR_CTISVR_OC_DISCONNECT055	The intermediate status of the common outgoing call, resource connection, and off-hook notification times out. The current call is disconnected.
	1306	ICD_ERR_CTISVR_OC_DISCONNECT056	Common outgoing call. The intermediate status of the resource connection and off-hook notification times out. The current call does not exist. The current call is released.
	1307	ICD_ERR_CTISVR_OC_DISCONNECT057	Waiting for the answer_ack message times out. The current call is disconnected.
	1308	ICD_ERR_CTISVR_OC_DISCONNECT058	The system releases the current call when waiting for the call to pick up the phone times out and the current call does not exist.
	1309	ICD_ERR_CTISVR_OC_DISCONNECT059	The system releases the current call when waiting for the off-hook of the internal call times out.
	1310	ICD_ERR_CTISVR_OC_DISCONNECT060	Outgoing call waiting times out, and the current call is disconnected.
	1311	ICD_ERR_CTISVR_OC_DISCONNECT061	The call is successfully transferred or the call is transferred to the waiting call. The call times out. The call is released.
	1312	ICD_ERR_CTISVR_OC_DISCONNECT062	When the three-party call transfer to the waiting call times out, the call is released.
	1313	ICD_ERR_CTISVR_OC_DISCONNECT063	In other transfer states, waiting for the call to pick up the phone times out, and the outgoing call is released.
	1314	ICD_ERR_CTISVR_OC_DISCONNECT064	Waiting for the transfer response timed out. The current call is null. The current call is disconnected.
	1315	ICD_ERR_CTISVR_OC_DISCONNECT065	In normal cases, waiting for resource connection times out and the current call is disconnected.
	1316	ICD_ERR_CTISVR_OC_DISCONNECT066	After the agent answers the call, the resource connection times out and the current call is disconnected.
	1317	ICD_ERR_CTISVR_OC_DISCONNECT067	Unmuting waiting for the resource connection timed out. The current call is disconnected.
	1318	ICD_ERR_CTISVR_OC_DISCONNECT068	During call muting, waiting for resource connection times out and the current call is disconnected.
	1319	ICD_ERR_CTISVR_OC_DISCONNECT069	During call unholding, waiting for resource connection times out and the current call is disconnected.
	1320	ICD_ERR_CTISVR_OC_DISCONNECT070	The connection is waiting for resource connection timeout. The current call is disconnected.
	1321	ICD_ERR_CTISVR_OC_DISCONNECT071	During call hold, waiting for resource connection times out and the call is disconnected.
	1322	ICD_ERR_CTISVR_OC_DISCONNECT072	During transfer-out, waiting for resource connection times out and the call is disconnected.
	1323	ICD_ERR_CTISVR_OC_DISCONNECT073	During transfer-out, waiting for resource connection times out, the held call does not exist, and the held call is released.
	1324	ICD_ERR_CTISVR_OC_DISCONNECT074	When the user picks up the phone, waiting for the resource connection times out, and the held call does not exist, the call is disconnected.
	1325	ICD_ERR_CTISVR_OC_DISCONNECT075	After the three-party connection fails, the two parties are connected or the agent is suspended and resumed. Waiting for

Release Source	Cause Code	Type	Description
			the resource connection times out. The current call is disconnected.
	1326	ICD_ERR_CTISVR_OC_DISCONNECT076	The resource connection for two-stage dialing is implemented. Waiting for the resource connection times out. The current call is disconnected.
	1327	ICD_ERR_CTISVR_OC_DISCONNECT077	Waiting for the three-party resource connection times out and the current call does not exist. The current call is released.
	1328	ICD_ERR_CTISVR_OC_DISCONNECT078	Waiting for the three-party resource connection times out and the held call does not exist. The held call is disconnected.
	1348	ICD_ERR_CTISVR_OC_DISCONNECT098	The CCS forcibly signs out the agent and disconnects the current call of the agent.
	1350	ICD_ERR_CTISVR_OC_DISCONNECT100	The agent channel breaks down and the call is disconnected.
	1357	ICD_ERR_CTISVR_OC_DISCONNECT116	Failover occurs and the current call is disconnected.
	1358	ICD_ERR_CTISVR_OC_DISCONNECT117	Failover occurs and the current call is disconnected.
	1364	ICD_ERR_CTISVR_OC_CONFMANAGE_NOT_EXIST	When the CP records and plays voices, it finds that the CP conference management party of the CP does not exist.
	1365	ICD_ERR_CTISVR_OC_CONF_NOT_EXIST	When the CP records and plays voices, the CP conference ID of the CP is incorrect.
	1366	ICD_ERR_CTISVR_OC_CONF_ERROR	When the CP records voices, it is found that the agent is in the recording or playing state.
	1367	ICD_ERR_CTISVR_OC_STATE_ERROR	During recording, the agent status is invalid.
	1371	ICD_ERR_CTISVR_IVR_NOT_ENOUGH_CCCNODE	When the IVR logs in to the CTI Server, it is found that there is insufficient client control block allocation.
	1372	ICD_ERR_CTISVR_IVR_NODE_NOT_LOGIN	The client node is not registered.
	1373	ICD_ERR_CTISVR_IVR_NO_CALLED_INNO	When the IVR process is started or the OBS requests to start the IVR process, it is found that the process access code is not loaded by any IVR.
	1374	ICD_ERR_CTISVR_IVR_INTER_ERROR	Internal error 1. The requested call does not exist when the flow tracing information is obtained. 2. The requested call does not exist or is set abnormally when the flow track is set. 3. The flow request is transferred to the specified device or the rerouting is initiated, the specified call does not exist. 4. When the IVR registers the access code, the Vdn parameter in the message is abnormal.
	1375	ICD_ERR_CTISVR_IVR_DATASIZE_TOO_LONG	When the IVR starts the automatic startup process, the length of the corresponding access code is too long, or the length of the data contained in the IVR process started by the OBS is too long.
	1376	ICD_ERR_CTISVR_IVR_TOO_MUCH_INNO	Too many access codes are registered.
	1377	ICD_ERR_CTISVR_IVR_TOO_LONG_INNO	The registered access code is too long.
	1378	ICD_ERR_CTISVR_IVR_NOT_SUPPORT_MODE	The transfer mode is not supported.
	1380	ICD_ERR_CTISVR_IVR_QUERY_DEVICE_DESCRIPTION_FAILED	Failed to query the IVR device description.
	1381	ICD_ERR_CTISVR_IVR_SCP_HUNGUPACK_ERROR	IVR call transfer in blocked mode failed.
	1382	ICD_ERR_CTISVR_IVR_NOT_GET_INNO	Failed to obtain the access code configuration.
	1391	ICD_ERR_CTISVR_IVR_DISCONNECT1	Invalid call ID.
	1392	ICD_ERR_CTISVR_IVR_DISCONNECT2	The call is released because the response to the incoming call notification from the client times out.
	1393	ICD_ERR_CTISVR_IVR_DISCONNECT3	Waiting for the client ringing times out.
	1394	ICD_ERR_CTISVR_IVR_DISCONNECT4	Waiting for the Setup_ACK message from the client times out when the call is not an internal or special call.
	1395	ICD_ERR_CTISVR_IVR_DISCONNECT5	Waiting for the Setup_ACK message from the client times out during internal and special calls.
	1396	ICD_ERR_CTISVR_IVR_DISCONNECT6	Waiting for the client to return the outgoing call result times out.
	1397	ICD_ERR_CTISVR_IVR_DISCONNECT7	When a call is allocated to the IVR, the value of VdnID is invalid.
	1398	ICD_ERR_CTISVR_IVR_DISCONNECT8	The IVR that loads the access code is not found.
	1399	ICD_ERR_CTISVR_IVR_DISCONNECT9	Invalid IVR access code.
	1400	ICD_ERR_CTISVR_IVR_DISCONNECT10	The call ID is invalid when the call is transferred from IVR to an agent in blocked mode.
	1401	ICD_ERR_CTISVR_IVR_DISCONNECT11	The call ID in the SetUpACK message sent by the SCP to the CIVR is invalid.

Release Source	Cause Code	Type	Description
	1402	ICD_ERR_CTISVR_IVR_DISCONNECT12	The call ID in the AnswerACK message sent by the SCP to the CIVR is invalid.
	1403	ICD_ERR_CTISVR_IVR_DISCONNECT13	The call ID in the Disconnect message sent by the SCP to the CIVR is invalid.
	1404	ICD_ERR_CTISVR_IVR_DISCONNECT14	The call ID in the Release message sent by the SCP to the CIVR is invalid.
	1405	ICD_ERR_CTISVR_IVR_DISCONNECT15	The call ID in the ResourceConnectRes message sent by the SCP to the CIVR is invalid.
	1406	ICD_ERR_CTISVR_IVR_DISCONNECT16	The call ID in the control block is invalid when the Alerting message sent by the client is received.
	1407	ICD_ERR_CTISVR_IVR_DISCONNECT17	The VdnID in the Setup message sent by the client is invalid.
	1409	ICD_ERR_CTISVR_IVR_DISCONNECT19	When the CollectDigit message sent by the client is received, the corresponding call does not exist.
	1410	ICD_ERR_CTISVR_IVR_DISCONNECT20	Waiting for call release timed out.
	1411	ICD_ERR_CTISVR_IVR_DISCONNECT21	The control fast status of the Disconnect message sent by the SCP to the CIVR is invalid.
	1412	ICD_ERR_CTISVR_IVR_DISCONNECT22	When the SCP sends a Disconnect message to the CIVR, the IVR access code for controlling the fast state is invalid.
	1413	ICD_ERR_CTISVR_IVR_DISCONNECT23	The handshake between the CTI Server and the IVR times out.
	1418	ICD_ERR_CTISVR_IVR_DISCONNECT28	The call duration times out.
	1422	ICD_ERR_CTISVR_RES_DIS_CAUSE2	In the conference recording mode of the network board, the resources are disconnected before the voice of the conference object is played.
	1423	ICD_ERR_CTISVR_RES_DIS_CAUSE3	In the listening mode of the network board, the resources are disconnected before the voice of the conference object is played.
	1425	ICD_ERR_CTISVR_RES_DIS_CAUSE5	The call resources are disconnected.
	1426	ICD_ERR_CTISVR_RES_DIS_CAUSE6	When the agent is listening, the agent cancels the listening and the resources are disconnected.
	1427	ICD_ERR_CTISVR_RES_DIS_CAUSE7	When the agent is being listened on, the listening of the agent is canceled, and resources are disconnected.
	1433	ICD_ERR_CTISVR_RES_DIS_CAUSE13	The two-stage dialing resource is disconnected.
	1434	ICD_ERR_CTISVR_RES_DIS_CAUSE14	The agent stops responding or the handshake times out. The agent object is reclaimed and the resources are disconnected.
	1435	ICD_ERR_CTISVR_RES_DIS_CAUSE15	The QC agent requests to stop playing voices and the resources are disconnected.
	1436	ICD_ERR_CTISVR_RES_DIS_CAUSE16	The QC agent requests to stop recording and the resources are disconnected.
	1437	ICD_ERR_CTISVR_RES_DIS_CAUSE17	The agent stops playing voices and the resources are disconnected.
	1438	ICD_ERR_CTISVR_RES_DIS_CAUSE18	The agent stops recording, and the resources are disconnected.
	1439	ICD_ERR_CTISVR_RES_DIS_CAUSE19	Stop listening or monitoring, and resources are disconnected.
	1440	ICD_ERR_CTISVR_RES_DIS_CAUSE20	Stop the insertion and disconnect the resource.
	1441	ICD_ERR_CTISVR_RES_DIS_CAUSE21	Resources are disconnected when an incoming call is intercepted.
	1442	ICD_ERR_CTISVR_RES_DIS_CAUSE22	Resources are disconnected during forcible logout.
	1444	ICD_ERR_CTISVR_RES_DIS_CAUSE24	The call is released, and resources are disconnected.
	1445	ICD_ERR_CTISVR_RES_DIS_CAUSE25	The resource is disconnected when the agent answers the call.
	1446	ICD_ERR_CTISVR_RES_DIS_CAUSE26	The current call resource is disconnected when the outgoing call is waiting for ringing.
	1447	ICD_ERR_CTISVR_RES_DIS_CAUSE27	The resource is disconnected when the resources of the two parties are connected.
	1448	ICD_ERR_CTISVR_RES_DIS_CAUSE28	1. When a two-party help request is initiated, a three-party help request is initiated. The original connection is disconnected. 2. When a two-party help request is transferred, the current help call is released. 3. When the three-party resource connection result is waiting, the call is released and resources are disconnected.
	1454	ICD_ERR_CTISVR_RES_DIS_CAUSE34	Resources are disconnected during announcement playing.
	1455	ICD_ERR_CTISVR_RES_DIS_CAUSE35	The resource is disconnected when the hang-up transfer is successful.
	1456	ICD_ERR_CTISVR_RES_DIS_CAUSE36	Resources are disconnected during a three-party call.

Release Source	Cause Code	Type	Description
	1457	ICD_ERR_CTISVR_RES_DIS_CAUSE37	The call duration exceeds the maximum, and the resource is disconnected.
	1458	ICD_ERR_CTISVR_RES_DIS_CAUSE38	During successful transfer, call transfer, or three-party transfer, the intermediate status of resource connection and off-hook notification times out, and resources are disconnected.
	1459	ICD_ERR_CTISVR_RES_DIS_CAUSE39	The intermediate status of the common outgoing call resource connection and off-hook notification times out, and resources are disconnected.
	1460	ICD_ERR_CTISVR_RES_DIS_CAUSE40	Waiting for the response to the response times out. The resource is disconnected.
	1461	ICD_ERR_CTISVR_RES_DIS_CAUSE41	During an outgoing call, waiting for the call to pick up the phone times out and resources are disconnected
	1462	ICD_ERR_CTISVR_RES_DIS_CAUSE42	When the call is transferred out, waiting for the call to pick up the phone times out and the resource is disconnected.
	1463	ICD_ERR_CTISVR_RES_DIS_CAUSE43	When the connection is held, the resources are disconnected.
	1464	ICD_ERR_CTISVR_RES_DIS_CAUSE44	When the connection is held, the resources are disconnected.
	1465	ICD_ERR_CTISVR_RES_DIS_CAUSE45	The resource is disconnected when a three-party call is requested.
	1468	ICD_ERR_CTISVR_RES_DIS_CAUSE48	The call is forwarded successfully. When the called party picks up the phone, the agent is disconnected from the outgoing call.
	1469	ICD_ERR_CTISVR_RES_DIS_CAUSE49	The resource is disconnected when the transfer-out fails.
	1472	ICD_ERR_CTISVR_RES_DIS_CAUSE52	When a call is transferred, the resource is disconnected when the agent releases the call.
	1473	ICD_ERR_CTISVR_RES_DIS_CAUSE53	During success transfer, call transfer, and three-party transfer, the call transfer response fails and resources are disconnected.
	1474	ICD_ERR_CTISVR_RES_DIS_CAUSE54	The current agent is disconnected when a held call is connected.
	1475	ICD_ERR_CTISVR_RES_DIS_CAUSE55	The call is converted into a response. The agent is disconnected from the current call.
	1476	ICD_ERR_CTISVR_RES_DIS_CAUSE56	During the QC recording, the agent is connected to the listening or supervising call, and the recording resources are disconnected.
	1477	ICD_ERR_CTISVR_RES_DIS_CAUSE57	During the recording of an agent, the agent is connected to the listening or supervising call, and the recording resources are disconnected.
	1478	ICD_ERR_CTISVR_RES_DIS_CAUSE58	The call interception is switched to the insertion mode, and resources are disconnected.
	1479	ICD_ERR_CTISVR_RES_DIS_CAUSE59	The call is switched to the listening state, and resources are disconnected.
	1482	ICD_ERR_CTISVR_RES_DIS_CAUSE62	Network listening fails, and resources are disconnected.
	1483	ICD_ERR_CTISVR_RES_DIS_CAUSE63	Waiting for the ACD response times out or waiting for the UIS response times out.
	1486	ICD_ERR_CTISVR_NRM_DISCONNECT01	The network call fails to receive the resource connection result from the SCP.
	1487	ICD_ERR_CTISVR_NRM_DISCONNECT02	During a network call, the NRM receives an incoming call disconnection message from the SCP when the system is waiting for call answer by the agent, call-out ringing, call answer by the called party, call-out response, resource connection result, call start, and resource connection status after call answer.
	1488	ICD_ERR_CTISVR_NRM_DISCONNECT03	The network call is received and the outgoing message is disconnected due to a busy line.
	1490	ICD_ERR_CTISVR_NRM_DISCONNECT05	The network call waiting for the SETUP_ACK/ALERTING/ANSWER_ACK/CONNECT_RESULT message times out.
	1491	ICD_ERR_CTISVR_NRM_DISCONNECT06	The network call is transferred and the call is released.
	1492	ICD_ERR_CTISVR_NRM_DISCONNECT07	The network call duration exceeds the maximum.
	1493	ICD_ERR_CTISVR_NRM_DISCONNECT08	The network call waiting for the NOTIFY message from the SCP times out.
	1494	ICD_ERR_CTISVR_NRM_DISCONNECT09	The network call waiting for the off-hook message of the called party times out.
	1501	ICD_ERR_CTISVR_NRM_DISCONNECT16	CVNR The inspected agent cannot be found, or the resource connection result fails to be received or the CVNR status is incorrect.
	1506	ICD_ERR_CTISVR_NRM_PREPARE_CHANNEL_FAULT	CVNR Waiting for the available message of the agent channel times out or the agent channel is unavailable.

Release Source	Cause Code	Type	Description
	1507	ICD_ERR_CTISVR_TOMUCH_OMDTRACE_TASK,	The number of OMD tracing tasks exceeds the maximum (5).
	1509	ICD_ERR_CTISVR_CALL_STATE_ERROR,	The call status is incorrect.
	1508	ICD_ERR_CTISVR_DEVICE_OCCUPIED	The device to be operated has been occupied.
	1510	ICD_ERR_CTISVR_TRI_DISCONNECT1, //1510	The three-party call is disconnected from one of the two parties.
	1511	ICD_ERR_CTISVR_TRI_DISCONNECT2, //1511	The three-party call is disconnected from the other party.
	1512	ICD_ERR_CTISVR_NOT_SUPPORT_CP_CONF,	The platform does not support CP conferences.
	1514	ICD_ERR_NOT_NET_CALL_IN,	The call is not an incoming call.
	1515	ICD_ERR_CTISVR_OC_RECORD_USERCALL_NOTIN_CP,	1515 The call is not in the CP conference.
	1516	ICD_ERR_CTISVR_OC_RECORD_USERCALL_TIME_OUT,	Waiting for ACD response timed out when recording calls to users.
	1517	ICD_ERR_CTISVR_OC_USERCALL_ALREADY_RECORD	The channel has been recorded. The channel recording cannot be initiated again.
	1519	ICD_ERR_NOT_SUPPORT_NET_CALL_QUEUE,	The call center does not support the queuing of network calls in the original call center.
	1551	ICD_ERR_NOT_SUPPORT_CALLOUT_NO_PREFIX	Invalid outgoing call prefix.
	1552	ICD_ERR_NAME_CONF_MID_INVALID	Invalid module number.
	1553	ICD_ERR_ACD_NO_RESOURCE	The ACD does not have conference resources.
	22000	ROUTE_FAILURE_CAUSE_IS_QUEUE_OVERFLOW	The call is released when the queue overflows.
	22001	ROUTE_FAILURE_CAUSE_IS_WHEN_CANCEL_QUEUE	Failed to route the call when the queuing is canceled.
	22002	ROUTE_FAILURE_CAUSE_IS_WHEN_QUEUE_TIME_OUT	Routing fails when queuing times out.
	35003	ICD_ERR_OCCUPY_RP_TASK_FAIL	Failed to occupy the recording or playing task.
	35004	ICD_ERR_OCCUPY_RESOURCE_FAIL	Failed to occupy the resource.
	35005	ICD_ERROR_WAIT_ACD_RES_TIMEOUT	Waiting for the response from the ACD times out.
	35006	ICD_ERR_CTISVR_OC_OCCUPY_PLAY_TASK_FAIL	Failed to occupy the video playing task.
	35010	ICD_ERR_CTISVR_RP_RELEASE_CALL_DISCONNECT	This operation fails because the task is released due to call release.
	35014	ICD_ERR_CTISVR_TASK_ABNORMAL_END	The task is terminated abnormally.
	35019	ICD_ERR_CTISVR_NOT_SUPPORT_API	Unsupported API interfaces, for example, cti5.0, cti3.0, and cti1.0 are not supported.
	35024	ICD_ERR_UAP_RETURN_ERROR,	The UAP returns a message indicating that the operation fails. The cause is unknown.
	35025	ICD_ERR_CTISVR_MRFCALL_RELEASE,	The virtual call of the site on the MRF side is released. Therefore, the real site is released.
	35026	ICD_ERR_CTISVR_MRFOWNER_RELEASE,	The conference control party on the MRF side releases the conference. Therefore, the actual site is released.
	35027	ICD_ERR_CTISVR_PREVIEW_CALLED_ERR,	The called number entered during preview dialing is invalid. The client does not transfer the original number.
	35029	ICD_ERR_RP_TASK_IP_SNAP_RECORD_EXIST,	Recording already exists.
	35030	ICD_ERR_RP_TASK_IP_SNAP_RECORD_NOEXIST,	No IP recording task exists.
	35031	ICD_ERR_CTISVR_OC_OCCUPY_RECORD_TASK_FAIL,	Failed to occupy the task control block.
	35033	ICD_ERR_CTISVR_OC_WAIT_UAP_TIMEOUT,	Waiting for the IP recording response from the UAP times out.
	35034	ICD_ERR_INVALID_CALL_ID,	Invalid callid.
	35035	ICD_ERR_NO_RESOURCE_FOR_TREATMENT,	No resource control block.
	35036	ICD_ERR_UAP_OPERATION_ERROR,	The UAP returns a failure response.
	35037	ICD_ERR_CALL_NOT_IN_ROUTEOUT_ERROR,	The call request is forwarded to the external IVR, but the call is not in the outgoing call module.
	35038	ICD_ERR_ROUTEOUT_TIMEOUT,	The call request is forwarded to the external IVR. The call times out.

Parent topic: [Appendix](#)

Cause Why a Call Accesses or Leaves the Device

Table 1

Cause code	Description	Cause code	Description
0	Normal access/transfer.	27	The called party rejects the call.
1	Overflow transfer.	28	The call is successfully transferred to a skill queue.
2	Timeout transfer.	29	The three-party conversation is transferred to a skill queue.
3	Transfer on no agent.	30	Transferring the call in the success transfer mode times out.
4	Transfer on queue cancellation.	31	Transferring the three-party conversation to a skill queue times out.
5	Transfer because the agent does not answer the call.	34	If call timeout or queuing on busy or overflow occurs, the network call fails.
6	Resume a suspended call.	35	The network call is directed to its original call center for queuing.
7	Connecting a held call	36	The queued call is re-routed.
8	Three-party help.	37	The call accesses the CDN through call routing.
9	Picking a held call.	38	The call accesses the CDN through agent consultation.
10	Three-party call.	39	The CDN properly returns a routing result.
11	The party requesting internal help releases the call.	40	CDN routing times out.
12	The call is intercepted.	41	An agent cancels the consultation call, or the routing fails.
13	The call is picked up.	42	The call accesses the PGR because CDN routing times out.
14	The analysis of the called is not configured.	43	The call is properly returned by the CDN and is routed to the PGR.
15	The user releases the call.	44	The call accesses the PGR through inbound routing.
16	The agent releases the call.	45	The call accesses the PGR through agent consultation.
17	The call is transferred out.	46	The agent is unreachable. The CDN reroutes the call.
18	The call is held.	47	The call is waiting in multiple queues.
19	An internal processing error occurs.	48	The primary-queue call is answered by numbers in the secondary queue.
20	The called party is busy.	50	The agent rejects the call.
22	The mobile phone is switched off.	51	A user call joins in a conference call.
23	The mobile phone is out of the service area.	52	A conference chairperson proactively releases a conference, or the conference is released due to a CCS exception.
24	The called number does not exist.	53	The participant is removed from the conference.
25	The ACD cannot distribute any resources for the call.	54	The call is transferred when the call completion rate is less than the threshold.
26	The user does not answer the call.	88	The user releases the call after the call is answered by the agent.
89	The agent has invoked the call answer interface, but the user releases the call before the call is answered by the agent.	—	—

Parent topic: [Appendix](#)

Voice Interface (ActiveX)

- [About This Document](#)
- [Overview](#)
- [Data Types](#)
- [Interface Description](#)
- [Event Description](#)
- [Return Codes](#)

Copyright © Chengdu TD-Tech Co., Ltd.

About This Document

[Intended Audience](#)

[Symbol Conventions](#)

[Change History](#)

Parent topic: [Voice Interface \(ActiveX\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Intended Audience

This document is intended for:

- Development personnel who are proficient in integrating the Voice Object Linking and Embedding Control eXtension (OCX) multimedia collaboration capability

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Symbol Conventions

The symbols that may be found in this document are defined as follows.

Symbol	Description
	Indicates an imminently hazardous situation which, if not avoided, will result in death or serious injury.
	Indicates a potentially hazardous situation which, if not avoided, could result in death or serious injury.
	Indicates a potentially hazardous situation which, if not avoided, may result in minor or moderate injury.
	Indicates a potentially hazardous situation which, if not avoided, could result in equipment damage, data loss, performance deterioration, or unanticipated results. NOTICE is used to address practices not related to personal injury.
	Calls attention to important information, best practices and tips. NOTE is used to address information not related to personal injury, equipment damage, and environment deterioration.

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Change History

- [V100R023C00](#)
- [V100R022C00](#)
- [V600R019C00](#)
- [V600R006C10](#)
- [V200R001C80](#)

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V100R023C00

V600R019C00SPC630

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00SPC630

Compared with V600R019C00SPC591, V600R019C00SPC630 does not include any changes.

Parent topic: [V100R023C00](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V100R022C00

V600R019C00SPC590

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00SPC590

Compared with V600R019C00SPC580, V600R019C00SPC590 does not include any changes.

Parent topic: [V100R022C00](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00

V600R019C00

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00

No change is made in CloudIPCC V600R019C00 compared with CloudIPCC V600R006C10.

Parent topic: [V600R019C00](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R006C10

V600R006C10

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R006C10

The following tables describe changes made in IPCC V600R006C10 compared with IPCC V200R001C80SPC700.

Interface Changes

Table 1 List of new interfaces

Interface Type	Changes
Call interfaces	CallEx
	AnonymousCallEx
	AnswerEx
	SetVideoWindow
	SetVideoWindowEx
Device interfaces	GetVideoDevices
	SnapShot
	SetVideoDeviceIndex
	OpenPreview
	ClosePreview

Table 2 List of modified interfaces

Interface Type	Changes
Call interfaces	Call : deprecated and replaced by CallEx.
	AnonymousCallEx : deprecated and replaced by AnonymousCallEx.
	Answer : deprecated and replaced by AnswerEx.

Event Changes

Table 3 List of new events

Event Type	Changes
Device events	VoiceSnapshotResultEvent

Table 4 List of modified events

Event Type	Event Name	Changes
Call events	VoiceTalkOutgoingEvent	Added the isVideo field.
	VoiceTalkAlertingEvent	
	VoiceTalkRingBackEvent	
	VoiceTalkConnectedEvent	
	VoiceTalkReleaseEvent	

Document Content Changes

Table 5 Document content changes

Location	Change Type	Changes	Reason
SetConfig	Add	CALL_D_CFG_DISABLE_AUTO_HOLD	Multi-call capability configuration in local conferences.
	Add	CALL_D_CFG_ACCOUNT_PASSWORD_TYPE	Account password type configuration.
	Add	CALL_D_CFG_VIDEO_FRAMERATE	Video framerate configuration.
GetConfig	Add	CALL_D_CFG_DISABLE_AUTO_HOLD	Multi-call capability configuration in local conferences.
	Add	CALL_D_CFG_ACCOUNT_PASSWORD_TYPE	Account password type configuration.
Return Codes	Add	Return code 16	Scenario adding.

Parent topic: [V600R006C10](#)

V200R001C80

[V200R001C80SPC700](#)

[V200R001C80SPC600](#)

[V200R001C80SPC500](#)

[V200R001C80SPC400](#)

[V200R001C80SPC300](#)

[V200R001C80SPC200](#)

[V200R001C80SPC100](#)

[V200R001C80](#)

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC700

The following tables describe changes made in IPCC V200R001C80SPC700 compared with IPCC V200R001C80SPC600.

Interface Changes

Table 1 List of new interfaces

Interface Type	Changes
Device interfaces	StartPlayMediaFile
	StopPlayMediaFile

Event Changes

Table 2 List of new events

Event Type	Changes
Initialization events	VoiceExceptionEvent

Document Content Changes

Table 3 Document content changes

Location	Change Type	Changes	Reason
Return Codes	Add	Added return code 13. Added return code 14. Added return code 15.	Scenario adding.

Parent topic: [V200R001C80](#)

V200R001C80SPC600

The following tables describe changes made in IPCC V200R001C80SPC600 compared with IPCC V200R001C80SPC500.

Interface Changes

None

Event Changes

None

Document Content Changes

Table 1 Document content changes

Location	Change Type	Changes	Reason
SetConfig	Add	CALL_D_CFG_CONF_TYPE	Conference type configuration.

Parent topic: [V200R001C80](#)

V200R001C80SPC500

No change is made in IPCC V200R001C80SPC500 compared with IPCC V200R001C80SPC400.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC400

No change is made in IPCC V200R001C80SPC400 compared with IPCC V200R001C80SPC300.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC300

The following tables describe changes made in IPCC V200R001C80SPC300 compared with IPCC V200R001C80SPC200.

Interface Changes

Table 1 List of new interfaces

Interface Type	Changes
Device interfaces	SetAudioDeviceByName

Event Changes

None

Document Content Changes

Table 2 Document content changes

Location	Change Type	Changes	Reason
SetConfig	Add	CONFIG_ALERTING_ENABLE	Ringing tone switch configuration.
	Add	CONFIG_ALERTING_FILE_PATH	Ringing tone file configuration.
	Add	CALL_D_CFG_DSCP_AUDIO	Audio channel DSCP configuration.
	Add	CALL_D_CFG_DSCP_SIP	SIP channel DSCP configuration.

Parent topic: [V200R001C80](#)

V200R001C80SPC200

The following tables describe changes made in IPCC V200R001C80SPC200 compared with IPCC V200R001C80SPC100.

Interface Changes

Table 1 List of new interfaces

Interface Type	Changes
Call interfaces	GetCurrentCall

Event Changes

None

Document Content Changes

Table 2 Document content changes

Location	Change Type	Changes	Reason
SetConfig	Add	1. CONFIG_AUTO_REGISTER_ENABLE	Auto-registration capability configuration.

Parent topic: [V200R001C80](#)

V200R001C80SPC100

The following tables describe changes made in IPCC V200R001C80SPC100 compared with IPCC V200R001C80.

Interface Changes

Table 1 List of new interfaces

Interface Type	Changes
Initialization interfaces	UnInit
Call interfaces	Mute
	UnMute
	Hold
	UnHold
	Transfer
	IntercomCall
	IntercomAnswer
Phone linkage interfaces	CallJointStart
	CallJointStop
Conference interfaces	CreateLocalConf
	DestroyLocalConf
	AddToLocalConf
	DelFromLocalConf
	MuteLocalConf
	HoldLocalConf
Device interfaces	SetSoundCardAidConfig
	ControlAudioAidDevice
	GetVolumeEx
	SetVolumeEx
	GetGainByCall
	SetGainByCall

Table 2 List of modified interfaces

Interface Type	Interface Name	Changes
Initialization interfaces	GetResultDesc	1. Modified the result returned when an input parameter is invalid. Before modification, when an input parameter is invalid, the value of resultCode is 0 and that of resultDesc is an empty string. After modification, the value of resultCode is 1999 and that of resultDesc is unknown error. 2. Modified the result returned when a result code to be queried does not exist. Before modification, when a result code to be queried does not exist, the value of resultCode is 0 and that of resultDesc is an empty string. After modification, the value of resultCode is 1999 and that of resultDesc is unknown error.

Event Changes

Table 3 List of new events

Event Type	Changes
Call events	VoiceNetworkQosNotifyEvent
	VoiceHoldResultEvent
	VoiceUnHoldResultEvent
	VoiceTransferResultEvent
Phone linkage events	VoiceCallJointStartResultEvent
	VoiceCallJointStopResultEvent
	VoiceStatusNotifyEvent
Conference events	VoiceAddToLocalConfResultEvent
	VoiceDelFromLocalConfResultEvent
	VoiceDestroyLocalConfResultEvent
	VoiceHoldLocalConfResultEvent
Device events	VoiceAidProcessStatusEvent

Event Type	Changes
	VoiceControlAudioAidDeviceResultEvent
	VoiceVolumeExEvent
	VoiceGainByCallEvent

Table 4 List of modified events

Event Type	Event Name	Changes
Call events	VoiceTalkAlertingEvent	Added the callType field.

Document Content Changes

Table 5 Document content changes

Location	Change Type	Changes	Reason
SetConfig	Modify	1. CALL_D_CFG_SIP_REGISTER_TIMEOUT 2. CALL_D_CFG_SERVER_REG_LOCAL 3. CALL_D_CFG_AUDIO_AEC 4. CALL_D_CFG_AUDIO_AGC 5. CALL_D_CFG_AUDIO_DTMF_MODE	Configuration item description optimization.
GetConfig	Modify	1. CALL_D_CFG_SIP_REGISTER_TIMEOUT 2. CALL_D_CFG_SIP_REGISTER_TIMEOUT 3. CALL_D_CFG_SIP_SESSIONTIME	Configuration item description optimization.

Parent topic: [V200R001C80](#)

V200R001C80

No change is made in IPCC V200R001C80 compared with IPCC V200R001C60SPC100.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Overview

[Introduction](#)

[Development Environment](#)

[Applicable Scope](#)

[Conventions](#)

[Terms Explanation](#)

Parent topic: [Voice Interface \(ActiveX\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Introduction

The IPCC Voice provides unified multimedia capabilities.

Parent topic: [Overview](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Development Environment

- Operating system: Windows 7
- Development software: Microsoft Visual Studio 2010
- Development language: C++

Parent topic: [Overview](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Applicable Scope

This document describes all interfaces provided by the IPCC Voice in detail.

Parent topic: [Overview](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Conventions

In this document, the description of each interface function consists of the following parts: interface description, prerequisites, interface prototype, parameter description, return code, triggered event, and invoking description. JSON character strings must be parsed before they are used to determine the invocation result of an interface or event. Full matching of JSON character strings may cause incompatibility between the new and earlier versions.

Prerequisites

Describes the prerequisites that must be met to invoke an interface.

Interface Description

Describes the functions of an interface.

Interface Prototype

Provides the form in which an interface exists in code, including the interface name, number of parameters, and name of each parameter.

Parameter Description

Describes all parameters involved in an interface in detail. The description includes the value range and type of each parameter.

In this section, parameters are listed in a table, which contains the following columns: **Parameter**, **M/O** (mandatory/optional), **In/Out** (input or output parameter), **Type** (int or string), and **Description** (value range and other conditions).

Return Code

Describes the code that is returned when an interface is invoked.

Troubleshooting

Describes responses for exceptions that occur during interface invoking.

Invoking Description

Describes precautions for using an interface.

Event Parameters

Event parameters refer to triggered event parameters, transmitting event information.

Parent topic: [Overview](#)

Terms Explanation

None

Parent topic: [Overview](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Data Types

Basic Data Types

Parent topic: [Voice Interface \(ActiveX\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Basic Data Types

Type Name	Description
String	MBCS (multi-byte character set)
SHORT	Two-byte integer

Parent topic: [Data Types](#)

Interface Description

Interface	Description
SetSipServerInfo	Sets the IP address and port number of the SIP server.
SetLocalInfo	Sets the local IP address, SIP port number, and audio port number.
Register	Registers a phone number.
Deregister	Deregisters a phone number.
GetConfig	Queries a configuration item.
SetConfig	Sets a configuration item.
Call	Initiates a voice call.
AnonymousCall	Initiates an anonymous call.
Answer	Answers an incoming call.
Release	Releases a call.
DtmfDial	Performs two-stage dialing.
SendSipInfo	Sends/Receives a SIP message.
SetSipTlsMode/SetAudioRtpType	Sets the SIP or audio transmission mode.
GetDevices	Obtains the information about audio input/output devices.
SetDeviceIndex	Sets the audio input/output device to be used.
SetVolume/GetVolume	Adjusts the volume.
GetResultDesc	Queries a result code.
GetLocalIpAddr	Queries the local IP address.
SetLogSaveDays	Sets the number of days that Voice OCX logs are stored.
SetLogLevel	Sets the log level.

[Initialization Interfaces](#)

[Call Interfaces](#)

[Phone Linkage Interfaces](#)

[Conference Interfaces](#)

[Device Interfaces](#)

Parent topic: [Voice Interface \(ActiveX\)](#)

Initialization Interfaces

[SetConfig](#)

[GetConfig](#)

[SetLogLevel](#)

[SetLogSaveDays](#)

[SetAudioRtpType](#)

[SetSipTlsMode](#)

[GetResultDesc](#)

[GetLocalIpAddr](#)

[SetSipServerInfo](#)

[SetLocalInfo](#)

[Register](#)

[Deregister](#)

[UnInit](#)

Parent topic: [Interface Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

SetConfig

Prerequisites

1. The Voice OCX has been successfully loaded and initialized.
2. A phone number has not been registered and the phone using the phone number is idle.

Interface Description

This interface is used to set a configuration item.

Interface Prototype

```
Short SetConfig(sConfigKey, sConfigValue)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sConfigKey	M	In	String	Indicates the configuration item key.
sConfigValue	M	In	String	Indicates the configuration item value.

Configuration items that can be set.

Key	Value	Description	Application Scenario
CALL_D_CFG_SIP_REGIST_TIME OUT	[30, 2147483647]	Registration timeout duration, in seconds. The default value is 120 .	After successful registration, the Voice OCX periodically sends a registration message to the server. The registration message functions as a heartbeat message. The interval for sending registration messages is half the value of this configuration item.
CALL_D_CFG_SIP_REREGISTER _TIMEOUT	[0, 1800]	Re-registration timeout duration, in seconds. The default value is 120 .	If registration fails, the Voice OCX initiates registration again. The interval for initiating registration is the value of this configuration item.
CALL_D_CFG_SIP_SESSIONTIME R_ENABLE	1 : enable 0 : disable	Whether the SessionTimer is enabled. The default value is 1 .	N/A
CALL_D_CFG_SIP_SESSIONTIME	[90, 2147483647]	SessionTimer duration, in seconds. The default value is 120 .	After a call is connected, the Voice OCX periodically sends an UPDATE message to the server to check the call status. The interval for sending UPDATE messages is half the value of this configuration item.
CALL_D_CFG_SIP_SUPPORT_10 OREL	1 : supported 0 : not supported	Whether 100Rel extension (PRACK) is supported. The default value is 1 .	N/A
CALL_D_CFG_SERVER_REG_LO CAL	{ "ip": "SIP server IP address", "port": "SIP server port number" }	Local SIP server. The local SIP server is used upon emergency. Note: If there is a domain name, the domain name must be the same as that of the active and standby SIP servers.	For example, the local SIP server is used when both the active and standby SIP servers at the center are faulty.
CALL_D_CFG_ENV_USEAGENT	Non-empty string The string can contain a maximum of 61 characters (excluding the end sign).	Identifier.	N/A
CALL_D_CFG_AUDIO_AEC	0 : disable 1 : enable	Whether EC is enabled. The default value is 0 .	N/A
CALL_D_CFG_AUDIO_AGC	0 : disable 1 : enable	Whether AGC is enabled. The default value is 0 .	N/A
CALL_D_CFG_AUDIO_DTMF_MO DE	0 : transparent transmission mode (default) 1 : RFC2833 mode (automatic negotiation) 2 : forcible 2833 mode	DTMF mode. The default value is 0 .	N/A
CALL_D_CFG_AUDIO_DTMF_PT	[96, 127] The default value is 97 .	DTMF PT value.	This configuration item is used in the outband mode. In a call, the DTMF PT value cannot be the same as PT values of other codecs. A PT value conflict may cause an HME fault.
CALL_D_CFG_AUDIO_CODEC	[{ "code": "Voice codec PT value" }, { "code": "Voice codec PT value" }] The default value is [{ "code": "98" }, { "code": "18" }, { "code": "8" }, { "code": "0" }].	Voice codec priority and supported voice codecs. PT values for common codecs are as follows: G711U: 0 G711A: 8 G722: 9 G729: 18 ILBC: 98 OPUS: 112	N/A
CONFIG_AUTO_REGISTER_ENA BLE	0 : disable 1 : enable	Whether to enable automatic registration. The default value is 0 .	After successful registration, due to network anomalies lead to disconnection, every time the registration time to automatically initiate a re-registration request to the server.

Key	Value	Description	Application Scenario
CONFIG_ALERTING_ENABLE	0: disable 1: enable	Whether to enable ring tone playback. The default value is 0.	N/A
CONFIG_ALERTING_FILE_PATH	File absolute path. If it is an empty string, the default ringing tone is used.	Path where the ring tone file is stored.	The file must be a pure 64 KB PCM .wav file. If the value is empty, the default ring tone will be used. If the file in the absolute path does not exist, or if it is invalid, no tone will be played when the phone rings, or only noise will be played.
CALL_D_CFG_DSCP_AUDIO	[0,63]	Audio channel DSCP configuration. The default value is 0.	The CAC does not support this configuration item.
CALL_D_CFG_DSCP_SIP	[0,63]	SIP channel DSCP configuration. The default value is 0.	The CAC does not support this configuration item.
CALL_D_CFG_CONF_TYPE	0: The conference call was held when participants were added. 1: The conference call is normal when participants were added.	Conference type. The default value is 0.	The configuration item is valid only when there are at least two calls in a local conference. If the value is 1, no hold message is sent to the server, reducing the call establishment time.
CALL_D_CFG_DISABLE_AUTO_HOLD	0: not disable 1: disable	Whether to disable automatic hold of an incoming or outgoing call. The default value is 0.	This configuration item needs to be set to 1 when the multi-call capability of the local conference is not used.
CALL_D_CFG_ACCOUNT_PASSWORD_TYPE	0: general password type 1: HA1 type	Account password type. The default value is 0.	When you log in to the CAC synchronously, you need to set it to 1.
CALL_D_CFG_VIDEO_FRAME_RATE	{ "uiFrameRate": "frame rate", "uiMinFrameRate": "minimum frame rate" }	Frame rate of a video.	N/A

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

NOTICE

Whether configuration items **CALL_D_CFG_SIP_REGIST_TIMEOUT** and **CALL_D_CFG_SIP_SESSIONTIME** can take effect is determined by the configuration on the server.

Parent topic: [Initialization Interfaces](#)

GetConfig

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to query a configuration item.

Interface Prototype

```
String GetConfig(sConfigKey)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sConfigKey	M	In	String	Indicates the configuration item key. For the valid keys, see "Parameter Description" in SetConfig .

Configuration items that can be queried

Table 1 Configuration items that can be queried

Key	Value	Description	Remarks
CALL_D_CFG_SIP_REGIST_TIMEOUT	(0,4294967295]	Registration timeout duration, in seconds. The default value is 120 .	After successful registration, the Voice OCX periodically sends a registration message to the server. The registration message functions as a heartbeat message. The interval for sending registration messages is half the value of this configuration item.
CALL_D_CFG_SIP_REREGISTER_TIMEOUT	(0,4294967295]	Re-registration timeout duration, in seconds. The default value is 120 .	If registration fails, the Voice OCX initiates registration again. The interval for initiating registration is the value of this configuration item.
CALL_D_CFG_SIP_SESSIONTIMER_ENABLE	1: enable 0: disable	Whether the SessionTimer is enabled. The default value is 1 .	N/A
CALL_D_CFG_SIP_SESSIONTIME	(0,4294967295]	SessionTimer duration, in seconds. The default value is 120 .	After a call is connected, the Voice OCX periodically sends an UPDATE message to the server to check the call status. The interval for sending UPDATE messages is half the value of this configuration item.
CALL_D_CFG_AUDIO_AEC	0 : disable 1 : enable	Whether EC is enabled.	N/A
CALL_D_CFG_AUDIO_AGC	0 : disable 1 : enable	Whether AGC is enabled.	N/A
CALL_D_CFG_AUDIO_DTMF_MODE	0 : transparent transmission mode (default) 1 : RFC2833 mode (automatic negotiation) 2 : forcible 2833 mode	DTMF mode. The default value is 0 .	N/A
CALL_D_CFG_AUDIO_DTMF_PT	[96,127]	DTMF PT value.	This configuration item is valid when the DTMF mode is set to RFC2833. In a call, the DTMF PT value cannot be the same as PT values of other codecs. A PT value conflict may cause an HME fault.
CONFIG_AUTO_REGISTER_ENABLE	0: disable 1: enable	Automatic registration switch. The default value is 0 .	After successful registration, due to network anomalies lead to disconnection, every time the registration time to automatically initiate a re-registration request to the server.
CONFIG_ALERTING_ENABLE	0: disable 1: enable	Whether to enable ring tone playback. The default value is 0 .	N/A
CONFIG_ALERTING_FILE_PATH	File absolute path. If it is an empty string, the default ringing tone is used.	Path where the ring tone file is stored.	The file must be a pure 64 KB PCM .wav file. If the value is empty, the default ring tone will be used. If the file in the absolute path does not exist, or if it is invalid, no tone will be played when the phone rings, or only noise will be played.
CALL_D_CFG_DSCP_AUDIO	[0,63]	Audio channel DSCP configuration. The default value is 0 .	The CAC does not support this configuration item.
CALL_D_CFG_DSCP_SIP	[0,63]	SIP channel DSCP configuration. The default value is 0 .	The CAC does not support this configuration item.
CALL_D_CFG_DISABLE_AUTO_HOLD	0 : not disable 1 : disable	Whether to disable automatic hold of an incoming or outgoing call. The default value is 0 .	This configuration item needs to be set to 1 when the multi-call capability of the local conference is not used.
CALL_D_CFG_ACCOUNT_PASSWORD_TYPE	0 : general password type 1 : HA1 type	Account password type. The default value is 0 .	When you log in to the CAC synchronously, you need to set it to 1 .

Return Code

Data Type	Description
String	{ "resultCode": "Result code. If code 0 is returned, the query is successful. A non-0 value indicates the failure cause code." "configValue": "Configuration item value. The value is an empty string if the query fails." }

The following table describes the possible return codes.

Return Code	Description
0	Success.
4	Parameter error.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Initialization Interfaces](#)

SetLogLevel

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to set the Voice OCX log level.

Interface Prototype

Short SetLogLevel(String sLogLevel)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sLogLevel	M	In	String	Indicates the log level. The default log level is DEBUG. 0: ERROR 1: WARNING 2: INFO 3 or greater: DEBUG

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
Others	Other errors.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Initialization Interfaces](#)

SetLogSaveDays

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to set the number of days that Voice OCX logs are stored.

Interface Prototype

Short SetLogSaveDays(String sLogSaveDays)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sLogSaveDays	M	In	String	Indicates the number of days for which log files are stored. The value ranges from 0 to 365 . The default value is 30 . If the value is 0 , log files will be not deleted.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Initialization Interfaces](#)

SetAudioRtpType

Prerequisites

- 1. The Voice OCX has been successfully loaded and initialized.
- 2. A phone number has not been registered and the phone using the phone number is idle.

Interface Description

This interface is used to set the audio transmission mode.

Interface Prototype

Short SetAudioRtpType(sAudioRtpType)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sAudioRtpType	M	In	String	Indicates the audio transmission mode. The default value is 0 . • 0: Both RTP and SRTP are supported. • 1: Only RTP is supported. • 2: Only SRTP is supported.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

NOTICE

If the audio transmission mode is set to SRTP only or RTP only for one party of a call, the other party must support SRTP or RTP audio transmission mode. Otherwise, the call fails to be connected.

Parent topic: [Initialization Interfaces](#)

SetSipTlsMode

Prerequisites

- 1. The Voice OCX has been successfully loaded and initialized.
- 2. A phone number has not been registered and the phone using the phone number is idle.

Interface Description

This interface is used to set the SIP transmission mode.

Interface Prototype

Short SetSipTlsMode(sSipTransportMode, sCertFilePath)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sSipTransportMode	M	In	String	Indicates the SIP transmission protocol mode. The default value is 1. • 1: UDP • 2: TLS • 3: TCP
sCertFilePath	M	In	String	Indicates the full path of the certificate file, such as C:/tlscerts . This parameter takes effect only for the TLS transmission mode.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

NOTICE

1. When the **sSipTransportMode** input parameter is set to **2** (TLS mode), you can set the **sCertFilePath** input parameter to a valid path or an empty string. If you set the **sCertFilePath** input parameter to a non-empty string that is not a valid path, exceptions such as sign-in failure will occur. If an exception occurs, the cause code 4 is returned. In addition, the OCX log records the information indicating that the certificate path is invalid.

2. When no certificate is available, you are advised to set the **sCertFilePath** input parameter to an empty string.

Parent topic: [Initialization Interfaces](#)

GetResultDesc

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to query a result code description.

Interface Prototype

String GetResultDesc(sResultCode)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sResultCode	M	In	String	Indicates the result code (string converted from a signed integer) returned by the Voice OCX.

Return Code

Data Type	Description
String	{ "resultCode": "Result code to be queried. If the result code does not exist, 1999 is returned," "resultDesc": "Returned result code description. If the result code does not exist, unknown error is returned." }

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Initialization Interfaces](#)

GetLocalIpAddr

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to query the local IP address.

Interface Prototype

String GetLocalIpAddr()

Parameter Description

None

Return Code

Data Type	Description
String	{ "localips":[{"ip":"10.1.1.1"}], "resultCode": "Result code. If code 0 is returned, the query is successful. A non-0 value indicates the failure cause code." }

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Initialization Interfaces](#)

SetSipServerInfo

Prerequisites

- 1. The Voice OCX has been successfully loaded and initialized.
- 2. A phone number has not been registered and the phone using the phone number is idle.

Interface Description

This interface is used to set the IP address and port number of the SIP server.

Interface Prototype

Short SetSipServerInfo(sSipServerIp, sSipServerPort, sBackSipInfo)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sSipServerIp	M	In	String	Indicates the IP address of the SIP server. It must be a valid IP address or domain. For example, 127.0.0.1 or 127.0.0.1 example.com .
sSipServerPort	M	In	String	Indicates the port number of the SIP server. The value ranges from 1024 to 65535.
sBackSipInfo	M	In	String	Indicates the SIP server standby node information. The format is as follows: [{ "ip": "SIP server IP address", "port": "SIP server port number" }] If standby SIP server information is not required, set this parameter to an empty string. Currently, a maximum of three standby SIP servers are supported.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Initialization Interfaces](#)

SetLocalInfo

Prerequisites

1. The Voice OCX has been successfully loaded and initialized.
2. A phone number has not been registered and the phone using the phone number is idle.

Interface Description

This interface is used to set local information.

Interface Prototype

```
Short SetLocalInfo(sLocalIp, sLocalSipPort, sLocalAudioPort)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sLocalIp	M	In	String	Indicates the local IP address.
sLocalSipPort	M	In	String	Indicates the local SIP port number. The value ranges from 1024 to 65535.
sLocalAudioPort	M	In	String	Indicates the local audio port number. The value ranges from 1024 to 65535. (If you enter the value of sLocalAudioPort , ports from the value of sLocalAudioPort to the value of sLocalAudioPort plus 72 are automatically generated.

NOTICE

The values of **sLocalSipPort** and **sLocalAudioPort** must be different.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

1. The local SIP port number cannot be the same as the local audio port number, or be within the range of *Local audio port number* to *Local audio port number* + 10. For example, if the local audio port number is set to 19100, the local SIP port number cannot be within the range of 19100 to 19110.
2. If you need to load multiple Voice OCX controls on the same computer, ensure that the port number ranges of different controls do not overlap. Otherwise, calls may fail or the ringing event cannot be received. The recommended port setting is as follows:
 - a. Voice ocx1 SipPort: 5061 AudioPort: 19100
 - b. Voice ocx2 SipPort: 5071 AudioPort: 19200
 - c. Voice ocx3 SipPort: 5081 AudioPort: 19300

Parent topic: [Initialization Interfaces](#)

Register

Prerequisites

1. The Voice OCX has been successfully loaded and initialized.
2. A phone number has not been registered and the phone using the phone number is idle.
3. SIP server information has been configured.

Interface Description

This interface is used to register a phone number.

Interface Prototype

Short Register(sPhoneNumber, sPassword, sRegisterMode)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sPhoneNumber	M	In	String	Indicates the softphone number, which can contain 1 to 32 digits.
sPassword	M	In	String	Indicates the password. (This parameter can be left empty.)
sRegisterMode	M	In	String	Indicates the registration mode. The options are as follows: • 0: The phone number is registered with the active and standby SIP servers simultaneously. • 1: The phone number is registered with the active SIP server, and is registered with the standby SIP server only when the phone number fails to register with the active SIP server.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
5	SIP Server information is not configured.
6	The status is incorrect.
7	Loading the TUP interface fails.
Others	Other errors.

Triggered Event

[VoiceRegisterResultEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Initialization Interfaces](#)

Deregister

Prerequisites

A soft phone number has been registered.

Interface Description

This interface is used to deregister a soft phone number.

Interface Prototype

Short Deregister()

Parameter Description

None

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
6	The status is incorrect.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceDeregisterResultEvent](#)

NOTICE

if you deregister a phone number that has a call connected, you will receive the call released event.

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Initialization Interfaces](#)

UnInit

Prerequisites

None

Interface Description

This interface is used to uninitialized the Voice OCX and recycle resources.

NOTICE

When this interface is called, the current Voice OCX is uninitialized, and if you want to use the interface, you need to reload the Voice OCX.

Interface Prototype

Short UnInit()

Parameter Description

None

Return Code

Return Code	Description
0	Success.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Initialization Interfaces](#)

Call Interfaces

- [Call](#)
- [AnonymousCall](#)
- [Answer](#)
- [CallEx](#)
- [AnonymousCallEx](#)
- [AnswerEx](#)
- [Release](#)
- [DtmfDial](#)
- [SendSipInfo](#)
- [Mute](#)
- [UnMute](#)
- [Hold](#)
- [UnHold](#)
- [Transfer](#)
- [IntercomCall](#)
- [IntercomAnswer](#)
- [GetCurrentCall](#)
- [SetVideoWindow](#)
- [SetVideoWindowEx](#)

Parent topic: [Interface Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Call

Prerequisites

- 1. A soft phone number has been registered.
- 2. The phone using the phone number is idle, or has a call connected.

Interface Description

This interface is used to initiate a voice call. The default maximum number of calls is 24.
This interface has been deprecated and replaced by CallEx.

Interface Prototype

Short Call(sCalleeNumber)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sCalleeNumber	M	In	String	Indicates the called number, which can contain 1 to 32 digits.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
12	The memory fails to be allocated.
Others	Other errors.

Triggered Event

- 1. [VoiceTalkOutgoingEvent](#)
- 2. [VoiceStartCallResultEvent](#)
- 3. [VoiceTalkRingBackEvent](#)

NOTICE

The called party will receive the [VoiceTalkAlertingEvent](#) event.

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Call Interfaces](#)

AnonymousCall

Prerequisites

1. SIP server information has been configured.
2. The phone using the phone number is idle, or has a call connected.

Interface Description

This interface is used to initiate an anonymous call. The default maximum number of calls is 24.

This interface has been deprecated and replaced by AnonymousCallEx.

Interface Prototype

```
Short AnonymousCall(sAnonymousNumber, sCalleeNumber)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sAnonymousNumber	M	In	String	Indicates an anonymous card number. The anonymous card number must be configured on the SIP server.
sCalleeNumber	M	In	String	Indicates the called number, which can contain 1 to 32 digits.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
5	SIP Server information is not configured.
6	The status is incorrect.
7	Loading the TUP interface fails.
12	The memory fails to be allocated.
Others	Other errors.

Triggered Event

1. [VoiceTalkOutgoingEvent](#)
2. [VoiceStartCallResultEvent](#)
3. [VoiceTalkRingBackEvent](#)

NOTICE

The called party will receive the [VoiceTalkAlertingEvent](#) event.

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Call Interfaces](#)

Answer

Prerequisites

The VoiceTalkAlertingEvent event has been received.

Interface Description

This interface is used by the called party to answer an incoming call when the VoiceTalkAlertingEvent event is received.
This interface has been deprecated and replaced by AnswerEx.

Interface Prototype

Short Answer(sCallId)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sCallId	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

- 1. [VoiceSrtpResultEvent](#)
- 2. [VoiceTalkConnectedEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Call Interfaces](#)

CallEx

Prerequisites

1. A soft phone number has been registered.
2. The phone using the phone number is idle, or has a call connected.
3. If the video call is currently active, no video calls are allowed.

Interface Description

This interface is used to initiate a voice or video call. The default maximum number of calls is 24. Only one video call is allowed.

Interface Prototype

Short CallEx(sInfo)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sInfo	M	In	String	Indicates call information.

NOTE

The value of **sInfo** is a JSON string. The format is as follows:

```
{"callee":"70502","isVideo":true}
```

Parameter	M/O	In/Out	Data Type	Description
callee	M	In	String	Indicates the called number, which can contain 1 to 32 digits.
isVideo	O	In	String	Indicates whether to answer in video mode. The default value is false . • 1 or true: audio and video mode. • 0 or false: audio mode.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
12	The memory fails to be allocated.
Others	Other errors.

Triggered Event

1. [VoiceTalkOutgoingEvent](#)
2. [VoiceStartCallResultEvent](#)
3. [VoiceTalkRingBackEvent](#)

NOTICE

The called party will receive the [VoiceTalkAlertingEvent](#) event.

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Call Interfaces](#)

AnonymousCallEx

Prerequisites

1. SIP server information has been configured.
2. The phone using the phone number is idle, or has a call connected.
3. If the video call is currently active, no video anonymous calls are allowed.

Interface Description

This interface is used to initiate an anonymous voice or video call. The default maximum number of calls is 24. Only one video call is allowed.

Interface Prototype

Short AnonymousCallEx(sInfo)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sInfo	M	In	String	Indicates the anonymous call information.

NOTE

The value of **sInfo** is a JSON string. The format is as follows:

```
{"anonymousCard":"AnonymousCard","callee":"70502","isVideo":true}
```

Parameter	M/O	In/Out	Data Type	Description
anonymousCard	M	In	String	Indicates an anonymous card number. The anonymous card number must be configured on the SIP server.
callee	M	In	String	Indicates the called number, which can contain 1 to 32 digits.
isVideo	O	In	String	Indicates whether to answer in video mode. The default value is false . • 1 or true: audio and video mode. • 0 or false: audio mode.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
5	SIP Server information is not configured.
6	The status is incorrect.
7	Loading the TUP interface fails.
12	The memory fails to be allocated.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

1. [VoiceTalkOutgoingEvent](#)
2. [VoiceStartCallResultEvent](#)
3. [VoiceTalkRingBackEvent](#)

NOTICE

The called party will receive the [VoiceTalkAlertingEvent](#) event.

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Call Interfaces](#)

AnswerEx

Prerequisites

The VoiceTalkAlertingEvent event has been received.

Interface Description

This interface is used to answer a voice or video call.

Interface Prototype

Short AnswerEx(sInfo)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sInfo	M	In	String	Indicates call information.

 **NOTE**

The value of **sInfo** is a JSON string. The format is as follows:
`{"callid":632000112,"isVideo":true}`

Parameter	M/O	In/Out	Data Type	Description
callid	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295 .
isVideo	O	In	String	Indicates whether to answer in video mode. The default value is false . 1 or true: audio and video mode. 0 or false: audio mode.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

- 1. [VoiceSrtpResultEvent](#)
- 2. [VoiceTalkConnectedEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Call Interfaces](#)

Release

Prerequisites

A call has been connected.

Interface Description

This interface is used to release a call that has been connected.

Interface Prototype

Short Release(sCallId)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sCallId	M	In	String	Indicates the call ID. If this parameter is left empty, the current call is released.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceTalkReleaseEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Call Interfaces](#)

DtmfDial

Prerequisites

- 1. The current call has been connected.
- 2. RTP channel has been established.

Interface Description

This interface is used to perform two-stage dialing after a voice call is connected.

Interface Prototype

Short DtmfDial(sDialNumber)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sDialNumber	M	In	String	Indicates the dialed number. The value range is [0, 12). If the value is out of range, the operation fails. • 0–9: keys 0 to 9 • 10: star key (*) • 11: pound key (#)

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

NOTICE

The real prerequisite for two-stage dialing is that an RTP channel is established. An RTP channel will be established when a voice call is connected. Therefore, two-stage dialing is supported when a voice call is connected. However, the client and server may perform re-negotiation during a call. During the re-negotiation, two-stage dialing is not supported. If the DtmfDial interface is invoked during the re-negotiation (which seldom happens because re-negotiation is a very fast process), the interface fails to be invoked, cause code 6 is returned, indicating a state error, and control logs will be recorded, indicating that the RTP channel is not established.

Parent topic: [Call Interfaces](#)

SendSipInfo

Prerequisites

The current call has been connected.

Interface Description

This interface is used to send a SIP message after a voice call is connected.

Interface Prototype

```
Short SendSipInfo(strSipInfo)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sSipInfo	M	In	String	Indicates a SIP message, which contains a maximum of 511 bytes (excluding the end sign).

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceSipInfoArrivedEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Call Interfaces](#)

Mute

Prerequisites

A call has been connected.

Interface Description

This interface is used to mute specified calls.

Interface Prototype

```
Short Mute(String sCallId)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sCallId	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295 .

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
7	Loading the TUP interface fails.
1002	The call ID is invalid (returned from the TUP Call library).
1019	The call ID does not exist (returned from the TUP Call library).
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Call Interfaces](#)

UnMute

Prerequisites

A call has been connected.

Interface Description

This interface is used to unmute specified calls.

Interface Prototype

```
Short UnMute(String sCallId)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sCallId	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295 .

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
7	Loading the TUP interface fails.
1002	The call ID is invalid (returned from the TUP Call library).
1019	The call ID does not exist (returned from the TUP Call library).
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Call Interfaces](#)

Hold

Prerequisites

- 1. A call has been connected.
- 2. The specified call has not been held.

Interface Description

This interface is used to hold specified calls.

Interface Prototype

```
Short Hold(String sCallId)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sCallId	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295 .

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
1019	The call ID does not exist.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceHoldResultEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Call Interfaces](#)

UnHold

Prerequisites

- 1. A call has been connected.
- 2. The specified call has been held.

Interface Description

This interface is used to unhold specified calls.

Interface Prototype

```
Short UnHold(String sCallId)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sCallId	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295 .

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
1019	The call ID does not exist.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceUnHoldResultEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Call Interfaces](#)

Transfer

Prerequisites

A call has been connected.

Interface Description

This interface is used to transfer specified calls.

Interface Prototype

```
Short Transfer(String sType, String sCallId, String sTargetNumber)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sType	M	In	String	Indicates the transfer type. The options are as follows: 1: blind transfer 2: consult transfer The phone linkage supports only blind transfer.
sCallId	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295 .
sTargetNumber	M	In	String	Indicates the phone number to which a call will be transferred For blind transfer, the target phone number contains a maximum of 32 characters. For consult transfer, the value ranges from 0 to 4294967295 .

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
7	Loading the TUP interface fails.
1019	The call ID does not exist.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceTalkReleaseEvent](#)

[VoiceTransferResultEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Call Interfaces](#)

IntercomCall

Prerequisites

A call has been connected.

Interface Description

This interface is used to place internal calls.

Interface Prototype

```
Short IntercomCall(String sCallId, String sTargetNumber)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sCallId	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295 .
sTargetNumber	M	In	String	Indicates the called number. This parameter cannot be empty.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceTalkRingBackEvent](#). Alternatively, the peer end receives the [VoiceTalkAlertingEvent](#).

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Call Interfaces](#)

IntercomAnswer

Prerequisites

The [VoiceTalkAlertingEvent](#) event for an internal call is received.

Interface Description

This interface is used to answer internal calls.

Interface Prototype

```
Short IntercomAnswer(String sCallId)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sCallId	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceTalkConnectedEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Call Interfaces](#)

GetCurrentCall

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to obtain information about the current call.

Interface Prototype

```
String GetCurrentCall(void)
```

Parameter Description

None

Return Code

Data Type	Result Type	Description
String	Normal	There is a connected call currently. <pre>{ "callType": "Call type", "callee": "Called number", "caller": "Calling number", "callid": "Call ID", "resultCode" : 0, "resultDesc" : "Success." }</pre> Values of callType: 1. 0: IPT call 2. 1: internal call 3. 4: IPCC call
	Abnormal	There is no call connected. <pre>{ "resultCode" : 13, "resultDesc" : "No Call." }</pre>

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Call Interfaces](#)

SetVideoWindow

Prerequisites

- 1. The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to set the audio and video call window.

Interface Prototype

Short SetVideoWindow(String sWindowInfo)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sWindowInfo	M	In	String	Indicates the video window information.

 **NOTE**

The value of **sWindowInfo** is a JSON string. The format is as follows:
`{"localVideoWindow": "1246168", "remoteVideoWindow": "1639484"}`

Parameter	M/O	In/Out	Data Type	Description
localVideoWindow	M	In	String	Displays the window handle for the local video. The window handle is generated by the third party. The value is a character string that consists of decimal digits. The value ranges from -2147483648 to 2147483647 .
remoteVideoWindow	M	In	String	Displays the window handle for the peer video. The window handle is generated by the third party. The value is a character string that consists of decimal digits. The value ranges from -2147483648 to 2147483647 .

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Call Interfaces](#)

SetVideoWindowEx

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to specify the voice and video window for a call.

Interface Prototype

```
Short SetVideoWindowEx(String sWindowInfo, String sCallId)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sWindowInfo	M	In	String	Indicates the video window information.
sCallId	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295.

 **NOTE**

The value of **sWindowInfo** is a JSON string. The format is as follows:
{**"localVideoWindow"**:**"1246168"**,**"remoteVideoWindow"**:**"1639484"**}

Parameter	M/O	In/Out	Data Type	Description
localVideoWindow	M	In	String	Displays the window handle for the local video. The window handle is generated by the third party. The value is a character string that consists of decimal digits. The value ranges from -2147483648 to 2147483647.
remoteVideoWindow	M	In	String	Displays the window handle for the peer video. The window handle is generated by the third party. The value is a character string that consists of decimal digits. The value ranges from -2147483648 to 2147483647.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Call Interfaces](#)

Phone Linkage Interfaces

[CallJointStart](#)

[CallJointStop](#)

Parent topic: [Interface Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

CallJointStart

Prerequisites

- 1. The soft phone has successfully logged in.
- 2. The phone linkage has not been started.
- 3. The phone is idle.

Interface Description

This interface is used to start phone linkage.

Interface Prototype

```
Short CallJointStart(String sPhoneNumber)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sPhoneNumber	M	In	String	Indicates the number registered on the phone. The value contains a maximum of 32 characters.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceCallJointStartResultEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Phone Linkage Interfaces](#)

CallJointStop

Prerequisites

- 1. Phone linkage has been started.
- 2. The phone is idle.

Interface Description

This interface is used to end phone linkage.

Interface Prototype

```
Short CallJointStop()
```

Parameter Description

None

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
6	The status is incorrect.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceCallJointStopResultEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Phone Linkage Interfaces](#)

Conference Interfaces

[CreateLocalConf](#)

[DestroyLocalConf](#)

[AddToLocalConf](#)

[DelFromLocalConf](#)

[MuteLocalConf](#)

[HoldLocalConf](#)

Parent topic: [Interface Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

CreateLocalConf

Prerequisites

- 1. A call has been connected.
- 2. The local conference has not been created.

Interface Description

This interface is used to create a local conference.

Interface Prototype

```
Short CreateLocalConf(String sCallId)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sCallId	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295 .

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
1019	The call ID does not exist.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Conference Interfaces](#)

DestroyLocalConf

Prerequisites

A local conference has been established.

Interface Description

This interface is used to destroy a local conference.

Interface Prototype

Short DestroyLocalConf()

Parameter Description

None

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
6	The status is incorrect.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceDestroyLocalConfResultEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Conference Interfaces](#)

AddToLocalConf

Prerequisites

- 1. Specified calls have been connected.
- 2. A local conference has been created.
- 3. Specified calls have not joined the local conference.

Interface Description

This interface is used to add specified calls to a local conference. A local conference supports a maximum of five calls.

Interface Prototype

```
Short AddToLocalConf(String sCallId)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sCallId	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295 .

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
1019	The call ID does not exist.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceAddToLocalConfResultEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Conference Interfaces](#)

DelFromLocalConf

Prerequisites

Specified calls have joined the local conference.

Interface Description

This interface is used to remove a specified call from a local conference. The calls will be released.

Interface Prototype

```
Short DelFromLocalConf(String sCallId)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sCallId	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295 .

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
6	The status is incorrect.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceDelFromLocalConfResultEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Conference Interfaces](#)

MuteLocalConf

Prerequisites

A local conference has been created.

Interface Description

This interface is used to mute or unmute a local conference.

Interface Prototype

Short MuteLocalConf (BOOL, isMuted)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
isMuted	M	In	BOOL	true: Mute the conference. false: Unmute the conference.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Conference Interfaces](#)

HoldLocalConf

Prerequisites

A local conference has been created.

Interface Description

This interface is used to hold a conference or retrieve a held conference.

Interface Prototype

Short HoldLocalConf(BOOL, isHold)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
isHold	M	In	BOOL	true : Hold the conference. false : Retrieve the held conference.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceHoldLocalConfResultEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Conference Interfaces](#)

Device Interfaces

[GetDevices](#)

[SetDeviceIndex](#)

[SetVolume](#)

[GetVolume](#)

[SetSoundCardAidConfig](#)

[ControlAudioAidDevice](#)

[GetVolumeEx](#)

[SetVolumeEx](#)

[GetGainByCall](#)

[SetGainByCall](#)

[SetAudioDeviceByName](#)

[StartPlayMediaFile](#)

[StopPlayMediaFile](#)

[GetVideoDevices](#)

[SnapShot](#)

[SetVideoDeviceIndex](#)

[OpenPreview](#)

[ClosePreview](#)

Parent topic: [Interface Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

GetDevices

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to obtain the information about all audio input/output devices on the equipment where the control is located.

Interface Prototype

String GetDevice(sInputType)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sInputType	M	In	String	0: input device 1: output device

Return Code

Data Type	Description
String	{ "currentDevIndex": "Index of the device that is currently used", "deviceList": [{"deviceName": "Device name", "deviceIndex": "Device index"},] "deviceNum": "Device quantity", "resultCode": "Result code. Value 0 indicates that input/output device information is obtained successfully. A non-0 value indicates the failure cause code." } If the equipment where the OCX is located does not have audio devices, the result does not contain the deviceList information.

The following table describes the possible return codes.

Return Code	Description
0	Success.
4	Parameter error.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

NOTICE

When you right-click the sound icon on the operating system and choose the recording or playback device, the displayed recording or playback device information is the same as that queried using this interface.

Parent topic: [Device Interfaces](#)

SetDeviceIndex

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to set an audio input/output device.

Interface Prototype

Short SetDeviceIndex(sInputType, sDeviceIndex)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sInputType	M	In	String	0: input device 1: output device
sDeviceIndex	M	In	String	Indicates the device index. The value ranges from 1 to 4294967295.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Device Interfaces](#)

SetVolume

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to set the volume.

Interface Prototype

```
Short SetVolume(sInputType, sVolume)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sInputType	M	In	String	0: input volume 1: output volume
sVolume	M	In	String	Indicates volume, which ranges from 0 to 100.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Device Interfaces](#)

GetVolume

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to obtain the volume.

Interface Prototype

```
String GetVolume(sInputType)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sInputType	M	In	String	• 0: input volume • 1: output volume

Return Code

Data Type	Description
String	{ "resultCode": "Result code. If code 0 is returned, the query is successful. A non-0 value indicates the failure cause code." , "volume": "Volume. The value is an empty string or zero if the query fails." }

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Device Interfaces](#)

SetSoundCardAidConfig

Prerequisites

The audio card auxiliary process has not started.

Interface Description

This interface is used to configure the audio card auxiliary devices.

Interface Prototype

```
Short SetSoundCardAidConfig(String sConfigInfo)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sConfigInfo	M	In	String	{ "aidMicDeviceName": "auxiliary microphone name", "aidSpeakDeviceName": "auxiliary speaker name", "mainIp": "main process IP address", "mainControlPort": "main process control port. The recommended value is 20000." "aidIp": "auxiliary process IP address", "aidControlPort": "auxiliary process control port. The recommended value is 20040." } aidMicDeviceName and aidSpeakDeviceName are required. Others are optional.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceAidProcessStatusEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Device Interfaces](#)

ControlAudioAidDevice

Prerequisites

Connection has been established to the audio card auxiliary process.

Interface Description

This interface is used to control the audio card auxiliary devices, for example, to switch the audio streams of specified calls to an auxiliary device for output, or switch the audio streams back to the main device.

Interface Prototype

```
Short ControlAudioAidDevice(String sCallId, BOOL isStart, String sAidDeviceName)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sCallId	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295.
isStart	M	In	BOOL	true : start false : stop
sAidDeviceNam	M	In	String	Indicates the name of the auxiliary audio card. This parameter cannot be empty.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceControlAudioAidDeviceResultEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Device Interfaces](#)

GetVolumeEx

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to check the volume of a specified audio device.

Interface Prototype

```
Short GetVolumeEx(String sDeviceName, String sInputType)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sDeviceName	M	In	String	Indicates the name of the audio card. This parameter cannot be empty.
sInputType	M	In	String	Indicates the audio card type. 0: input 1: output

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceVolumeExEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Device Interfaces](#)

SetVolumeEx

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to set the volume of a specified audio device.

Interface Prototype

```
Short SetVolumeEx(String sDeviceName, String sInputType,String sVolume)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sDeviceName	M	In	String	Indicates the name of the audio card. This parameter cannot be empty.
sInputType	M	In	String	Indicates the audio card type. 0 : input 1 : output
sVolume	M	In	String	Indicates volume. Value range: [0,100]

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceVolumeExEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Device Interfaces](#)

GetGainByCall

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to query the audio device gain for a specified call.

Interface Prototype

```
Short GetGainByCall(String sCallId, String sInputType)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sCallId	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295.
sInputType	M	In	String	Indicates the audio card type. 0: input 1: output

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceGainByCallEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Device Interfaces](#)

SetGainByCall

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to control the audio device gain for a specified call.

Interface Prototype

```
Short SetGainByCall(String sCallId, String sInputType,String sGain)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sCallId	M	In	String	Indicates the call ID. The value ranges from 0 to 4294967295 .
sInputType	M	In	String	Indicates the audio card type. 0 : input 1 : output
sGain	M	In	String	Indicates the volume gain. Value range: [0,10]

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceGainByCallEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Device Interfaces](#)

SetAudioDeviceByName

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to set audio device.

Interface Prototype

```
SHORT SetAudioDeviceByName(String sInputType, String sAudioDeviceName)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sInputType	M	In	String	Indicates the audio card type. 0: input 1: output
sAudioDeviceName	M	In	String	Indicates the audio device name. The value cannot be empty.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Device Interfaces](#)

StartPlayMediaFile

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to start playing the specified audio file.

Interface Prototype

```
String StartPlayMediaFile(String sAudioFilePath, String sLoops);
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sAudioFilePath	M	In	String	Indicates the absolute path of an audio file.
sLoops	M	In	String	Indicates the number of playback cycles. Value 0 indicates that audio files are played circularly.

Return Code

Data Type	Description
String	{ "resultCode": "Result code. If code 0 is returned, the playback is successful. A non-0 value indicates the failure cause code." , "resultDesc": "Result code description", "fileHandle": "Audio file playing handle" }

The following table describes the possible return codes.

Return Code	Description
0	Success.
4	Parameter error.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Device Interfaces](#)

StopPlayMediaFile

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to stop playing the specified audio file.

Interface Prototype

```
SHORT StopPlayMediaFile(String sAudioPlayHandle)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sAudioPlayHandle	M	In	String	Indicates the playing handle of an audio file.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Device Interfaces](#)

GetVideoDevices

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to obtain the video device information.

Interface Prototype

```
String GetVideoDevices()
```

Parameter Description

None

Return Code

Data Type	Result Type	Description
String	Normal	Character string in JSON format. Example: <pre>{ "deviceNum" : 1, "deviceList" : [{ "deviceIndex" : 2044781860, "deviceName" : "e2eCap Video Capture" }], "resultCode" : 0 }</pre> In the preceding information: deviceNum: number quantity. deviceList: device information list (array). deviceIndex: device index number. deviceName: device name. If the equipment where the OCX is located does not have video devices, the result does not contain the deviceList information.
	Abnormal	If the query fails, the following information is returned: <pre>{ "resultCode": "Error code" }</pre>

The following table describes the possible return codes.

Return Code	Description
0	Success.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Device Interfaces](#)

SnapShot

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to take snapshots.

Interface Prototype

SHORT Snapshot(String sSnapshotInfo)

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sSnapshotInfo	M	In	String	Indicates the snapshot information.

 **NOTE**

The value of **sSnapshotInfo** must be in JSON format. The format is as follows:
{ "deviceIndex": "512461684", "filePath": "D:/test.jpg", "height": "288", "width": "352" }

Parameter	M/O	In/Out	Data Type	Description
deviceIndex	M	In	String	Indicates the video device SN. The value ranges from 0 to 4294967295 .
filePath	M	In	String	Indicates the absolute path for storing images.
height	M	In	String	Indicates the image height.
width	M	In	String	Indicates the image width.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

[VoiceSnapshotResultEvent](#)

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Device Interfaces](#)

SetVideoDeviceIndex

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to specify the video device to be used.

Interface Prototype

```
Short SetVideoDeviceIndex(String sDeviceIndex)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sDeviceIndex	M	In	String	Indicates the video device SN. The value ranges from 0 to 4294967295.

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Device Interfaces](#)

OpenPreview

Prerequisites

The Voice OCX has been successfully loaded and initialized.

Interface Description

This interface is used to enable video preview.

Interface Prototype

```
SHORT OpenPreview(String sWindowHandle, String sDeviceIndex)
```

Parameter Description

Parameter	M/O	In/Out	Data Type	Description
sWindowHandle	M	In	String	Indicates the window handle. The value ranges from -2147483648 to 2147483647 .
sDeviceIndex	M	In	String	Indicates the video device SN. The value ranges from 0 to 4294967295 .

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
4	Parameter error.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Device Interfaces](#)

ClosePreview

Prerequisites

- 1. The Voice OCX has been successfully loaded and initialized.
- 2. Video preview has been enabled.

Interface Description

This interface is used to disable video preview.

Interface Prototype

```
SHORT ClosePreview()
```

Parameter Description

None

Return Code

Return Code	Description
0	Success.
1	Voice control uninitialized.
7	Loading the TUP interface fails.
Others	Other error code that is returned from the TUP Call library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Device Interfaces](#)

Event Description

Event Name	Description
VoiceInitResultEvent	Control initialization result event.
VoiceRegisterResultEvent	Registration result event.
VoiceDeregisterResultEvent	Deregistration result event.
VoiceTalkOutgoingEvent	Call initiation success event.
VoiceStartCallResultEvent	Call operation result event.
VoiceTalkAlertingEvent	Ringing event.
VoiceTalkRingBackEvent	Ring back event.
VoiceSrtpResultEventSRTP	SRTP negotiation result event.
VoiceTalkConnectedEvent	Call connection event.
VoiceTalkReleaseEvent	Call release event.
VoiceSipInfoArrivedEvent	SIP message arrival event.

[Initialization Events](#)

[Call Events](#)

[Phone Linkage Events](#)

[Conference Events](#)

[Device Events](#)

Parent topic: [Voice Interface \(ActiveX\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Initialization Events

- [VoiceInitResultEvent](#)
- [VoiceRegisterResultEvent](#)
- [VoiceDeregisterResultEvent](#)
- [VoiceExceptionEvent](#)

Parent topic: [Event Description](#)

VoiceInitResultEvent

Event Description

Control initialization result event. This event is sent to the control invoker. If the control initialization fails, you can check control logs for the specific cause.

Parameter Description

Data Type	Description
String	{ "resultCode": "Result code. If code 0 is returned, the initialization is successful. A non-0 value indicates the failure cause code." , "resultDesc": "Result code description" }

Triggering Condition

This event is triggered when the Voice OCX is loaded.

Parent topic: [Initialization Events](#)

VoiceRegisterResultEvent

Event Description

Registration result event. This event is sent to the interface invoker.

Parameter Description

Data Type	Description
String	{ "telephone": "Phone number", "name": "User name", "resultCode": "Result code. If code 0 is returned, the registration is successful. A non-0 value indicates the failure cause code." , "resultDesc": "Result code description" }

Triggering Condition

This event is triggered when registration succeeds or fails. This event is also triggered when the SIP server fails to respond within 32 seconds due to an error (for example, when the SIP server IP address or port number is incorrectly set or the network is disconnected).

Parent topic: [Initialization Events](#)

VoiceDeregisterResultEvent

Event Description

Deregistration result event. This event is sent to the interface invoker.

Parameter Description

Data Type	Description
String	{ "telephone": "Phone number", "name": "User name", "resultCode": "Result code. If code 0 is returned, the deregistration is successful. A non-0 value indicates the failure cause code." , "resultDesc": "Result code description" }

Triggering Condition

This event is triggered when a phone number is deregistered.

Parent topic: [Initialization Events](#)

VoiceExceptionEvent

Event Description

The exception prompt event is used to notify the exception that the Voice OCX cannot handle.

Parameter Description

Data Type	Description
String	{ "resultCode": "Result code", "resultDesc": "Result code description" }

Triggering Condition

An exception that the Voice OCX cannot handle, such as the operating system sound card driver exception.
You are advised to restart the PC.

Parent topic: [Initialization Events](#)

Call Events

[VoiceTalkOutgoingEvent](#)
[VoiceStartCallResultEvent](#)
[VoiceTalkAlertingEvent](#)
[VoiceTalkRingBackEvent](#)
[VoiceSrtpResultEvent](#)
[VoiceTalkConnectedEvent](#)
[VoiceTalkReleaseEvent](#)
[VoiceSipInfoArrivedEvent](#)
[VoiceNetworkQosNotifyEvent](#)
[VoiceHoldResultEvent](#)
[VoiceUnHoldResultEvent](#)
[VoiceTransferResultEvent](#)

Parent topic: [Event Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

VoiceTalkOutgoingEvent

Event Description

Call initiation success event. This event is sent to the calling party, indicating that the call request has been successfully sent to the SIP server. Note that this event does not mean that the call is made successfully.

Parameter Description

Data Type	Description
String	{ "callee": "Called number", "callid": "Call ID", "isVideo": "Whether to answer in video mode." false/true }

 **NOTE**

For example:
{
"callee" : "86665",
"callid" : "787480576",
"isVideo" : false
}

Triggering Condition

This event is triggered when a call (or an anonymous call) is initiated successfully.

Parent topic: [Call Events](#)

VoiceStartCallResultEvent

Event Description

Call operation result event. This event is sent to the calling party. In some cases (for example, when the audio port number is occupied), the call operation fails and no call request is sent to the SIP server. Therefore, the VoiceTalkOutgoingEvent event will not be received, and the VoiceStartCallResultEvent event must be used to notify the calling party of the call failure.

Parameter Description

Data Type	Description
String	{ "callid": "Call ID", "resultCode": "Result code. If code 0 is returned, the calling party initiates a call successfully. A non-0 value indicates the failure cause code." , "resultDesc": "Result code description" " }

 **NOTE**

For example:
{
"callid" : "787480576",
"resultCode" : 0,
"resultDesc" : "Success."
}

Triggering Condition

This event is triggered when a call (or an anonymous call) is initiated successfully.

Parent topic: [Call Events](#)

VoiceTalkAlertingEvent

Event Description

Ringing event. This event is sent to the called party, notifying the calling party of the incoming call.

Parameter Description

Data Type	Description
String	<pre>{ "callid": "Call ID", "caller": "Calling number", "callType": "Call type", "isVideo": "Whether to answer in video mode." false/true }</pre> Values of callType: 0: IPT call 1: internal call 4: IPCC call

 **NOTE**

For example:

```
{
  "callType" : 0,
  "caller" : "86665",
  "callid" : "175046656",
  "isVideo" : true
}
```

Triggering Condition

This event is triggered when the call arrives at the called party.

Parent topic: [Call Events](#)

VoiceTalkRingBackEvent

Event Description

Call ring back event, indicating that the peer end rings. This event is sent to the calling party, indicating that the called party's phone is ringing.
If the called party also uses a phone developed based on the Voice OCX control, the Voice OCX automatically sends this event when the incoming call request is received.

Parameter Description

Data Type	Description
String	{ "callid": "Call ID", "callee": "Called number", "isVideo": "Whether to answer in video mode." false/true" }

 **NOTE**

For example:
{
"callee" : "86665",
"callid" : "1040318464",
"isVideo" : true
}

Triggering Condition

This event is sent by the called party to the calling party.

Parent topic: [Call Events](#)

VoiceSrtpResultEvent

Event Description

SRTP negotiation result event. This event carries two parameters, where the **enableSrtp** parameter specifies whether SRTP audio transmission mode is used.

Parameter Description

Data Type	Description
String	{ "callid": "Call ID", "enableSrtp": "Whether SRTP is enabled. true : enabled; false : disabled." }

Triggering Condition

This event is triggered when a call is connected, and is sent to both the calling and called parties.

Parent topic: [Call Events](#)

VoiceTalkConnectedEvent

Event Description

Call connection event. This event is sent to both the calling and called parties, indicating that the call is connected.

Parameter Description

Data Type	Description
String	{ "callid": "Call ID", "caller": "Calling number", "callee": "Called number", "isVideo": "Whether to answer in video mode." false/true }

 **NOTE**

For example:

```
{  
"callee" : "86665",  
"caller" : "86666",  
"callid" : "1040318464",  
"isVideo" : true  
}
```

Triggering Condition

This event is triggered when a call is connected, and is sent to both the calling and called parties.

Parent topic: [Call Events](#)

VoiceTalkReleaseEvent

Event Description

Call release event. This event is sent to both the calling and called parties, indicating that the call is released.

Parameter Description

Data Type	Description
String	{ "callid": "Call ID", "caller": "Calling number", "callee": "Called number", "isVideo": "Whether to answer in video mode. false/true", "resultCode": "Result code. If code 0 is returned, the call is released successfully. A non-0 value indicates the failure cause code. ", "resultDesc": "Result code description" }

NOTE

For example:

```
{  
"callee" : "86665",  
"caller" : "86666",  
"callid" : "223477760",  
"isVideo" : true,  
"resultCode" : 0,  
"resultDesc" : "Success."  
}
```

Triggering Condition

This event is triggered when:

1. The application invokes the Release interface successfully.
2. The background server releases the call due to an exception.

Parent topic: [Call Events](#)

VoiceSipInfoArrivedEvent

Event Description

SIP message arrival event. This event is sent to the SIP message recipient.

Parameter Description

Data Type	Description
String	{ "mimeType": "text/xml", "message": "SIP message" }

Currently, only the **text** and **xml** formats are supported.

Triggering Condition

This event is triggered when a SIP message is received.

Parent topic: [Call Events](#)

VoiceNetworkQosNotifyEvent

Event Description

Network QoS monitoring event for a voice call.

Parameter Description

Data Type	Description
String	{ "Jblost": "JB packet loss rate", "callid": "Call ID", "jitter": "Network jitter", "latency": "Network delay", "mos ": "Voice MOS value", "netLost": "Network packet loss rate" }

Triggering Condition

This event is triggered every 5 seconds after a voice call is set up.

Parent topic: [Call Events](#)

VoiceHoldResultEvent

Event Description

Call holding result event.

Parameter Description

Data Type	Description
String	{ "callid": "Call ID" "resultCode": "Result code" "resultDesc": "Result code description" }

Triggering Condition

This event is triggered when the interface of holding a specified call is invoked or another call is initiated.

Parent topic: [Call Events](#)

VoiceUnHoldResultEvent

Event Description

Result event for retrieving a held call.

Parameter Description

Data Type	Description
String	{ "callid": "Call ID" "resultCode": "Result code" "resultDesc": "Result code description" }

Triggering Condition

This event is triggered when the interface of retrieving a specified held call is invoked.

Parent topic: [Call Events](#)

VoiceTransferResultEvent

Event Description

Result reporting transfer event.

Parameter Description

Data Type	Description
String	{ "targetNumber": "Target number for the transfer" "callid": "Call ID" "resultCode": "Result code" "resultDesc": "Result code description" }

Triggering Condition

This event is triggered when the [Transfer](#) interface is invoked.

Parent topic: [Call Events](#)

Phone Linkage Events

- [VoiceCallJointStartResultEvent](#)
- [VoiceCallJointStopResultEvent](#)
- [VoiceStatusNotifyEvent](#)

Parent topic: [Event Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

VoiceCallJointStartResultEvent

Event Description

Phone linkage enabling result event. This event is sent to indicate whether the phone linkage is enabled.

Parameter Description

Data Type	Description
String	{ "phoneNumber": "Phone number for which the linkage will be enabled", "resultCode": "Result code 0: success Other values: error code" "resultDesc": "Error code description" }

Triggering Condition

This event is triggered when the [CallJointStart](#) interface is invoked or the linkage is stopped unexpectedly and restored.

Parent topic: [Phone Linkage Events](#)

VoiceCallJointStopResultEvent

Event Description

Phone linkage enabling result event. This event is sent to indicate whether the phone linkage is enabled.

Parameter Description

Data Type	Description
String	{ "phoneNumber": "Phone number for which the linkage will be enabled", "resultCode": "Result code 0: success Other values: error code" "resultDesc": "Result code description" }

Triggering Condition

This event is triggered when the [CallJointStop](#) interface is invoked or the linkage is stopped unexpectedly.

Parent topic: [Phone Linkage Events](#)

VoiceStatusNotifyEvent

Event Description

Phone linkage status reporting event.

Parameter Description

Data Type	Description
String	{ "phoneNumber": "Phone number for which the linkage will be enabled" "callid": "Call ID" "remoteNumber": "Phone number of the remote end", "status": "Phone status" } The options of status are as follows: • 0: online • 1: offline • 2: on-hook • 3: off-hook • 4: outgoing • 5: established • 6: ring • 7: hold • 8: unhold

Triggering Condition

This event is triggered in case of phone status updates. The phone may be offline, off-hook, on-hook, in a call, placing a call, holding a call, or retrieving a held call.

Parent topic: [Phone Linkage Events](#)

Conference Events

- [VoiceAddToLocalConfResultEvent](#)
- [VoiceDelFromLocalConfResultEvent](#)
- [VoiceDestroyLocalConfResultEvent](#)
- [VoiceHoldLocalConfResultEvent](#)

Parent topic: [Event Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

VoiceAddToLocalConfResultEvent

Event Description

Result event for joining a local conference.

Parameter Description

Data Type	Description
String	{ "callid": "Call ID" "resultCode": "Result code" "resultDesc": "Result code description" }

Triggering Condition

This event is triggered when the [AddToLocalConf](#) interface is invoked to join a local conference.

Parent topic: [Conference Events](#)

VoiceDelFromLocalConfResultEvent

Event Description

Result event for removing a specified call from the local conference.

Parameter Description

Data Type	Description
String	{ "callid": "Call ID" "resultCode": "Result code" "resultDesc": "Result code description" }

Triggering Condition

This event is triggered when the [DelFromLocalConf](#) interface is invoked to remove a specified call from the local conference.

Parent topic: [Conference Events](#)

VoiceDestroyLocalConfResultEvent

Event Description

Result event for ending a local conference.

Parameter Description

Data Type	Description
String	{ "resultCode": "Result code" "resultDesc": "Result code description" }

Triggering Condition

This event is triggered when a local conference is released.

Parent topic: [Conference Events](#)

VoiceHoldLocalConfResultEvent

Event Description

Result event for holding a local conference or retrieving the held conference.

Parameter Description

Data Type	Description
String	{ "isHold": "Value true indicates holding a local conference while value false indicates retrieving the held conference." "resultCode": "Result code" "resultDesc": "Result code description" }

Triggering Condition

This event is triggered when a local conference is held or the held conference is retrieved.

Parent topic: [Conference Events](#)

Device Events

[VoiceAidProcessStatusEvent](#)

[VoiceControlAudioAidDeviceResultEvent](#)

[VoiceVolumeExEvent](#)

[VoiceGainByCallEvent](#)

[VoiceSnapshotResultEvent](#)

Parent topic: [Event Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

VoiceAidProcessStatusEvent

Event Description

Auxiliary-process status event.

Parameter Description

Data Type	Description
String	{ "resultCode": "Result code", "resultDesc": "Result code description", "status": "Connection operation status" } The options of status are as follows: 0: Disconnect the auxiliary process. 1: Connect the auxiliary process.

Triggering Condition

This event is triggered when the [SetSoundCardAidConfig](#) interface is invoked, or Auxiliary-process is stopped.

Parent topic: [Device Events](#)

VoiceControlAudioAidDeviceResultEvent

Event Description

Result event for controlling the audio auxiliary device.

Parameter Description

Data Type	Description
String	{ "callid": "Call ID", "isStart": "Value true indicates starting while value false indicates stopping.", "resultCode": "Result code" "resultDesc": "Result code description" }

Triggering Condition

This event is triggered when the [ControlAudioAidDevice](#) interface is invoked.

Parent topic: [Device Events](#)

VoiceVolumeExEvent

Event Description

Voice volume operation event.

Parameter Description

Data Type	Description
String	{ "isGet": " true : Obtain the volume; false : Set the volume." "isMic": " true : microphone; false : speaker", "volume": "Volume" "resultCode": "Result code" "resultDesc": "Result code description" }

Triggering Condition

This event is triggered when the [GetVolumeEx](#) or [SetVolumeEx](#) interface is invoked.

Parent topic: [Device Events](#)

VoiceGainByCallEvent

Event Description

Gain operation event for a specified call.

Parameter Description

Data Type	Description
String	{ "callid": "Call ID", "isGet": " true : Obtain the volume; false : Set the volume." "gain": "Gain" "resultCode": "Result code" "resultDesc": "Result code description" }

Triggering Condition

This event is triggered when the [GetGainByCall](#) or [SetGainByCall](#) interface is invoked.

Parent topic: [Device Events](#)

VoiceSnapshotResultEvent

Event Description

Snapshot taking event.

Parameter Description

Data Type	Description
String	{ filePath: "Absolute path for storing images", "height": "Image height", "width": "Image width", "resultCode": "Result code", "resultDesc": "Result code description" }

Triggering Condition

This event is triggered when the [SnapShot](#) interface is invoked.

Parent topic: [Device Events](#)

Return Codes

Return Code	Description
0	Success.
1	Voice control uninitialized.
2	Point of param is null.
3	Param is empty.
4	Param is not a valid value.
5	Required information is not configured.
6	State wrong.
7	Load tup dll failed.
8	Set tup config value failed.
9	System unknown error.
10	Register canceled.
11	Normal error.
12	Indicates that the memory fails to be allocated.
13	No call.
14	The operating system sound card driver API is unusually unresponsive.Restart the PC to resolve this issue.
15	The operating system sound card driver switches abnormally to WMM mode.Sign in again to resolve this issue.
16	Audio driver error.Restart the PC to resolve this issue.
1000	Call tup api failed.
1001	TUP call general error.
1002	TUP call parameter error.
1003	TUP call memory alloc error.
1004	TUP call system error.
1005	TUP call send message error.
1006	TUP call system configuration error.
1007	TUP call physical network error.
1008	TUP call network access failed.
1009	TUP call create timer error.
1010	TUP call state error.
1011	TUP call some other operation has not finished error.
1012	TUP call request main control to call error.
1013	TUP call apply audio media resource error.
1014	TUP call additional service is on processing error.
1015	TUP call record call operation error.
1016	TUP call media process error.
1017	TUP call exist max call number error.
1018	TUP call sip account id not exist error.
1019	TUP call call id not exist error.
1020	TUP call registering error.
1021	TUP call invoke sip register interface error.
1022	TUP call invoke sip unregister interface error.
1023	TUP call set account info error.
1024	TUP call set sip module error.
1025	TUP call notification error.
1026	TUP call sip server information error.
1027	TUP call account information error.
1028	TUP call SIP error.
1029	TUP call unregister error.
1030	TUP call invoke sip subscribe interface error.

1031	TUP call undo subscribe error.
1032	TUP call subscribing error.
1057	TUP call network error.
1058	TUP call service conflict error.
1078	TUP call tls root cert error.

Parent topic: [Voice Interface \(ActiveX\)](#)

JSSDK Interface (JavaScript)

- [About This Document](#)
- [Overview](#)
- [Interface Description](#)
- [Event Definition](#)
- [Return Code](#)

Copyright © Chengdu TD-Tech Co., Ltd.

About This Document

[Intended Audience](#)

[Symbol Conventions](#)

[Change History](#)

Parent topic: [JSSDK Interface \(JavaScript\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Intended Audience

This document is intended for:

- Integration developers responsible for integrating the JavaScript multimedia collaboration capabilities

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Symbol Conventions

The symbols that may be found in this document are defined as follows.

Symbol	Description
	Indicates an imminently hazardous situation which, if not avoided, will result in death or serious injury.
	Indicates a potentially hazardous situation which, if not avoided, could result in death or serious injury.
	Indicates a potentially hazardous situation which, if not avoided, may result in minor or moderate injury.
	Indicates a potentially hazardous situation which, if not avoided, could result in equipment damage, data loss, performance deterioration, or unanticipated results. NOTICE is used to address practices not related to personal injury.
 NOTE	Calls attention to important information, best practices and tips. NOTE is used to address information not related to personal injury, equipment damage, and environment deterioration.

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Change History

[V100R023C00](#)

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V100R023C00

[V600R019C00SPC680](#)

[V600R019C00SPC670](#)

[V600R019C00SPC640](#)

[V600R019C00SPC636](#)

[V600R019C00SPC630](#)

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00SPC680

Compared with CloudIPCC V600R019C00SPC670, CloudIPCC V600R019C00SPC680 has the following updates.

Table 1 List of modified interfaces

Interface Type	Interface Name	Changes
MSP Installation Check: checkMSPIsInstall	CheckMSPIsInstall	Add the interface.

Table 2 Change events

Event Type	Event Name	Change Content
Media Service Notification Events: OnUpdateMsp	OnUpdateMsp	Add the event.

Parent topic: [V100R023C00](#)

V600R019C00SPC670

Compared with CloudIPCC V600R019C00SPC650, CloudIPCC V600R019C00SPC670 has the following updates. CloudIPCC V600R019C00SPC636 is a branch version and corresponds to CloudIPCC V600R019C00SPC650.

Table 1 List of modified interfaces

Interface Type	Interface Name	Changes
Forcibly Initializing the MSP: forcInitMSP	Forcibly Initializing the MSP	The initialization level parameter is added.

Parent topic: [V100R023C00](#)

V600R019C00SPC640

Compared with CloudIPCC V600R019C00SPC630, CloudIPCC V600R019C00SPC630 has the following updates.

Table 1 Change events

Event Type	Event Name	Change Content
Resource Status Notification Event: OnUserStatusNotify	OnUserStatusNotify	Modified the event description.
Call Events: OnCallRelease	OnCallRelease	Modified the event description.

Parent topic: [V100R023C00](#)

V600R019C00SPC636

Compared with CloudIPCC V600R019C00SPC636, CloudIPCC V600R019C00SPC636 has the following updates. CloudIPCC V600R019C00SPC636 is a branch version and corresponds to CloudIPCC V600R019C00SPC650.

Table 1 Change events

Event Type	Event Name	Change Content
Resource Status Notification Event: OnUserStatusNotify	OnUserStatusNotify	Add the rsp reason code.
Resource Status Notification Event: OnMicOrSpeakerStateNotify	OnMicOrSpeakerStateNotify	Add the event.

Parent topic: [V100R023C00](#)

V600R019C00SPC630

Compared with CloudIPCC V600R019C00SPC591, there are no changes in this version.

Parent topic: [V100R023C00](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Overview

- [Introduction](#)
- [Development Environment](#)
- [Applicable Scope](#)
- [Conventions](#)
- [Terms Explanation](#)

Parent topic: [JSSDK Interface \(JavaScript\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Introduction

The JSSDK provides unified multimedia capabilities.

Parent topic: [Overview](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Development Environment

- System: Windows 10
- Browser: Chrome 58 or later is recommended.

Parent topic: [Overview](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Applicable Scope

This document describes all interfaces provided by the IPCC JSSDK in detail.

Parent topic: [Overview](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Conventions

In this document, the description of each interface function consists of the following parts: interface description, prerequisites, interface definition, parameter description, return code, exceptions, and precautions. JSON character strings must be parsed before they are used to determine the invocation result of an interface or event. Full matching of JSON character strings may cause incompatibility between the new and earlier versions.

NOTICE

The JSSDK does not support opening multiple windows in the same browser.

Prerequisites

Describes the prerequisites that must be met to invoke an interface.

Interface Function

Describes the functions of an interface.

Interface Prototype

Provides the form in which an interface exists in code, including the interface name, number of parameters, and name of each parameter.

Parameter Description

Describes all parameters involved in an interface in detail. The description includes the value range and type of each parameter.

In this section, parameters are listed in a table, which contains the following columns: **Parameter**, **M/O** (mandatory/optional), **In/Out** (input or output parameter), **Type** (int or string), and **Description** (value range and other conditions).

Return Code or Value

Describes the code that is returned when an interface is invoked.

Exception Handling

Describes responses for exceptions that occur during interface invoking.

Invoking Description

Describes precautions for using an interface.

Event Parameter

Refers to triggered event parameters, transmitting event information.

Parent topic: [Overview](#)

Terms Explanation

None

Parent topic: [Overview](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Interface Description

[Initialization Interfaces](#)

[Call Interfaces](#)

[Device Interfaces](#)

Parent topic: [JSSDK Interface \(JavaScript\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Initialization Interfaces

[Initializing the JS SDK](#)

[Forcibly Initializing the MSP](#)

[Querying Version Number](#)

[Event Registration](#)

[Deregistration](#)

[Registration](#)

Parent topic: [Interface Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Initializing the JS SDK

Prerequisites

- The **ICPSDK_ALL.js** file has been referenced in the code.

Interface Function

The interface is used to initialize the ICP-C JSSDK.

Interface Definition

New ICPCSDK (param)

Parameter Description

Parameter	M/O	Type	Description
serverAddress	M	string	Indicates the IP address and port number of the CAC server: xx.xx.xx.xx, port.
sdkStatusNotify	M	function	Indicates the SDK status notification callback.
debugMode	O	bool	Indicates whether to enable the debug mode to record interface invoking logs to the log folder in the local media library. The default value is false . The options are true and false . In the development and test phases, you are advised to enable the debug log to provide more detailed SDK running information and error messages for fault locating. You are advised to disable the debug log during version release to improve program running efficiency.
localMediaServiceWSPort	O	string	Indicates the websocket port number of the local daemon process. Default value: 17804
localDeamonServiceWSPort	O	string	Indicates the websocket port number of the local daemon process. Default value: 17803
ringFlag	O	string	The value 0 indicates that the local ring tone is played by default. Other numeric strings indicate that the ring tone of the server is played. The default value is 0 , indicating that the local ring tone is played.
ssl_enable	O	bool	Indicates whether the WebSocket connection uses SSL encryption. The options are true (WSS connection) and false (WS connection). If this parameter is left blank, the WSS connection is used by default. If there is a video window, set this parameter to wssflow . The value of ssl_enable must be the same as that in the MSP_Config.ini file in the MSP installation path. (If the upper-layer application is an HTTPS page, ssl_enable must be set to true .)
mode	O	string	Indicates the video window mode. The pop-up window mode is used by default. window : pop-up window mode wssflow : H5 embedded mode
isLocalCamerWindow	O	bool	Indicates whether to display the local camera window for a P2P video call. By default, the window is not displayed. true : display false : not display

The content of the sdkStatusNotify notification is as follows.

Parameter	Type	Description
status	string	Indicates the SDK status. 0: The SDK is successfully initialized. 1: The local daemon process fails to be connected. The SDK is initialized by page reloading. 2: The local media server fails to be connected. The SDK is initialized by page reloading. 3: The local IP address fails to be obtained. The SDK is initialized by page reloading. 4: The local camera fails to be obtained. The SDK is initialized by page reloading.
desc	string	Indicates the status description.

Response Parameter

Forcibly Initializing the MSP

Prerequisites

- The ICPSDK_ALL.js file has been referenced in the code.

Interface Function

This interface is used to forcibly initialize the ICP-C audio and video media server MSP.

Interface Definition

```
cloudICP.call.device.forceInitMSP(param)
```

Parameter Description

Parameter	M/O	Type	Description
callback	M	function	Indicates the callback function for returning a result.
flag	O	string	Initialization Level.

The initialization level are as follows.

ParameterValue	Description
0	Default value. Only the connection between the JS and MSP is initialized.
1	Restart the TPP_S process.

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result. The value 0 indicates a success, and other values indicate failures. For details, see the error code.
desc	string	Describes the failure cause.

Parent topic: [Initialization Interfaces](#)

Querying Version Number

Prerequisites

- The SDK initialization has been complete.
- A user has logged in.

Interface Function

The interface is used to query the ICP-C JSSDK version number.

Interface Definition

```
cloudICP.call.device.getVersion(param)
```

Parameter Description

Parameter	M/O	Type	Description
callback	M	function	Indicates the callback function for returning a result.

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result.
desc	string	Describes the reason code.
versions	object	Indicates the version information.

Description of the parameter **versions**

Parameter	Type	Description
mvpVersion	string	Indicates the media service version.
sdkVersion	string	Indicates the interface version.

Parent topic: [Initialization Interfaces](#)

Event Registration

Prerequisites

- The SDK initialization has been complete.
- A user has logged in.

Interface Function

This interface is used to register the events to be processed.

Interface Definition

cloudICP.call.event.register (param)

Parameter Description

Parameter	M/O	Type	Description
eventType	M	string	Indicates the event type.
eventName	M	string	Indicates the event name.
callback	M	function	Indicates the processing method after an event is received.

The event types are as follows.

Event Type	Description
ModuleNotify	Indicates the module status notification.
CallNotify	Indicates the audio or video status notification.
ResourceNotify	Indicates the resource status notification.
MSPNotify	Indicates the media service notification.

Response Parameter

Parent topic: [Initialization Interfaces](#)

Deregistration

Prerequisites

- The SDK initialization has been complete.
- A user has logged in.

Interface Function

The interface is used to deregister the ICP-C JS SDK (analog phone) from the CAC.

Interface Definition

```
cloudICP.call.auth.logout(param)
```

Parameter Description

Parameter	M/O	Type	Description
callback	M	function	Indicates the callback function for returning a result.

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result.
desc	string	Describes the reason code.

The actual login result is reported through **ResourceNotify**.

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the status code. 4011 : The SIP registration succeeds. 4012 : The SIP registration fails. 4014 : The user does not exist.

Parent topic: [Initialization Interfaces](#)

Registration

Prerequisites

- The SDK initialization has been complete.

Interface Function

The interface is used to register the ICP-C JS SDK (analog phone) from the CAC.

Interface Definition

```
cloudICP.call.login(param)
```

Parameter Description

Parameter	M/O	Type	Description
user	M	string	Indicates the user name. The user number contains a maximum of 18 digits and cannot start with 0. It does not belong to the MRS number segment (99900001 to 99909999) and cannot be the same as the CC access code.
password	M	string	Indicates the password. The value contains 8 to 32 characters.
callback	M	function	Indicates the callback function for returning a result.

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result.
desc	string	Describes the reason code.

The actual login result is reported through **resourceNotify**.

Parameter	Type	Description
eventName	string	Indicate the event name (sip register).
rsp	string	Indicates the status code. 4011 : The SIP registration succeeds. 4012 : The SIP registration fails. 4014 : The user does not exist.

Parent topic: [Initialization Interfaces](#)

Call Interfaces

[Dial](#)

[Answer](#)

[Release](#)

[Reject](#)

[mute](#)

[getCurrentCall](#)

Parent topic: [Interface Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Dial

Prerequisites

1. A phone number has been registered.
2. The phone is in the standby state (no call), or the current call is held or muted.
3. If the video call is currently active, no video calls are allowed.

Interface Function

This interface is used to initiate an audio or video call.

Interface Definition

```
cloudICP.call.call.dial(param)
```

Parameter Description

Parameter	M/O	Type	Description
callee	M	string	Indicates the called number. The value is a numeric string. The length of the called number ranges from 1 to 18.
isVideo	O	bool	Indicates whether to initiate a P2P video call. The default value is false . true : video call false : voice call
videoParam	O	object	1. This parameter is invalid when isVideo is set to false . 2. If this parameter is left blank, the default window size is 640 x 480 for a video call, and the values of posX and posY in the upper left corner of the window are 400 .
callback	M	string	Indicates the callback function for returning a result.

Description of the **videoParam** parameter

Parameter	M/O	Type	Description
fmt	O	string	Indicates the resolution, which can be 720p, D1, CIF, or QCIF. If this parameter is not set, the default value 720p is used. Notes: (1) Set the parameter based on the query result of the interface for invoking and querying local camera capabilities. (2) The resolution is not the final resolution. The final resolution is displayed in subsequent video call events after negotiation.
width	O	string	[Pop-up window mode] (Optional) Indicates the window width, in pixels. [H5 embedded mode] Indicates the div width, in pixels.
height	O	string	[Pop-up window mode] (Optional) Indicates the window height, in pixels. [H5 embedded mode] Indicates the div height, in pixels.
posX	O	string	Indicates the horizontal axis position of the video window. The value is 0 in the upper left corner of the screen.
posY	O	string	Indicates the vertical axis position of the video window. The value is 0 in the upper left corner of the screen.
mode	O	string	Indicates whether the pop-up window mode or embedded mode is used. By default, the configuration is made by using <code>cloudICP.config["mode"]</code> .
isShowToolBar	O	bool	[Pop-up window only] Indicates whether the window border is displayed. By default, the window border is not displayed. false : not display true : display
isLocalCameraWindow	O	bool	Indicates whether to display the local camera window for a P2P video call. By default, the window is not displayed. true : display false : not display

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result.
desc	string	Describes the reason code.

Parent topic: [Call Interfaces](#)

Answer

Prerequisites

The call ringing event has been received.

Interface Function

This interface is used to answer an audio or video call.

Interface Definition

```
cloudICP.call.call.answer(param)
```

Parameter Description

Parameter	M/O	Type	Description
callId	M	string	Indicates the call ID.
videoParam	O	object	If this parameter is left blank, the default window size is 640 x 480 and the window is in the lower right corner of the screen. If this parameter is left blank, the default window size in pop-up window mode is 640 x 480, and the values of posX and posY in the upper left corner of the window are 400 .
callback	M	string	Indicates the callback function for returning a result.

For details about the **videoParam** parameter, see the description of the audio or video call interface.

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result.
desc	string	Describes the reason code.

Parent topic: [Call Interfaces](#)

Release

Prerequisites

A call is in progress.

Interface Function

This interface is used to end an audio or video call.

Interface Definition

```
cloudICP.call.call.release(param)
```

Parameter Description

Parameter	M/O	Type	Description
callId	M	string	Indicates the call ID.
callback	M	string	Indicates the callback function for returning a result.

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result.
desc	string	Describes the reason code.

Parent topic: [Call Interfaces](#)

Reject

Prerequisites

The call ringing event has been received.

Interface Function

This interface is used to reject an audio or video call.

Interface Definition

```
cloudICP.call.call.reject(param)
```

Parameter Description

Parameter	M/O	Type	Description
callId	M	string	Indicates the call ID.
callback	M	string	Indicates the callback function for returning a result.

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result.
desc	string	Describes the reason code.

Parent topic: [Call Interfaces](#)

mute

Prerequisites

A call has been set up.

Interface Function

The interface is used to mute or unmute a specified call.

Interface Definition

```
cloudICP.call.call.mute(param)
```

Parameter Description

Parameter	M/O	Type	Description
callId	M	string	Indicates the call ID. -1 : All participants are muted.
flag	M	bool	Indicates the muting/unmuting flag. true : mute false : unmute
micOrSpeaker	O	bool	The default value is 0 . 0 : Mute the speaker. 1 : Mute the microphone. 2 : Mute the speaker and microphone.
callback	M	string	Indicates the callback function for returning a result.

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result.
desc	string	Describes the reason code.

Parent topic: [Call Interfaces](#)

getCurrentCall

Prerequisites

Information about ongoing calls exists.

Interface Function

This interface is used to obtain information about the current call.

Interface Definition

```
cloudICP.call.call.getCurrentCall(param)
```

Parameter Description

Parameter	M/O	Type	Description
callId	M	string	Indicates the call ID. If this parameter does not exist, the current call information is returned by default.
callback	M	string	Indicates the callback function for returning a result.

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result.
desc	string	Describes the reason code.
value	object	Queries the result.

Object information of value

Parameter	M/O	Type	Description
caller	O	string	Indicates the calling party.
callee	O	string	Indicates the called party.
callType	O	string	Indicates the call type.
callId	O	string	Indicates the ID of a call.

Parent topic: [Call Interfaces](#)

Device Interfaces

[GetSoundDevice](#)

[SetSoundDevice](#)

[QueryCameraAbility](#)

[GetVolume](#)

[SetVolume](#)

[CheckMSPIsInstall](#)

Parent topic: [Interface Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

GetSoundDevice

Prerequisites

The SDK has been initialized.

Interface Function

This interface is used to query the local speaker and microphone list.

Interface Definition

cloudICP.call.device.getSoundDevice (param)

Parameter Description

Parameter	M/O	Type	Description
callback	M	string	Indicates the callback function for returning a result.

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result.
desc	string	Describes the reason code.

Parent topic: [Device Interfaces](#)

SetSoundDevice

Prerequisites

The SDK has been initialized.

Interface Function

This interface is used to switch the local speaker and microphone list.

Interface Definition

cloudICP.call.device.setSoundDevice (param)

Parameter Description

Parameter	M/O	Type	Description
callId	M	string	Indicates the call ID. If the parameter is set to -1, an audio card is bound. If the parameter is set to a call ID, an audio card is switched.
number	M	string	Indicates the user number bound to the audio card.
outputDev	M	string	Indicates the name of a speaker audio card.
inputDev	M	string	Indicates the name of a microphone audio card.
callback	M	string	Indicates the callback function for returning a result.

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result.
desc	string	Describes the reason code.

Parent topic: [Device Interfaces](#)

QueryCameraAbility

Prerequisites

The SDK has been initialized.

Interface Function

This interface is used to query the local camera capability.

Interface Definition

cloudICP.call.device.queryCameraAbility (param)

Parameter Description

Parameter	M/O	Type	Description
callback	M	string	Indicates the callback function for returning a result.

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result.
desc	string	Describes the reason code.
camera_ability	string	Indicates the local camera capability. 1(QCIF)+2(CIF)+4(D1)+8(720P)+16(1080P)+32(2K)+64(4K) (If D1 and CIF are supported, the value is 6.)

Parent topic: [Device Interfaces](#)

GetVolume

Prerequisites

The SDK has been initialized.

Interface Function

This interface is used to query speaker volume.

Interface Definition

```
cloudICP.call.device.getVolume(param)
```

Parameter Description

Parameter	M/O	Type	Description
callId	M	string	Indicates the call ID. When the value of callId is -1 , the volume of all current calls is set.
callback	M	string	Indicates the callback function for returning a result.

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result.
desc	string	Describes the reason code.

Parent topic: [Device Interfaces](#)

SetVolume

Prerequisites

The SDK has been initialized.

Interface Function

This interface is used to set speaker volume.

Interface Definition

```
cloudICP.call.device.setVolume(param)
```

Parameter Description

Parameter	M/O	Type	Description
callId	M	string	Indicates the call ID. When the value of callId is -1, the volume of all current calls is set.
volume	M	string	Specifies the volume. The value range is [0,100].
callback	M	string	Indicates the callback function for returning a result.

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result.
desc	string	Describes the reason code.

Parent topic: [Device Interfaces](#)

CheckMSPisInstall

Prerequisites

The SDK has been initialized.

Interface Function

Check whether the MSP plug-in is installed on the local host. When this interface is invoked, the IP address of the CAC server must be transferred.

Interface Definition

```
cloudICP.call.device.checkMSPisInstall(param)
```

Parameter Description

Parameter	M/O	Type	Description
cacip	M	string	IP address of the CAC.
callback	M	function	Indicates the callback function for returning a result.

Response Parameter

Parameter	Type	Description
isInstall	bool	false: not installed; true: has been installed.
downloadUrl	string	If the MSP is not installed, the link for downloading the MSP installation package is provided. This field does not exist if it has been installed.

Parent topic: [Device Interfaces](#)

Event Definition

[Media Service Notification Events](#)

[Resource Status Notification Event](#)

[Call Events](#)

Parent topic: [JSSDK Interface \(JavaScript\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Media Service Notification Events

[OnGetSoundDeviceResult](#)

[OnSetSoundDeviceResult](#)

[OnGetVolumeResult](#)

[OnSetVolumeResult](#)

[OnMuteMicOrSpeakerResult](#)

[OnUnmuteMicOrSpeakerResult](#)

[OnUpdateMsp](#)

[GetResultDesc](#)

Parent topic: [Event Definition](#)

Copyright © Chengdu TD-Tech Co., Ltd.

OnGetSoundDeviceResult

Event Description

This event is returned when the operation of querying the speaker and microphone list results is successful.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the event code.
value	object	Indicates the event content.

Description of the **value** parameter

Parameter	Type	Description
speaker	array	Indicates the speaker list. The first 32 characters of each speaker name are obtained.
mic	array	Indicates the microphone list. The first 32 characters of each microphone name are obtained.

Parent topic: [Media Service Notification Events](#)

OnSetSoundDeviceResult

Event Description

This event is returned when the operation of binding the speaker and microphone is successful. The event type is **MSPNotify**.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the event code.
value	object	Indicates the event content.

Description of the **value** parameter

Parameter	Type	Description
outputDev	string	Indicates the output audio card.
inputDev	string	Indicates the input audio card.

Parent topic: [Media Service Notification Events](#)

OnGetVolumeResult

Event Description

This event is returned when the operation of setting the speaker volume is successful.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the event code.
value	object	Indicates the event content.

Description of the **value** parameter

Parameter	Type	Description
callId	string	Indicates the call ID.
volume	string	Describes the volume.

Parent topic: [Media Service Notification Events](#)

OnSetVolumeResult

Event Description

This event is returned when the operation of setting the speaker volume is successful.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the result code.
value	object	Indicates the event content.

Description of the **value** parameter

Parameter	Type	Description
callId	string	Indicates the call ID.
newVolume	string	Describes the volume.

Parent topic: [Media Service Notification Events](#)

OnMuteMicOrSpeakerResult

Event Description

This event is returned when the operation of muting the speaker and microphone is successful.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the result code.
value	object	Indicates the event content.

Description of the **value** parameter

Parameter	Type	Description
micOrSpeaker	bool	0: Mute the speaker. 1: Mute the microphone. 2: Mute the speaker and microphone.

Parent topic: [Media Service Notification Events](#)

OnUnmuteMicOrSpeakerResult

Event Description

This event is returned when the operation of unmuting the speaker and microphone is successful.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the result code.
value	object	Indicates the event content.

Description of the **value** parameter

Parameter	Type	Description
micOrSpeaker	bool	0: Mute the speaker. 1: Mute the microphone. 2: Mute the speaker and microphone.

Parent topic: [Media Service Notification Events](#)

OnUpdateMsp

Event Description

When the JSSDK and MSP versions are different,the JSSDK version is used to check the version number,this event is used to send notifications.

 **NOTE**

The automatic update, download, and installation functions need to be developed by upper-layer applications based on customer requirements. The current version provides the version verification, MSP update event notification, MSP version package download, and MSP version package silent installation functions.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
mspVersion	string	Indicates the msp version.
downloadUrl	string	Indicates the msp download url corresponding to the jssdk version number.

Parent topic: [Media Service Notification Events](#)

GetResultDesc

Prerequisites

- The SDK initialization has been complete.

Interface Function

The detailed description of the error is returned based on the error code.

Interface Definition

```
cloudICP.call.event.getResultDesc(param)
```

Parameter Description

Parameter	M/O	Type	Description
code	M	string	Indicates the error code.
callback	M	string	Indicates the callback function for returning a result.

Response Parameter

Parameter	Type	Description
rsp	string	Indicates the interface invocation result.
desc	string	Describes the reason code.

Parent topic: [Media Service Notification Events](#)

Resource Status Notification Event

[OnUserStatusNotify](#),

[OnMicOrSpeakerStateNotify](#).

Parent topic: [Event Definition](#)

Copyright © Chengdu TD-Tech Co., Ltd.

OnUserStatusNotify

Event Description

A user status change is notified. When an IP phone is faulty, a user status change notification event with status code 4012 is reported.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the user list status.

Description of the **rsp** parameter

Value	Description
4011	The user registration is successful.
4012	The user is deregistered.
4013	The user registration failed due to the password is incorrect.
4014	The user registration failed due to the user does not exist.
4015	The user registration failed due to an internal server error.
4016	The user goes offline after the heartbeat times out.
4018	The user registration failed due to other reasons.
4019	The user registration request is suspended.

Parent topic: [Resource Status Notification Event](#)

OnMicOrSpeakerStateNotify

Event Description

Audio device status change notification.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
deviceName	string	Indicates the audio device name.
newState	string	Indicates the latest status of the audio device.

Description of the **newState** parameter

Value	Description
1	The audio device is active.
2	The audio device disabled
4	The audio device does not exist.
8	The audio device is unplugged.

Parent topic: [Resource Status Notification Event](#)

Call Events

[OnDialOutProceeding](#)

[OnDialOutRinging](#)

[OnCallConnect](#)

[OnDialOutFailure](#)

[OnCallRelease](#)

[OnDialInRinging](#)

[OnConnectProceeding](#)

[OnCallException](#)

Parent topic: [Event Definition](#)

Copyright © Chengdu TD-Tech Co., Ltd.

OnDialOutProceeding

Event Description

The current user is making an outgoing call.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the event code: 2005: outbound voice call 2006: outgoing video call
value	object	Indicates the event content.

Description of the **value** parameter

Parameter	Type	Description
callId	string	Indicates the call ID.
caller	string	Indicates the calling number.
callee	string	Indicates the called number.
callType	string	video : video call voice : voice call
fmt	string	Indicates the video format.

Parent topic: [Call Events](#)

OnDialOutRinging

Event Description

The called party receives the call and the called party's terminal is ringing.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the event code: 2006 : ringback event for an outgoing voice call 3005 : ringback event for an outgoing video call
value	object	Indicates the event content.

Description of the **value** parameter

Parameter	Type	Description
callId	string	Indicates the call ID.
caller	string	Indicates the calling number.
callee	string	Indicates the called number.
callType	string	video : video call voice : voice call
fmt	string	Indicates the video format. For a voice call, this parameter is invalid. For a video call, the value of this parameter indicates the resolution obtained after the negotiation. The options are as follows: 0 : CIF 1 : QCIF 2 : D1 3 : 720p 4 : 1080p 5 : 2K 6 : 4K 7 : INVALID_FMT

Parent topic: [Call Events](#)

OnCallConnect

Event Description

A call is set up.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the event code: 2003 : outgoing voice call 2007 : incoming voice call 3003 : outgoing video call 3006 : incoming video call
value	object	Indicates the event content.

Description of the **value** parameter

Parameter	Type	Description
callId	string	Indicates the call ID.
caller	string	Indicates the calling number.
callee	string	Indicates the called number.
callType	string	video : video call voice : voice call
fmt	string	Indicates the video format.
direction	string	in : incoming call out : outgoing call
wssflow	string	[Only in H5 embedded mode] This parameter is used when a player is created at the frontend. The input parameter playerConfig.wsUrl in new MSP_PLAYER(playerConfig) is used.

Parent topic: [Call Events](#)

OnDialOutFailure

Event Description

The outgoing call fails to be set up.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the event code. Voice call scenarios: • 2013: The called party is busy. • 2016: The calling party has no permission to make an outbound call. • 2017: The call is not answered and times out. • 2018: The called number does not exist. • 2024: The called party is offline or hangs up the call. • 2049: The called party does not support this operation. • 2052: The called party has no incoming call answering permission. • 2023: The called party does not support the required audio format. • 2033: The terminal of the called party is powered off. • 2048: The calling party does not support this operation. Video call scenarios: • 3013: The called party is busy. • 3014: The calling party has no permission to make a P2P video call. • 3015: The called party times out. • 3016: The called number does not exist. • 3021: The called party is offline or hangs up the call. • 3044: The calling party does not support this operation. • 3045: The called party does not support this operation. The possible cause is that the called party has no permission or does not support the resolution. • 3048: The called party has no permission.
value	object	Indicates the event content.

Description of the **value** parameter

Parameter	Type	Description
callId	string	Indicates the call ID.
caller	string	Indicates the calling number.
callee	string	Indicates the called number.
callType	string	video : video call voice : voice call
fmt	string	Indicates the video format.

Parent topic: [Call Events](#)

OnCallRelease

Event Description

A call is hung up after being set up. If an active/standby switchover occurs on CAC during a call on an IP phone, the IP phone releases the call and reports the OnCallRelease event after the call heartbeat times out for three times after the switchover.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the event code. 2009 : The voice call is hung up by the called party. 2011 : The voice call request is canceled. 2010 : The voice call is hung up by the calling party. 3009 : The video call is hung up by the calling party. 3008 : The video call is hung up by the called party. 3010 : The video call request is canceled. 3013 : The called party of the video call is busy.
value	object	Indicates the event content.

Description of the **value** parameter

Parameter	Type	Description
callId	string	Indicates the call ID.
caller	string	Indicates the calling number.
callee	string	Indicates the called number.
callType	string	video : video call voice : voice call
fmt	string	Indicates the video format.
direction	string	in : incoming call out : outgoing call
releaseType	string	self : proactive hang-up other : passive hang-up
wssflow	string	[Only in H5 embedded mode] This parameter is used when a player is created at the frontend. The input parameter playerConfig.wsUrl in new MSP_PLAYER(playerConfig) ; is used.

Parent topic: [Call Events](#)

OnDialInRinging

Event Description

An inbound call is received.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the event code: 2002 : incoming voice call ringing 3002 : incoming video call ringing
value	object	Indicates the event content.

Description of the **value** parameter

Parameter	Type	Description
callId	string	Indicates the call ID.
caller	string	Indicates the calling number.
callee	string	Indicates the called number.
callType	string	video : video call voice : voice call
fmt	string	Indicates the video format.

Parent topic: [Call Events](#)

OnConnectProceeding

Event Description

The current user answers the call.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the event code: 2040 : answering an incoming voice call 3040 : answering an incoming video call
value	object	Indicates the event content.

Description of the **value** parameter

Parameter	Type	Description
callId	string	Indicates the call ID.
caller	string	Indicates the calling number.
callee	string	Indicates the called number.
callType	string	video : video call voice : voice call
fmt	string	Indicates the video format.
direction	string	in : incoming call out : outgoing call

Parent topic: [Call Events](#)

OnCallException

Event Description

A call is abnormal.

Parameter Description

Parameter	Type	Description
eventName	string	Indicates the event name.
rsp	string	Indicates the event code: 2000 : no media data
value	object	Indicates the event content.

Description of the **value** parameter

Parameter	Type	Description
callId	string	Indicates the call ID.
caller	string	Indicates the calling number.
callee	string	Indicates the called number.
callType	string	Indicates the call type.

Parent topic: [Call Events](#)

Return Code

Return Code	Description
0	Operation success.
1	Resource already exist.
2	Resource not exist.
3	No resource.
4	Param is invalid.
5	User is not login.
6	User phone is not idle.
7	Can not dial self.
8	Msp internal error.
9	Listen address failed.
10	Call state error.
20	Callee is null or invalid.
21	IsVideo param must be boolean.
22	CallId is not valid.
23	User phone is not active.
24	CallId is null.
25	The user number bound to the sound card is empty.
26	Speaker sound card name is empty.
27	Microphone sound card name is empty.
28	Volume is empty or checked failed.
29	Flag to mute or unmute is empty or is not boolean.
30	Current state is the same as flag.
31	MicOrSpeaker is 1 or 2 or 0, default 0".

Parent topic: [JSSDK Interface \(JavaScript\)](#)

Conference Interfaces (ActiveX)

- [About This Document](#)
- [Overview](#)
- [Data Type](#)
- [Interface Description](#)
- [Event Description](#)
- [Return Code](#)

Copyright © Chengdu TD-Tech Co., Ltd.

About This Document

[Intended Audience](#)

[Safety Notices](#)

[Reference Documents](#)

[Symbol Conventions](#)

[Change History](#)

Parent topic: [Conference Interfaces \(ActiveX\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Intended Audience

Applicable Audience

The document is intended for:

- Integration developers responsible for integrating the Conference Object Linking and Embedding Control eXtension (OCX) multimedia collaboration capabilities.

Skill Requirements

1. To integrate the ActiveX control through web pages, developers must meet the following requirements:
 - Be equipped with JavaScript development skills.
 - Be proficient in JSON.
 - Know how to use the ActiveX control that is integrated through web pages.
 - Understand MFC-based C++ or C# control development.
2. To integrate the ActiveX control through C#, developers must meet the following requirements:
 - Be equipped with C# development skills.
 - Know how to use the ActiveX control that is integrated through C#.
 - Be proficient in JSON.
 - Be proficient in Visual Studio 2010.
3. To integrate the ActiveX control through C++, developers must meet the following requirements:
 - Be equipped with MFC-based C++ development skills.
 - Be proficient in MFC.
 - Be proficient in JSON.
 - Know how to use the ActiveX control that is integrated through MFC-based C++.
 - Be proficient in Visual Studio 2010.
4. To integrate the ActiveX control through Java JNI, developers must meet the following requirements:
 - Be proficient in JSON.
 - Know how to use the ActiveX control that is integrated through Java JNI.
 - Be proficient in a Java development tool, such as the Eclipse.

Parent topic: [About This Document](#)

Safety Notices

- Document sharing/Desktop sharing/Remote control

When agents are processing complex problems proposed by users, the document sharing/desktop sharing/remote control function can assist in the presentation/operation. The document sharing/desktop sharing/remote control function can be enabled only after it is confirmed by users or initiated by users. Document sharing/whiteboard sharing/desktop sharing/remote control is a real-time operation, during which no user information will be recorded.

It is recommended that you enable these functions only when being allowed by local laws and regulations. When using and storing communication information of users, you must take measures to prevent the information from leakage. Engineers must comply with applicable laws and regulations and take measures to protect user data.

- Photoshot

For some financial services, users' photos are required for material archiving. Users take the photos by themselves and send the photos to agents for material archiving. The photos will be deleted after the user materials are archived. No user information will be recorded. It is recommended that integrators should let users understand the photoshot function, guide users to take and send the photos, and delete the photos after the materials are archived when integrators develop services.

It is recommended that you enable these functions only when being allowed by local laws and regulations. When using and storing communication information of users, you must take measures to prevent the information from leakage. Engineers must comply with applicable laws and regulations and take measures to protect user data.

Parent topic: [About This Document](#)

Reference Documents

[Table 1](#) lists the document provided for the Conference OCX interface.

Table 1 Conference OCX interface document

Document	Description
Conference Interface Reference (ActiveX)	This document describes Conference OCX interfaces and events in detail, including the interface prototypes, parameters, and return codes.

Parent topic: [About This Document](#)

Symbol Conventions

The symbols that may be found in this document are defined as follows.

Symbol	Description
 DANGER	Indicates an imminently hazardous situation which, if not avoided, will result in death or serious injury.
 WARNING	Indicates a potentially hazardous situation which, if not avoided, could result in death or serious injury.
 CAUTION	Indicates a potentially hazardous situation which, if not avoided, may result in minor or moderate injury.
 NOTICE	Indicates a potentially hazardous situation which, if not avoided, could result in equipment damage, data loss, performance deterioration, or unanticipated results. NOTICE is used to address practices not related to personal injury.
 NOTE	Calls attention to important information, best practices and tips. NOTE is used to address information not related to personal injury, equipment damage, and environment deterioration.

Parent topic: [About This Document](#)

Change History

- [V100R023C00](#)
- [V100R022C00](#)
- [V600R019C00](#)
- [V600R006C10](#)
- [V200R001C80](#)

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V100R023C00

V600R019C00SPC630

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00SPC630

Compared with V600R019C00SPC591, V600R019C00SPC630 does not include any changes.

Parent topic: [V100R023C00](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V100R022C00

V600R019C00SPC590

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00SPC590

Compared with V600R019C00SPC580, V600R019C00SPC590 does not include any changes.

Parent topic: [V100R022C00](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00

V600R019C00

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R019C00

No change is made in CloudIPCC V600R019C00 compared with CloudIPCC V600R006C10.

Parent topic: [V600R019C00](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R006C10

V600R006C10

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V600R006C10

The following table describes changes made in IPCC V600R006C10 compared with IPCC V200R001C80SPC703.

Interface Changes

None

Event Changes

None

Document Content Changes

Table 1 Document content changes

Location	Mode	Change Content	Reason
JoinConf	Modify	Added the ClusterType parameter for joining a conference.	The function of using the SBC as a proxy of the MS for conference joining is added.

Parent topic: [V600R006C10](#)

V200R001C80

[V200R001C80SPC703](#)

[V200R001C80SPC702](#)

[V200R001C80SPC701](#)

[V200R001C80SPC700](#)

[V200R001C80SPC600](#)

[V200R001C80SPC500](#)

[V200R001C80SPC400](#)

[V200R001C80SPC300](#)

[V200R001C80SPC200](#)

[V200R001C80SPC100](#)

[V200R001C80](#)

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC703

No change is made in CloudIPCC V200R001C80SPC703 compared with CloudIPCC V200R001C80SPC702.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC702

No change is made in CloudIPCC V200R001C80SPC702 compared with CloudIPCC V200R001C80SPC701.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC701

No change is made in CloudIPCC V200R001C80SPC701 compared with CloudIPCC V200R001C80SPC700.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC700

No change is made in CloudIPCC V200R001C80SPC700 compared with CloudIPCC V200R001C80SPC600.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC600

No change is made in CloudIPCC V200R001C80SPC600 compared with CloudIPCC V200R001C80SPC500.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC500

No change is made in CloudIPCC V200R001C80SPC500 compared with CloudIPCC V200R001C80SPC400.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC400

No change is made in CloudIPCC V200R001C80SPC400 compared with CloudIPCC V200R001C80SPC300.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC300

No change is made in CloudIPCC V200R001C80SPC300 compared with CloudIPCC V200R001C80SPC200.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC200

No change is made in CloudIPCC V200R001C80SPC200 compared with CloudIPCC V200R001C80SPC100.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80SPC100

No change is made in CloudIPCC V200R001C80SPC100 compared with CloudIPCC V200R001C80.

Parent topic: [V200R001C80](#)

Copyright © Chengdu TD-Tech Co., Ltd.

V200R001C80

The following tables describe changes made in CloudIPCC V200R001C80 compared with CloudIPCC V200R001C60SPC100.

Interface Changes

Table 1 New interface list

Interface Type	Change Content
Video interfaces	Snapshot
Document sharing interfaces	ShareFileSetDisplayWnd
	ShareFileSetDisplaySize
	ShareFileOpen
	ShareFileGetFileInfo
	ShareFileClose
	ShareFileSave
	ShareFileSpecifiedPage
	ShareFilePreviousPage
	ShareFileNextPage
	ShareFileSwitch
	ShareFileZoomControl
	ShareFileMoveByHand
	ShareFileAutoMoveByHand

Event Changes

Table 2 New event list

Event Type	Change Content
Conference basic events	ConfNetworkQosNotifyEvent
Document sharing events	ShareFileLoadingProgressEvent
	ShareFileOpenEvent
	ShareFileCurrentPageEvent
	ShareFileCloseEvent

Table 3 Modified event list

Event Type	Event Name	Change Content
Conference basic events	JoinConfResultEvent	Added the confId parameter indicating the conference ID.
	MemberLeaveConfEvent	Added the confId parameter indicating the conference ID.
	TerminateConfResultEvent	Added the confId parameter indicating the conference ID.
Video events	VideoSwitchEvent	Added the isSelf parameter indicating whether the event is about yourself.

Document Content Changes

Table 4 Document content changes

Location	Mode	Change Content	Reason
Safety Notices	Add	Added the new chapter.	The new chapter is added.
Conference OCX Overview	Modify	Added the document sharing function.	A new function is added.
Development and Operating Environment Requirements	Modify	Deleted the precautions.	The development and operating environment needs to be optimized.
SendFile	Modify	Added a security note.	The description is optimized.
Public Return Codes	Modify	Added return codes 5011, 5050, 5051, 5052, 5053, 5054, 5055, 5056, 5057, 5058, 5059, 5060, 5061, and 5062.	Return codes are added.
Meeting Return Code	Add	Added return codes 1101 to 1141 of the conference.	Return codes are added.

Parent topic: [V200R001C80](#)

Overview

- [Conference OCX Overview](#)
- [Development and Operating Environment Requirements](#)

Parent topic: [Conference Interfaces \(ActiveX\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Conference OCX Overview

The Conference OCX is an MFC-based ActiveX control that provides multimedia collaboration capabilities. The Conference OCX provides the following functions:

1. Video conference
2. Desktop sharing
3. Remote assistance
4. Document sharing

Parent topic: [Overview](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Development and Operating Environment Requirements

Development Environment Requirements

Table 1 Development environment requirements

System Environment	Windows 7 32-bit
Environment Requirements	Microsoft Visual Studio 2010 The Conference OCX an MFC-based ActiveX control. Compatible with a wide range of development languages, the Conference OCX can be loaded in most programs. If the Conference OCX is integrated using C# or C++, it is recommended that you use the Visual Studio 2010.
Development Language	C++

Operating Environment Requirements

The following operating systems are supported:

- Windows 7 (32-bit/64-bit)
- Windows 8 (32-bit/64-bit)

The Windows RT operating system that is based on the ARM platform is not supported.

Parent topic: [Overview](#)

Data Type

The following table lists the data types involved in interface return values, input parameters, and event return information in this document:

Data Type	Type Name	Description
Character string	String	MBCS (multi-byte character set).
Short integer	SHORT	Two-byte integer.

Parent topic: [Conference Interfaces \(ActiveX\)](#)

Interface Description

[Structure](#)

[Conference Basic Interfaces](#)

[Video Interfaces](#)

[I/O Interfaces](#)

[Multimedia Collaboration Interfaces](#)

[Document Sharing Interfaces](#)

Parent topic: [Conference Interfaces \(ActiveX\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Structure

In this document, description about each interface function mainly consists of the following parts:

- Prerequisites
- Interface Description
- Interface Prototype
- Parameter Description
- Return Code
- Triggered Event
- Event Parameters

JSON character strings must be parsed before they are used to determine the invocation result of an interface or event. Full matching of JSON character strings may cause incompatibility between the new and earlier versions.

Prerequisites

Prerequisites refer to the conditions that a program must meet when invoking an interface.

Parameter Description

- **Data Type:** data type of a parameter.
- **In/out:** parameter input/output property.
 - **in:** indicates that the parameter is an input parameter.
 - **out:** indicates that the parameter is an output parameter.
 - **inout:** indicates that the parameter is both an input and output parameter.
- **M/O/C:** mandatory/optional/conditional.

NOTICE

Spaces before and after all input parameters except message parameters in the interface document are removed before the parameters are transferred.

Return Code

A return code refers to a code that is returned after an interface is invoked.

Triggered Event

A triggered event refers to an event that is received after an interface is invoked.

Event Parameters

Event parameters refer to triggered event parameters, transmitting event information.

Parent topic: [Interface Description](#)

Conference Basic Interfaces

[JoinConf](#)

[LeaveConf](#)

[TerminateConf](#)

[GetPresenter](#)

[LimitDataFlowSize](#)

[SetVideoCodec](#)

[SetLogLevel](#)

[SetLogSaveDays](#)

[GetResultDesc](#)

Parent topic: [Interface Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

JoinConf

Prerequisites

1. The Conference OCX has been successfully loaded and initialized.
2. You have not joined the conference.

Interface Description

This interface is for a user to join a multimedia conference.

Prototype

```
Short JoinConf (String sConfInfo)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sConfInfo	M	In	String	Conference information. Generally, the value is obtained from the JAU (ICS Gateway) or the WECC_MEETING_PREPARE_JOIN event in Agent OCX. This parameter is in the following format: ConfID=13107125 UserID=100054 UserType=2 HostKey=111 SiteID=6j1f1 SiteUrl=10.177.239.174:5062 MSServerIP=10.177.121.119 ConfPrivilege=111 ClusterType=3

Table 1 Conference information parameters

Parameter	Description and Value Range
ConfID	Conference ID. Value range: [11, 4294967295] In the CC scenario, the value of ConfID is an eight-digit random number generated by the security random number generator.
UserID	User ID. Value range: [1, 4294967295] In the CC scenario, the options are as follows: • Attendant: agent ID • User: user name for webmail login
UserType	User type. Value range: 1, 2, and 8 In the CC scenario, the options are as follows: • 2: conference initiator • 8: conference participant
HostKey	Conference chair password. This parameter is mandatory for a conference initiator and is left empty for a conference participant. In the CC scenario: The value is a 32-digit random number generated by a security random number generator.
SiteUrl	Authentication server address. This parameter is in <i>IP address:Port number</i> format. Example: 10.71.165.11:6688 . The variables in the format are as follows: • <i>IP address</i>: IP address of the local CCS • <i>Port</i>: listening port for initializing the authentication dynamic library
SiteID	ID of the central MS cluster server.
MSServerIP	List of conference server IP addresses and ports. Multiple IP addresses are separated by semicolons (;), for example, 10.71.105.66;10.71.105.67 .
ConfPrivilege	Conference password. This parameter must be set on both the user and agent sides; otherwise, users cannot join the conference. In the CC scenario: The value is a 16-digit random number that is generated by a security random number generator.
ClusterType	Cluster type. The options are as follows: • 0: authentication cluster, which is a cluster that contains an authentication server. There can be only one authentication cluster at a site. • 1: central cluster. There can be no or multiple central clusters at a site. If no cluster is matched, a central cluster or an authentication cluster is selected to serve clients. • 2: branch cluster. There can be no or multiple branch clusters at a site. A branch cluster can be a regional branch cluster or DMZ cluster in the distributed mode. • 3: SBC proxy cluster. There can be no or multiple SBC proxy clusters at a site. When the SBC proxy in the DMZ serves as an intranet MS, this parameter must be set to 3 for the SBC proxy.

Return Code

Return Code	Description
0	Indicates that the interface is successfully invoked.
5005	Indicates that you have joined the conference.
5006	Indicates that the parameter is incorrect.

Triggered Event

- [JoinConfResultEvent](#).
- [MemberEnterConfEvent](#). The number of times this event is received is equal to the number of users in a conference. For users who have joined the conference, this event is triggered each time a user joins the conference.

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Conference Basic Interfaces](#)

LeaveConf

Prerequisites

You have joined the conference.

Interface Description

This interface is for a user to leave a multimedia conference.

Interface Prototype

Short LeaveConf ()

Parameter Description

None

Return Code

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.

Triggered Event

[MemberLeaveConfEvent](#). All users in the conference receive this event.

Invoking Description

This interface is invoked in asynchronous mode.

 **NOTE**

When you use the control to develop the agent clients of the CTI call center, this interface and that of another control (such as iccctrol.ocx) need to be successively invoked to notify CTI agents of leaving the multimedia conference.

Parent topic: [Conference Basic Interfaces](#)

TerminateConf

Prerequisites

You have joined the conference.

Interface Description

This interface is used to end a multimedia conference.

Interface Prototype

Short TeminateConf()

Parameter Description

None

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.

Triggered Event

[TerminateConfResultEvent](#). All users in the conference receive this event.

Invoking Description

This interface is invoked in asynchronous mode.

 **NOTE**

When you use the control to develop agent clients of the CTI call center, this interface and that of another control (such as iccctrl.ocx) need to be successively invoked to notify the CTI platform of terminating the multimedia conference.

Parent topic: [Conference Basic Interfaces](#)

GetPresenter

Prerequisites

You have joined the conference successfully and received [JoinConfResultEvent](#).

Interface Description

This interface is used to obtain the presenter ID.

Interface Prototype

String GetPresenter(void)

Parameter Description

None

Return Value

Type	Result Type	Description
String	Normal	JSON character string. Example: <pre>{ "isSelf" : true, "resultCode" : 0, "resultDesc" : "success", "userId" : 100021 }</pre> Parameters that are displayed in the preceding example are described as follows: • userId: presenter ID. • isSelf: indicates whether the event is about yourself.
	Abnormal	If the query fails, the system returns a character string in the following format: <pre>{ "resultCode": error code, "resultDesc": "error code description" }</pre>

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Conference Basic Interfaces](#)

LimitDataFlowSize

Prerequisites

You have joined the conference.

Interface Description

This interface is used to restrict data traffic. It is applied to the current conference. It is used after you join the conference and before the video/data functions are enabled.

NOTICE

This interface can restrict only the upstream traffic but not the downstream traffic.

Interface Prototype

Short LimitDataFlowSize(sDataType, sLimitSize)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sDataType	M	In	String	Data type to be configured. VIDEO: video SCREEN: screen sharing DOC: document (file transfer) The value is case-insensitive.
sLimitSize	M	In	String	Peak bandwidth (unit: byte). Value range: [15360, 4294967295]

Return Code

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Conference Basic Interfaces](#)

SetVideoCodec

Prerequisites

The Conference OCX has been successfully loaded and initialized.

Interface Description

This interface is used to set the video codec mode. The codec mode is hardware encoding and software decoding by default.

NOTICE

Some CPU hardware decoding faults will cause green bars to be displayed on video images. In this case, use software decoding.

Interface Prototype

Short: SetVideoCodec(sEnCode, sDeCode)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sEnCode	M	In	String	Encoding. The value is case-insensitive. The options are as follows: soft: software encoding hard: hardware encoding
sDeCode	M	In	String	Decoding. The value is case-insensitive. The options are as follows: soft: software decoding hard: hardware decoding

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5006	Indicates that the parameter is incorrect.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Conference Basic Interfaces](#)

SetLogLevel

Prerequisites

The Conference OCX has been successfully loaded and initialized.

Interface Description

This interface is used to set the log level. The default level is debug.

Interface Prototype

Short SetLogLevel(sLogLevel)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sLogLevel	M	In	String	Log level. Value range: [0, 2147483647] 0: error 1: warning 2: info 3 or other numbers: debug

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5006	Indicates that the parameter is incorrect.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Conference Basic Interfaces](#)

SetLogSaveDays

Prerequisites

The Conference OCX has been successfully loaded and initialized.

Interface Description

This interface is used to set the log storage duration. Log files are stored for 30 days by default.

Interface Prototype

Short SetLogSaveDays(sDays)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sDays	M	In	String	Number of days for which log files are stored. Value range: [0, 365] The value 0 indicates log files are stored permanently.

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5006	Indicates that the parameter is incorrect.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Conference Basic Interfaces](#)

GetResultDesc

Prerequisites

The Conference OCX has been successfully loaded and initialized.

Interface Description

This interface is used to query the description about a return code.

Interface Prototype

```
String GetResultDesc(sResultCode)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sResultCode	M	In	String	Return code. Value range: [0, 2147483647]

Return Value

Type	Description
String	Description about the queried return code. If the description about the queried return code cannot be found, an empty string is returned.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Conference Basic Interfaces](#)

Video Interfaces

[GetLocalVideoDevices](#)

[OpenVideoDevice](#)

[CloseVideoDevice](#)

[StartDrawVideo](#)

[StopDrawVideo](#)

[PauseVideo](#)

[ResumeVideo](#)

[NotifyVideoCmd](#)

[GetSupportVideoParams](#)

[GetVideoCurrentParam](#)

[SetVideoCurrentParam](#)

[Snapshot](#)

Parent topic: [Interface Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

GetLocalVideoDevices

Prerequisites

The Conference OCX has been successfully loaded and initialized.

Interface Description

This interface is used to obtain information about all local devices that can be identified.

Interface Prototype

```
String GetLocalVideoDevices()
```

Parameter Description

N/A

Return Code

Type	Result Type	Description
String	Normal	JSON character string. Example: <pre>{ "deviceCount" : 1, "devicesInfo" : [{ "deviceId" : 2044781860, "name" : "e2eCap Video Capture" }], "resultCode" : 0, "resultDesc" : "success" }</pre> Parameters that are displayed in the preceding example are described as follows: deviceCount: number of devices devicesInfo: device list (array) deviceId: device ID name: device name
	Abnormal	If the query fails, the system returns a character string in the following format: <pre>{ "resultCode": error code, "resultDesc": "error description" }</pre>

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Video Interfaces](#)

OpenVideoDevice

Prerequisites

- 1. You have joined the conference.
- 2. The video device with the specified ID has not been turned on.

Interface Description

This interface is used to turn on a video device.

Interface Prototype

Short OpenVideoDevice(sDeviceId)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sDeviceId	M	In	String	Device ID. The value is obtained from the GetLocalVideoDevices interface. Value range: [0, 4294967295]

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

[VideoSwitchEvent](#). All users in the conference receive this event.

Invoking Description

This interface is invoked in asynchronous mode. Whether the video device is successfully turned on is determined by the VideoSwitchEvent event.

Parent topic: [Video Interfaces](#)

CloseVideoDevice

Prerequisites

- 1. You have joined the conference.
- 2. The video device with the specified ID has been turned on.

Interface Description

This interface is used to turn off a video device.

Interface Prototype

```
Short CloseVideoDevice(sDeviceId)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sDeviceId	M	In	String	ID of the device to be turned off. Value range: [0, 4294967295]

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

[VideoSwitchEvent](#). All users in the conference receive this event.

Invoking Description

This interface is invoked in asynchronous mode. Whether the video device is successfully turned off is determined by the VideoSwitchEvent event.

Parent topic: [Video Interfaces](#)

StartDrawVideo

Prerequisites

1. You have joined the conference.
2. A window to display video has been properly created.
3. The video device with the specified ID has been turned on.
4. Video streams of the specified device ID have not been rendered to the specified window.

Interface Description

This interface is used to render a video feed to a window. When a user opens video and wants to draw the video on a window, the user can use this interface.

Interface Prototype

```
Short StartDrawVideo(sUserId, sDeviceId, sHwnd, sShowMode)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sUserId	M	In	String	ID of the user to whom the video to render belongs. The value is generally obtained from the VideoSwitchEvent event. Value range: [1, 4294967295]
sDeviceId	M	In	String	ID of the specified video device. The value is generally obtained from the VideoSwitchEvent event. Value range: [0, 4294967295]
sHwnd	M	In	String	Window handle for displaying the video. The application layer creates the window, and then the window obtains the handle, which is a numeric string. Value range: [-2147483648, 2147483647]
sShowMode	M	In	String	Displaying mode. The options are as follows: • 0: indicates that the video is displayed in full window mode. • 1: indicates that the video is displayed in the original ratio. Parts that are not covered by video images are filled with black bars. • 2: indicates that the video is cropped to match the window size. • 3: indicates that the video is displayed according to the display area movement.

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
5007	Indicates an invalid window handle.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Video Interfaces](#)

StopDrawVideo

Prerequisites

- 1. You have joined the conference.
- 2. The video device with the specified ID has been turned on.
- 3. Video streams of the specified device ID have been rendered to the specified window.

Interface Description

This interface is used to stop rendering a video feed to a window.

Interface Prototype

```
Short StopDrawVideo(sUserId, sDeviceId, sHWnd)
```

Parameter Description

Parameter	M/O	In/out	Type	Description
sUserId	M	In	String	ID of the user to whom the video to be stopped from being rendered belongs. Value range: [1, 4294967295]
sDeviceId	M	In	String	ID of the specified video device. Value range: [0, 4294967295]
sHWnd	M	In	String	Window handle for rendering the video. The application layer creates the window, and then the window obtains the handle, which is a numeric string. Value range: [-2147483648, 2147483647]

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Video Interfaces](#)

PauseVideo

Prerequisites

1. You have joined the conference.
2. The video device with the specified ID has been turned on.
3. The video device with the specified ID is not paused.

Interface Description

This interface is used to pause your own video or other users' video.

- If you pause your own video, the system temporarily stops the collection function of the specified video device.
- If you pause the video of another user, the system stops receiving the video data from the specified device.

Interface Prototype

```
Short PauseVideo(sUserId, sDeviceId)
```

Parameter Description

Parameter	M/O	In/out	Type	Description
sUserId	M	In	String	ID of the user to whom the video to be paused belongs. Value range: [1, 4294967295]
sDeviceId	M	In	String	ID of the specified video device. Value range: [0, 4294967295]

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

[VideoSwitchEvent](#).

- When you pause your own video, every participant in the conference receives this event. The other participants receive two VideoSwitchEvent events.
- When you pause another participant's video, the event is not received.

Invoking Description

This interface is invoked in asynchronous mode. Whether the video is successfully paused is determined by the **VideoSwitchEvent** event.

Parent topic: [Video Interfaces](#)

ResumeVideo

Prerequisites

- 1. You have joined the conference.
- 2. The video device with the specified ID has been turned on.
- 3. The video device with the specified ID has been paused.

Interface Description

This interface is used to resume playing your own video or other users' video.

Interface Prototype

Short ResumeVideo(sUserId, sDeviceId)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sUserId	M	In	String	ID of the user to whom the specified video device belongs. Value range: [1, 4294967295]
sDeviceId	M	In	String	ID of the specified video device. Value range: [0, 4294967295]

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

[VideoSwitchEvent](#).

- If you resume playing your own video, every participant in the conference receives this event.
- When you resume another participant's video, the event is not received.

Invoking Description

This interface is invoked in asynchronous mode. Whether the video playback is successfully resumed is determined by the VideoSwitchEvent event.

Parent topic: [Video Interfaces](#)

NotifyVideoCmd

Prerequisites

You have joined the conference.

Interface Description

This interface is used to instruct other participants to turn on or to turn off video devices.

Interface Prototype

```
Short NotifyVideoCmd(sNotifyCmd, sUserId, sVideoParam)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sNotifyCmd	M	In	String	Instruction name. The value is case-insensitive. The options are as follows: • open: Turn on the video devices. • close: Turn off the video devices.
sUserId	M	In	String	ID of the user who receives the instruction. Value range: [1, 4294967295]
sVideoParam	M	In	String	Video parameters. This parameter is a JSON character string. <pre>{ "deviceId": 100082, "X": 320, "Y": 240, "frameRate": 30 }</pre> Parameters that are displayed in the preceding example are described as follows: • deviceId: video device ID Value range: [0, 4294967295] • X: horizontal resolution Value range: [0, 4294967295] • Y: vertical resolution Value range: [0, 4294967295] • frameRate: frame rate Value range: [0, 4294967295] NOTICE: Specifications configured in this parameter must be supported by the video devices.

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

The user specified by **sUserId** receives the [ConfVideoNotifyEvent](#) event.

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Video Interfaces](#)

GetSupportVideoParams

Prerequisites

The Conference OCX has been successfully loaded and initialized.

Interface Description

This interface is used to obtain the list of supported video parameters.

Interface Prototype

String GetSupportVideoParams(sDeviceId)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sDeviceId	M	In	String	ID of the device from which the video parameters are to be obtained. Value range: [0, 4294967295]

Return Value

Type	Result Type	Description
String	Normal	JSON character string. Example: <pre>{ "capabilityCount" : 1, "resultCode" : 0, "resultDesc": "success", "SupportVideoParam" : [{ "x" : 320, "y" : 240, "frameRate" : 30 }] }</pre> Parameters that are displayed in the preceding example are described as follows: capabilityCount: number of lists of supported video parameters SupportVideoParam: list of supported video parameters. This parameter is an array X: horizontal resolution Y: vertical resolution framRate: frame rate
	Abnormal	If the query fails, the system returns a character string in the following format: <pre>{ "resultCode": error code, "resultDesc": "error code description" }</pre>

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Video Interfaces](#)

GetVideoCurrentParam

Prerequisites

You have joined the conference.

Interface Description

This interface is used to obtain current video parameters of a specified device.

Interface Prototype

```
String GetVideoCurrentParam(sDeviceId)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sDeviceId	M	In	String	ID of the device from which the video parameters are to be obtained. Value range: [0, 4294967295]

Return Code

Type	Result Type	Description
String	Normal	JSON character string. Example: <pre>{ "x" : 320, "y" : 240, "frameRate" : 30, "resultCode" : 0, "resultDesc" : "success" }</pre> Parameters that are displayed in the preceding example are described as follows: • X: horizontal resolution • Y: vertical resolution • framRate: frame rate
	Abnormal	If the query fails, the system returns a character string in the following format: <pre>{ "resultCode": error code, "resultDesc": "error code description" }</pre>

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Video Interfaces](#)

SetVideoCurrentParam

Prerequisites

- 1. You have joined the conference.
- 2. The specified video device exists.

Interface Description

This interface is used to set current video parameters for a specified device.

Interface Prototype

Short SetVideoCurrentParam(sDeviceId, sVideoParam)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sDeviceId	M	In	String	ID of the device for which the video parameters are to be set. Value range: [0, 4294967295]
sVideoParam	M	In	String	Video parameters. <pre>{ "X" : 320, "Y" : 240, "frameRate" : 30 }</pre> Parameters that are displayed in the preceding example are described as follows: • X: horizontal resolution Value range: [0, 4294967295] • Y: vertical resolution Value range: [0, 4294967295] • frameRate: frame rate Value range: [0, 4294967295] NOTICE: Specifications configured in this parameter must be supported by the video devices.

Return Code

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Video Interfaces](#)

Snapshot

Prerequisites

- 1. You have joined the conference.
- 2. The specified video device exists.

Interface Description

This interface is used to take a snapshot.

Interface Prototype

Short Snapshot (sDeviceId, sFileName, sResolution)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sDeviceId	M	In	String	ID of the device to take the snapshot. Value range: [0, 4294967295]
sFileName	M	In	String	Absolute storage path of the taken snapshot. The file name extension can only be .png. Eg: "C:\cc\c.png "
sResolution	M	In	String	Snapshot resolution. The value is in the following format: { <i>"X":Horizontal resolution,"Y":Vertical resolution</i> } The value of X ranges from 0 to 1920 . The value of Y ranges from 0 to 1080 . Enter the resolution obtained from the GetSupportVideoParams interface. If the parameter is empty, the parameter value is 0 , or the entered resolution is not supported by the device, the system obtains the resolution that is supported by the device. Example: { <i>"X":1920,"Y":1080</i> }

Return Code

Return Code	Description
0	Indicates that the interface is successfully invoked.
5002	Indicates that no video device is detected.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
5061	Indicates insufficient disk space.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Video Interfaces](#)

I/O Interfaces

[SendMessage](#)

[SendFile](#)

[CancelSendingFile](#)

[ReceiveFile](#)

[CancelReceiveFile](#)

Parent topic: [Interface Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

SendMessage

Prerequisites

1. You have joined the conference.
2. The message to be sent cannot be empty, and the message size is less than or equal to 16 KB. If a message is to be sent to all participants, the message size must be less than 8 KB.

Interface Description

This interface is used to send messages.

Interface Prototype

```
Short SendMessage(sRecvUserId, sMessage, sMsgId)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sRecvUserId	M	In	String	Recipient ID. If the value is 0 , all participants except the sender will receive the message. Value range: [0, 4294967295]
sMessage	M	In	String	Message content. The content cannot be empty and the size is less than or equal to 16 KB. If a message is to be sent to all participants, the message size must be less than 8 KB.
sMsgId	M	In	String	Message ID. Value range: [0, 85]. This parameter can be used to classify messages.

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

[MessageArrivedEvent](#). This event is received by message recipients.

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [I/O Interfaces](#)

SendFile

Prerequisites

1. You have joined the conference.
2. The path of the file to be sent must be a local file path.
3. The size of the file to be sent cannot exceed 250 MB. The value cannot be 0.
4. The path of the file to be sent must meet the requirements of the current operating system.
5. On the Windows operating system, the length of a file path cannot exceed 245 bytes.
6. The maximum size of a file to be sent varies according to the network bandwidth. If the bandwidth is 2 Mbit/s, the size of files to be sent at a time cannot exceed 500 KB; otherwise, video will be frozen for a long time.

Interface Description

This interface is used to send a file.

NOTE

1. The interface does not restrict the formats of files to be sent and any files can be sent.
2. For security purposes, when using this interface, the application layer needs to customize a file format whitelist based on service requirements. Before invoking this interface, the application layer filters the file formats and restricts the transmission of executable files like EXE files.
3. If you need to restrict the formats of files to be transferred at the interface layer, contact engineers.

Interface Prototype

```
Short SendFile(sRecvUserId,sFileName)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sRecvUserId	M	In	String	Recipient ID. If the value is 0, all participants except the sender will receive the file. Value range: [0, 4294967295]
sFileName	M	In	String	Full path of the local file. Example: C:\\test\\c.txt

Return Code

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

1. [FileTranProgressEvent](#).
When the file size is small and the network is stable, the file is immediately sent. In this case, the sender will not receive the event.
2. [FileTranOverEvent](#).
3. [FileArrivedEvent](#). If the file is sent successfully, the recipient receives this event.

Invoking Description

This interface is invoked in asynchronous mode. Whether the file is successfully sent is determined by [FileTranOverEvent](#).

Parent topic: [I/O Interfaces](#)

CancelSendingFile

Prerequisites

A file is being sent.

Interface Description

This interface is used to cancel file sending. During file sending, you can use this interface to cancel file sending.

Interface Prototype

```
Short CancelSendingFile(sFileHandle)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sFileHandle	M	In	String	File handle. File handle returned by the FileTranProgressEvent event. Value range: [0, 4294967295]

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

[FileTranOverEvent](#). If the file sending is canceled successfully, the sender receives this event, which carries the corresponding error code information.

Invoking Description

This interface is invoked in asynchronous mode. Whether file sending is successfully canceled is determined by [FileTranOverEvent](#).

Parent topic: [I/O Interfaces](#)

ReceiveFile

Prerequisites

- 1. The FileArrivedEvent event has been received.
- 2. The path of the file to be received must meet the requirements of the current operating system.
- 3. The path of the file to be received must be a local file path.
- 4. On the Windows operating system, the length of a file path cannot exceed 245 bytes.
- 5. The space of the disk where the path is located is greater than or equal to 1 GB.

Interface Description

This interface is used to receive files.

Interface Prototype

```
Short ReceiveFile(sFileHandle, sFileAbsolutePath)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sFileHandle	M	In	String	File handle. File handle returned by the FileArrivedEvent event. Value range: [0, 4294967295]
sFileAbsolutePath	M	In	String	Full path of the local file. Example: C:\\test\\c.txt

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

- 1. [FileTranProgressEvent](#). When the file size is small and the network is stable, the file is immediately sent. In this case, the recipient will not receive the event.
- 2. [FileTranOverEvent](#).

Invoking Description

This interface is invoked in asynchronous mode. Whether the file is successfully received is determined by the message result code in [FileTranOverEvent](#).

Parent topic: [I/O Interfaces](#)

CancelReceiveFile

Prerequisites

A file is being received.

Interface Description

This interface is used to cancel file reception.

Interface Prototype

Short CancelReceiveFile(sFileHandle)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sFileHandle	M	In	String	File handle. File handle returned by the FileArrivedEvent event. Value range: [0, 4294967295]

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

1. [FileTranOverEvent](#).

Invoking Description

This interface is invoked in asynchronous mode. Whether file receiving is successfully canceled is determined by the result code in [FileTranOverEvent](#).

Parent topic: [I/O Interfaces](#)

Multimedia Collaboration Interfaces

[SetDisplayShareScreenWnd](#)

[GetApplicationList](#)

[AddApplicationToShare](#)

[DeleteSharedApplication](#)

[StartShareScreen](#)

[StopShareScreen](#)

[RequestOperationPrivilege](#)

[SetOperationPrivilege](#)

[SetShareScreenDisplaySize](#)

Parent topic: [Interface Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

SetDisplayShareScreenWnd

Prerequisites

- 1. The Conference OCX has been successfully loaded and initialized.
- 2. A window has been created.

Interface Description

This interface is used to set the window to be shared.

Interface Prototype

Short SetDisplayShareScreenWnd(sHWnd)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sHWnd	M	In	String	Window handle. Window handle generated by a third party. The value is a character string that consists of decimal digits. Value range: [-2147483648, 2147483647]

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5001	Indicates that the memory fails to be allocated. This return code is returned only when the memory is extremely insufficient.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
5007	Indicates an invalid window handle.
5008	Indicates that the system fails to set the window hook. The hook mechanism can apply to only one process, and the window and Conference OCX must be in the same process or application.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Multimedia Collaboration Interfaces](#)

GetApplicationList

Prerequisites

You have joined the conference.

Interface Description

This interface is used to obtain the list of applications that can be shared.

Interface Prototype

String GetApplicationList()

Parameter Description

None

Return Value

Type	Result Type	Description
String	Normal	<pre>{ "appInfoList" : [{ "hwnd" : 13503662, "sharing" : 0, "title" : "IPCC UserApp TestTool v1.0 - Windows Internet Explorer" }, { "hwnd" : 1454284, "sharing" : 0, "title" : "E:\\resipx4\\resipx4.log - Notepad++" }, { "hwnd" : 198510, "sharing" : 0, "title" : "Remote Desktop Organizer" }], "count" : 3, "resultCode" : 0, "resultDesc" : "success" }</pre> Parameters that are displayed in the preceding example are described as follows: count: number of applications appInfoList: JSON array of the application list hwnd: application window handle sharing: 1 indicates that the application is shared, and 0 indicates that the application is not shared title: application title
	Abnormal	If the query fails, the system returns a character string in the following format: <pre>{ "resultCode": error code, "resultDesc": "error code description" }</pre>

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Multimedia Collaboration Interfaces](#)

AddApplicationToShare

Prerequisites

Screen sharing has been enabled.

Interface Description

This interface is used to set the applications to be shared.

Interface Prototype

Short AddApplicationToShare(sHAppWnd)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sHAppWnd	M	In	String	Window handle of the application to be shared. The value is obtained from the return code of the getApplicationList interface. Value range: [-2147483648, 2147483647]

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
5007	Indicates an invalid window handle.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Multimedia Collaboration Interfaces](#)

DeleteSharedApplication

Prerequisites

The application to be deleted is in shareable mode.

Interface Description

This interface is used to delete an application that is in shareable mode.

Interface Prototype

Short DeleteSharedApplication(sHAppWnd)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sHAppWnd	M	In	String	Window handle of the application to be deleted. Value range: [-2147483648, 2147483647]

Return Code

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Multimedia Collaboration Interfaces](#)

StartShareScreen

Prerequisites

- 1. You have joined the conference.
- 2. Screen sharing has not been enabled.

Interface Description

This interface is used to enable screen (desktop or application) sharing.

NOTICE

1. If the user has already enabled screen sharing when the interface is invoked, only the success code is returned and no event is generated.

2. If another user in the conference has enabled screen sharing when the interface is invoked, screen sharing of the user is disabled and then screen sharing of the local user is enabled.

3. The screen sharing viewer may receive two ShareScreenWndSizeEvent events.

Interface Prototype

Short StartShareScreen(sShareType)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sShareType	M	In	String	Sharing type. The value is case-insensitive. The options are as follows: • desktop: desktop sharing • application: application sharing

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

- [StartShareScreenResultEvent](#). The sharer receives this event.
- [SharingOwnerNotifyEvent](#). All users in the conference receive this event.
- [ShareScreenStateNotifyEvent](#). All users in the conference receive this event.
- [ShareScreenWndSizeEvent](#). All users except the screen sharer receive this event.

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Multimedia Collaboration Interfaces](#)

StopShareScreen

Prerequisites

You are sharing the screen (desktop or application).

Interface Description

This interface is used to stop screen sharing.

Interface Prototype

Short StopShareScreen()

Parameter Description

None

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

- [SharingOwnerNotifyEvent](#). All users in the conference receive this event.
- [ShareScreenStateNotifyEvent](#). All users in the conference receive this event.

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Multimedia Collaboration Interfaces](#)

RequestOperationPrivilege

Prerequisites

The requester is viewing the screen of the requested party.

Interface Description

This interface is used to apply for remote operation rights. The viewer applies to the sharer for remote operation rights. Currently, only the remote assistance rights can be applied.

Interface Prototype

Short RequestOperationPrivilege(sPrivilegeType)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sPrivilegeType	M	In	String	Rights type. Currently, only the value RemoteCtl (remote assistance) is available. The value is case-insensitive.

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

[OperationPrivilegeRequestEvent](#). The requested party (screen sharer) receives this event.

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Multimedia Collaboration Interfaces](#)

SetOperationPrivilege

Prerequisites

The invoking party is sharing the screen.

Interface Description

This interface is used to configure operation rights. Operation rights can be assigned to or revoked from a viewer. In addition, a viewer's application for operation rights can be rejected.

Interface Prototype

```
Short SetOperationPrivilege(sUserId, sPrivilegeType, sAction)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sUserId	M	In	String	Target user ID. Value range: [1, 4294967295]
sPrivilegeType	M	In	String	Rights type. Currently, only the value RemoteCtl (remote assistance) is available. The value is case-insensitive.
sAction	M	In	String	Operation. The value is case-insensitive. • Add: Assign rights. • Delete: Revoke rights. • Reject: Reject the application.

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

[OperationPrivilegeStateEvent](#). All users in the conference receive this event.

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Multimedia Collaboration Interfaces](#)

SetShareScreenDisplaySize

Prerequisites

The Conference OCX has been successfully loaded and initialized.

Interface Description

This interface is used to set the window size for displaying the shared screen.

Interface Prototype

```
Short SetShareScreenDisplaySize(sWidth, sHeight)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sWidth	M	In	String	Window width for displaying the shared screen. Value range: [-2147483648, 2147483647]
sHeight	M	In	String	Window height for displaying the shared screen. Value range: [-2147483648, 2147483647]

Return Code

Return Code	Description
0	Indicates that the interface is successfully invoked.
5006	Indicates that the parameter is incorrect.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Multimedia Collaboration Interfaces](#)

Document Sharing Interfaces

[ShareFileSetDisplayWnd](#)
[ShareFileSetDisplaySize](#)
[ShareFileOpen](#)
[ShareFileGetFileInfo](#)
[ShareFileClose](#)
[ShareFileSave](#)
[ShareFileSpecifiedPage](#)
[ShareFilePreviousPage](#)
[ShareFileNextPage](#)
[ShareFileSwitch](#)
[ShareFileZoomControl](#)
[ShareFileMoveByHand](#)
[ShareFileAutoMoveByHand](#)

Parent topic: [Interface Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

ShareFileSetDisplayWnd

Prerequisites

- 1. The Conference OCX has been successfully loaded and initialized.
- 2. The window for sharing a document has been created.

Interface Description

This interface is used to set the window handle for the shared document.

Interface Prototype

Short ShareFileSetDisplayWnd(sHWnd)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sHWnd	M	In	String	Window handle generated by the third party. The value is a character string that consists of decimal digits. Value range: [-2147483648, 2147483647]

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5001	Indicates that the memory fails to be allocated. This return code is returned only when the memory is extremely insufficient.
5006	Indicates that the parameter is incorrect.
5007	Indicates an invalid window handle.
5008	Indicates that the system fails to set the window hook. The hook mechanism can apply to only one process, and the window and Conference OCX must be in the same process or application.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Document Sharing Interfaces](#)

ShareFileSetDisplaySize

Prerequisites

- 1. The Conference OCX has been successfully loaded and initialized.
- 2. A window has been created.
- 3. You have joined the conference.

Interface Description

This interface is used to set the size of the display area in the window for sharing a document.

Interface Prototype

```
Short ShareFileSetDisplaySize(sWidth, sHeight)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sWidth	M	In	String	Width of the display area in the window for sharing a document. Value range: [1, 2560]
sHeight	M	In	String	Height of the display area in the window for sharing a document. Value range: [1, 1600]

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
5007	Indicates that the window is invalid.
5050	Indicates that the window handle has not been set.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Document Sharing Interfaces](#)

ShareFileOpen

Prerequisites

1. The window handle for the shared document has been set.
2. The size of the display area in the window for sharing a document has been set.
3. Currently, no document to be shared is being opened.
4. Currently, 50 or fewer documents are shared.

Interface Description

This interface is used to open a shared document.

Interface Prototype

```
Short ShareFileOpen(sFileName)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sFileName	M	In	String	Absolute path of the document to be shared. Example: C:\cclc.doc

Return Code

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
5007	Indicates that the window is invalid.
5050	Indicates that the window handle has not been set.
5051	Indicates that the display area size has not been set.
5052	Indicates that the document does not exist.
5054	Indicates that a document is being opened.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

Event	Description	Description of the Recipient
ShareFileLoadingProgressEvent	Notification of the load progress of a shared document.	This event is triggered each time a page of the document is loaded. Recipient: user who shares the document
ShareFileOpenEvent	Result of opening a shared document.	This event is triggered when a document has been opened. Recipient: all people
ShareFileCurrentPageEvent	Notification of the current page number of a shared document.	This event is triggered when a document has been opened. Recipient: all people

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Document Sharing Interfaces](#)

ShareFileGetFileInfo

Prerequisites

- 1. A document has been shared.

Interface Description

This interface is used to obtain information about a shared document.

Interface Prototype

```
String ShareFileGetFileInfo(sFileId)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sFileId	M	In	String	ID of the shared document. The value can be obtained from events such as ShareFileOpenEvent.

Return Value

Return Code	Description
String	JSON character string. <pre>{ "zoomType": "zoom type", "pageHeight": "page height", "pageWidth": "page width", "fileName": "absolute path of the document", "pageCount": "total number of pages", "currentPageNo": "current page number", "ratio": "zoom ratio", "resultCode": "result code", "resultDesc": "result code description", }</pre> The options of zoomType are as follows: PageSize: Display pages in the original size. FitWidth: Set the page width equal to the display area width while keeping the width-height ratio fixed. DisplaySize: Set the page size to that in which the whole page can be just displayed in the display area. Percentage: Display pages based on the size percentage specified by the sRatio parameter.

Triggered Event

None

Invoking Description

This interface is invoked in synchronous mode.

Parent topic: [Document Sharing Interfaces](#)

ShareFileClose

Prerequisites

You have shared the document to be closed.

Interface Description

This interface is used to close a shared document.

Interface Prototype

Short ShareFileClose(sFileId)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sFileId	M	In	String	ID of the shared document. The value can be obtained from events such as ShareFileOpenEvent or be 0. When the value is 0, the Conference OCX closes the document that is being opened.

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
1137	Indicates that you do not have the rights.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
5053	Indicates that the document has not been opened.
5055	Indicates that no document is being opened.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

Event	Description	Description of the Recipient
ShareFileCloseEvent	Result of closing a shared document.	This event is triggered when a document is closed. Recipient: all people
ShareFileCurrentPageEvent	Notification of the current page number of a shared document.	This event is triggered when another document is also shared. Recipient: all people

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Document Sharing Interfaces](#)

ShareFileSave

Prerequisites

A shared document has been opened.

Interface Description

This interface is used to save a shared document to the local PC.

Interface Prototype

Short ShareFileSave (sFileId, sFileName)

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sFileId	M	In	String	Document ID that is obtained by parsing the ShareFileOpenEvent, ShareFileCurrentPageEvent, or ShareFileLoadingProgressEvent event.
sFileName	M	In	String	Absolute storage path of the document. The length of the document path cannot exceed 240 bytes. Example: C:\cc\test. The document is saved with the file name test.vtmd. It is automatically saved as a .vtmd file. Other formats are invalid.

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
5053	Indicates that the document has not been opened.
5061	Indicates insufficient disk space.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

None.

Invoking Description

This interface is invoked in synchronous mode.

At least 100 MB disk space is available.

Parent topic: [Document Sharing Interfaces](#)

ShareFileSpecifiedPage

Prerequisites

The specified page exists, and the document has been activated.

Interface Description

This interface is used to jump to a specified page in a shared document.

Interface Prototype

```
Short ShareFileSpecifiedPage (sFileId, sPageNo, sSync)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sFileId	M	In	String	Document ID that is obtained by parsing the ShareFileOpenEvent, ShareFileCurrentPageEvent, or ShareFileLoadingProgressEvent event.
sPageNo	M	In	String	Page number, which starts from 0. (The first page is page 0.)
sSync	M	In	String	Indicates whether to synchronize the document to other users' clients. The options are as follows: 0: no 1: yes

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
5053	Indicates that the document has not been opened.
5056	Indicates that the specified page does not exist or the document has no page.
5057	Indicates that the current document has not been activated.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

[ShareFileCurrentPageEvent](#). This event is triggered when the specified page has been jumped to. If the specified page is the current page, the event is not triggered. If the value of **sSync** is 0, only the user who turns pages receives this event. If the value of **sSync** is 1, all users receive this event.

Invoking Description

1. This interface is invoked in asynchronous mode.
2. Each page in the document being shared is uploaded from the local client to the server, and then is distributed to remote clients by the server. The currently activated page is uploaded first, and then all subsequent pages are uploaded in ascending order of the page number. After all subsequent pages are uploaded, if there are pages previous to the activated page that have not been uploaded, they are also uploaded in ascending order of the page number. Assume that a document with too many pages is being shared, and **sSync** is set to 0. When the sharer jumps to a page that has not been distributed, users to whom the document is shared fail to view the page while the sharer can view the page. When **sSync** is set to 1, it is recommended that the sharer jumps to a page that has been viewed.

Parent topic: [Document Sharing Interfaces](#)

ShareFilePreviousPage

Prerequisites

At least one page previous to the currently activated page exists.

Interface Description

This interface is used to turn to the previous page.

Interface Prototype

```
Short ShareFilePreviousPage (sFileId, sSync)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sFileId	M	In	String	Document ID that is obtained by parsing the ShareFileOpenEvent, ShareFileCurrentPageEvent, or ShareFileLoadingProgressEvent event.
sSync	M	In	String	Indicates whether to synchronize the document to other users' clients. The options are as follows: • 0: no • 1: yes

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
5053	Indicates that the document has not been opened.
5056	Indicates that the specified page does not exist or the document has no page.
5057	Indicates that the current document or page has not been activated.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

[ShareFileCurrentPageEvent](#). This event is triggered when the previous page has been turned to. If the value of **sSync** is **0**, only the user who turns pages receives this event. If the value of **sSync** is **1**, all users receive this event.

Invoking Description

1. This interface is invoked in asynchronous mode.
2. Each page in the document being shared is uploaded from the local client to the server, and then is distributed to remote clients by the server. The currently activated page is uploaded first, and then all subsequent pages are uploaded in ascending order of the page number. After all subsequent pages are uploaded, if there are pages previous to the activated page that have not been uploaded, they are also uploaded in ascending order of the page number. Assume that a document with too many pages is being shared, and **sSync** is set to **0**. When the sharer jumps to the previous page that has not been distributed, users to whom the document is shared fail to view the page while the sharer can view the page. When **sSync** is set to **0**, ensure that the previous page has been viewed before it is turned to.

Parent topic: [Document Sharing Interfaces](#)

ShareFileNextPage

Prerequisites

At least one page subsequent to the currently activated page exists.

Interface Description

This interface is used to turn to the next page.

Interface Prototype

```
Short ShareFileNextPage (sFileId, sSync)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sFileId	M	In	String	Document ID that is obtained by parsing the ShareFileOpenEvent, ShareFileCurrentPageEvent, or ShareFileLoadingProgressEvent event.
sSync	M	In	String	Indicates whether to synchronize the document to other users' clients. The options are as follows: • 0: no • 1: yes

Return Code

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
5053	Indicates that the document has not been opened.
5056	Indicates that the specified page does not exist or the document has no page.
5057	Indicates that the current document or page has not been activated.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

[ShareFileCurrentPageEvent](#). This event is triggered when the next page has been turned to. If the value of **sSync** is **0**, only the user who turns pages receives this event. If the value of **sSync** is **1**, all users receive this event.

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Document Sharing Interfaces](#)

ShareFileSwitch

Prerequisites

Shared documents are opened.

Interface Description

This interface is used to switch to another shared document.

Interface Prototype

```
Short ShareFileSwitch(sFileId, sSync)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sFileId	M	In	String	ID of the shared document. The value can be obtained from events such as ShareFileOpenEvent.
sSync	M	In	String	Indicates whether to synchronize the document to other users' clients. The options are as follows: • 0: no • 1: yes

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
5053	Indicates that the document has not been opened.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

[ShareFileCurrentPageEvent](#). This event is not triggered when the document to be switched to is the currently activated document. If the value of **sSync** is **0**, only the user who turns pages receives this event. If the value of **sSync** is **1**, all users receive this event.

Invoking Description

This interface is invoked in asynchronous mode.

Parent topic: [Document Sharing Interfaces](#)

ShareFileZoomControl

Prerequisites

A document has been shared.

Interface Description

This interface is used to zoom in/out document pages.

Interface Prototype

```
Short ShareFileZoomControl (sFileId, sZoomType, sRatio, sSync)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sFileId	M	In	String	ID of the shared document. The value can be obtained from events such as ShareFileOpenEvent.
sZoomType	M	In	String	Zoom type. The options are as follows: PageSize : Display pages in the original size. FitWidth : Set the page width equal to the display area width while keeping the width-height ratio fixed. DisplaySize : Set the page size to that in which the whole page can be just displayed in the display area. Percentage : Display pages based on the size percentage specified by the sRatio parameter.
sRatio	M	In	String	Zoom ratio. The value is an integral character string that is greater than 0 . Value range: (0, 65535]. The value is valid only when the value of SZoomType is Percentage .
sSync	M	In	String	Indicates whether to synchronize the document to other users' clients. The default value is 0 . The options are as follows: 0: no 1: yes

Return Code

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
5053	Indicates that the document has not been opened.
5057	Indicates that the current document or page has not been activated.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

None

Invoking Description

1. This interface is invoked in synchronous mode.
2. If the document is not in activated state on both local and remote clients, the operation is not synchronized even when **sSync** is set to **1**.

Parent topic: [Document Sharing Interfaces](#)

ShareFileMoveByHand

Prerequisites

A document has been shared.

Interface Description

This interface is used to drag a page in a document.

Interface Prototype

```
Short ShareFileMoveByHand (sFileId, sOperation, sPointX, sPointY, sSync)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sFileId	M	In	String	ID of the shared document. The value can be obtained from events such as ShareFileOpenEvent.
sOperation	M	In	String	Operation type. The options are as follows: Begin : Start dragging. Move : Drag the page. End : Stop dragging.
sPointX	M	In	String	X coordinate of the mouse pointer when the upper left corner of the display area is the coordinate origin. The parameter is valid only when the value of sOperation is Begin or Move . Value range: (0, 2560]
sPointY	M	In	String	Y coordinate of the mouse pointer when the upper left corner of the display area is the coordinate origin. The parameter is valid only when the value of sOperation is Begin or Move . Value range: (0, 2560]
sSync	M	In	String	Indicates whether to synchronize the document to other users' clients. The options are as follows: • 0: no • 1: yes

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
5053	Indicates that the document has not been opened.
5057	Indicates that the current document or page has not been activated.
5058	Indicates that the drag distance exceeds the valid range.
5062	Indicates that the status is incorrect.
Others	Indicates the error code that is returned from the TUP Meeting library.

Triggered Event

None

Invoking Description

1. This interface is invoked in synchronous mode.
2. If the document is not in activated state on both local and remote clients, the operation is not synchronized even when **sSync** is set to **1**.

Parent topic: [Document Sharing Interfaces](#)

ShareFileAutoMoveByHand

Prerequisites

A document is shared.

Interface Description

This interface is used to enable/disable automatic dragging.

Interface Prototype

```
Short ShareFileAutoMoveByHand (sEnableAutoMove, sSync)
```

Parameter Description

Parameter	M/O	In/out	Data Type	Description
sEnableAutoMove	M	In	String	Indicates whether to enable automatic dragging. The options are as follows: 1 : yes 0 : no
sSync	M	In	String	Indicates whether to synchronize the document to other users' clients. The options are as follows: 0: no 1: yes

Return Value

Return Code	Description
0	Indicates that the interface is successfully invoked.
5004	Indicates that you have not joined the conference.
5006	Indicates that the parameter is incorrect.
5060	Indicates that no document is being shared.

Triggered Event

None

Invoking Description

1. This interface is invoked in synchronous mode.
2. If the document is not in activated state on both local and remote clients, the operation is not synchronized even when **sSync** is set to **1**.

Parent topic: [Document Sharing Interfaces](#)

Event Description

This chapter describes events triggered by all interfaces in detail.

[Conference Basic Events](#)

[Video Events](#)

[I/O Events](#)

[Multimedia Collaboration Events](#)

[Document Sharing Events](#)

Parent topic: [Conference Interfaces \(ActiveX\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Conference Basic Events

[ConflnitResultEvent](#)

[JoinConfResultEvent](#)

[MemberEnterConfEvent](#)

[MemberLeaveConfEvent](#)

[TerminateConfResultEvent](#)

[ConfNetWorkDisconnectedEvent](#)

[ConfNetWorkReconnectedEvent](#)

[LoadComponentFailedEvent](#)

[ConfNetWorkStatusEvent](#)

[ConfRemainingTimeEvent](#)

[ConfNetworkQosNotifyEvent](#)

Parent topic: [Event Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

ConflnitResultEvent

Event Description

Result of initializing the Conference OCX.

Parameter Description

Data Type	Parameter Description
String	<pre>{ "resultCode": "result code. When the result code is 0, the initialization is successful. When the result code is not 0, the initialization fails.", "resultDesc": "result code description" }</pre>

Triggering Condition

This event is triggered after the Conference OCX control is loaded.

Parent topic: [Conference Basic Events](#)

JoinConfResultEvent

Event Description

Result of joining a conference. The return code of this event is used to determine whether a user successfully joins a conference.

If the return code indicates a success, indicating that the current TUP video, file, and multimedia components have been loaded, the video, file, and multimedia collaboration interfaces can be invoked.

Parameter Description

Data Type	Description
String	<pre>{ "confId": "conference ID", "resultCode": "result code. When the result code is 0, the user successfully joins the conference. When the result code is not 0, the user fails to join a conference." "resultDesc": "result code description" }</pre>

Triggering Condition

- The [JoinConf](#) interface is invoked successfully, but the user fails to join the conference.
- The user successfully joins the conference.

Parent topic: [Conference Basic Events](#)

MemberEnterConfEvent

Event Description

Notification returned when a user joins a conference. When a user joins the conference, the number of times this event is received for existing and new participants is different.

- For an existing participant, this event is triggered once each time a user joins the conference.
- For a new participant, this event is triggered multiple times to introduce conference participants. The number of times this event is received by a new participant is the same as the number of all participants including the new participant in the conference.

Parameter Description

Data Type	Description
String	<pre>{ "isSelf" : true, "userFlag" : 1, "userId" : "100052" }</pre> Parameters that are displayed in the preceding example are described as follows: • userId: user ID. • userFlag: user flag. (0: existing participant; 1: new participant) • isSelf: indicates whether the event is about yourself.

Triggering Condition

This event is triggered when a new participant successfully joins the conference. The new participant receives the MemberEnterConfEvent event of himself or herself joining the conference and also the MemberEnterConfEvent events of other participants. The number of times this event is received is the same as the number of all participants including the new participant in the conference. Existing participants and the new participant are differentiated by the value of **userFlag**. For an existing participant, this event is triggered each time a user joins the conference.

Parent topic: [Conference Basic Events](#)

MemberLeaveConfEvent

Event Description

Notification of leaving a conference. All participants in a conference receive this event of a leaving user.

Parameter Description

Data Type	Description
String	<pre>{ "confId": "conference ID", "isSelf" : true, "userId" : 100052 }</pre> Parameters that are displayed in the preceding example are described as follows: • userId: user ID. • isSelf: indicates whether the event is about yourself.

Triggering Condition

This event is triggered when a conference participant proactively leaves a conference or is disconnected from the conference because of network exceptions.

Parent topic: [Conference Basic Events](#)

TerminateConfResultEvent

Event Description

Result of ending a conference. All participants in a conference receive this event of an ended conference.

Parameter Description

Data Type	Description
String	<pre>{ "confId": "conference ID", "resultCode": "result code. When the result code is 0, the conference is ended successfully. When the result code is not 0, the conference fails to be ended." "resultDesc": "result code description" }</pre>

Triggering Condition

This event is triggered when a conference is ended.

Parent topic: [Conference Basic Events](#)

ConfNetWorkDisconnectedEvent

Event Description

Notification of network disconnection.

Parameter Description

None

Triggering Condition

The network between the Conference OCX and conference server is abnormal. This event is triggered when the network does not recover in a specified period.

Parent topic: [Conference Basic Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

ConfNetWorkReconnectedEvent

Description

Notification of network reconnection.

Parameter Description

None

Triggering Condition

This event is triggered when the network between the Conference OCX and the conference server recovers after disconnection.

Parent topic: [Conference Basic Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

LoadComponentFailedEvent

Event Description

Notification of a module loading failure.

Parameter Description

Data Type	Description
String	<pre>{ "component": "component module ID", "resultCode": "result code", "resultDesc": "result code description" }</pre>

Triggering Condition

This event is triggered when a user successfully joins a conference but does not have the necessary component library.

Parent topic: [Conference Basic Events](#)

ConfNetWorkStatusEvent

Event Description

Notification of network status.

Parameter Description

Data Type	Description
String	{ "status": "network status. 1: extremely bad; 2: bad" }

Triggering Condition

This event is triggered when a user successfully joins a conference, but the network status is unfavorable.

Parent topic: [Conference Basic Events](#)

ConfRemainingTimeEvent

Event Description

Notification of remaining time of a conference.

Parameter Description

Data Type	Description
String	{ "time": "conference remaining time, in seconds" }

Triggering Condition

This event is triggered when the remaining time of a conference is insufficient.

Parent topic: [Conference Basic Events](#)

ConfNetworkQosNotifyEvent

Event Description

Notification of network quality of service (QoS) monitoring for a multimedia conference.

Parameter Description

Data Type	Description
String	<pre>{ "tcp_jitter": "network jitter", "tcp_latency": "round-trip delay time", "tcp_send_delay": "TCP sending delay time", "tcp_send_rate": "TCP sending speed" }</pre>

Triggering Condition

This event is triggered every 10 seconds when you join a conference.

Parent topic: [Conference Basic Events](#)

Video Events

[VideoSwitchEvent](#)

[ConfVideoDisconnectedEvent](#)

[ConfVideoReconnectedEvent](#)

[ConfVideoNotifyEvent](#)

[ConfVideoFlowWarningEvent](#)

Parent topic: [Event Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

VideoSwitchEvent

Description

Notification of changes of video device status. This event is triggered when the status of a video device of a user changes.

Parameter Description

Data Type	Description
String	<pre>{ "isSelf": "true", "userId": "conference user ID", "deviceId": "device ID", "status": "status" }</pre> isSelf: indicates whether the event is about yourself. The options for the status parameter are as follows • 0: turned off. • 1: turned on. • 2: resumed (turned on). • 4: paused.

Triggering Condition

This event is triggered when you turn on, turn off, pause, or resume the video.

NOTICE

When you pause a video, the other participants receive two VideoSwitchEvent events.

Parent topic: [Video Events](#)

ConfVideoDisconnectedEvent

Event Description

Notification of video device disconnection.

Parameter Description

None

Triggering Condition

This event is triggered when the network is disconnected or the MS restarts.

Parent topic: [Video Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

ConfVideoReconnectedEvent

Event Description

Video reconnection event.

Parameter Description

None

Triggering Condition

This event is triggered when a conference resumes after the network disconnection or video device disconnection due to MS restarting.

Parent topic: [Video Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

ConfVideoNotifyEvent

Event Description

Notification of video-related instructions.

Parameter Description

Data Type	Description
String	<pre>{ "senderId": "ID of the user who sends the instruction", "receiverId": "ID of the user who receives the instruction", "deviceId": "video device ID", "frameRate": "frame rate", "x": "horizontal resolution", "y": "vertical resolution", "action": "operations to be performed on the video device" }</pre>

Triggering Condition

This event is triggered when you receive the request from another participant to turn on or turn off a camera.

Parent topic: [Video Events](#)

ConfVideoFlowWarningEvent

Event Description

Alarm of controlling video streams.

Parameter Description

Data Type	Description
String	<pre>{ "userId": "user ID", "deviceId": "user device ID" }</pre>

Triggering Condition

This event is triggered when the bandwidth is the minimum for videos but you still attempt to perform further video traffic control.

Parent topic: [Video Events](#)

I/O Events

- [MessageArrivedEvent](#)
- [FileTranProgressEvent](#)
- [FileTranOverEvent](#)
- [FileArrivedEvent](#)

Parent topic: [Event Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

MessageArrivedEvent

Event Description

Notification of message arrival.

Parameter Description

Data Type	Description
String	<pre>{ "data" : "hello world.", "dataLen" : 12, "msgId" : 0, "senderId" : 100052 }</pre> Parameters that are displayed in the preceding example are described as follows: • senderId: sender ID. • data: message content. • dataLen: message length. • msgId: message ID. The value ranges from 0 to 85. This parameter can be used to classify messages.

Triggering Condition

This event is triggered when a message arrives.

Parent topic: [I/O Events](#)

FileTranProgressEvent

Event Description

Notification of file transfer progress.

Parameter Description

Data Type	Description
String	<pre>{ "fileHandle": "file ID ", "fileName": "file name", "fileProgress": "transfer progress", "fileSize": "file size (unit: byte)", "fileStatus": "transfer status. 1: being received; 3: being sent", "resultCode" : "0", "resultDesc" : "success", "senderId": "sender ID" }</pre>

Triggering Condition

If the file being sent or received is large and cannot be transferred immediately, this event is triggered to display the transfer progress.

Parent topic: [I/O Events](#)

FileTranOverEvent

Event Description

Notification of file transfer completion. This event indicates the end of sending or receiving a file. The result code of the event determines whether the file is successfully transferred.

Parameter Description

Data Type	Description
String	<pre>{ "fileHandle": "file ID", "fileName": "file name", "senderId": "sender ID", "fileSize": "file size (unit: byte)", "fileStatus": "transfer status. 1: being received; 3: being sent", "resultCode": "result code", "resultDesc": "result code description" }</pre>

Triggering Condition

- File sending or reception ends.
- File sending or reception is canceled.
- An exception, such as sending timeout and network exception, occurs during file sending or reception.

Parent topic: [I/O Events](#)

FileArrivedEvent

Event Description

Notification of file arrival.

Parameter Description

Data Type	Description
String	<pre>{ "fileHandle": "file ID", "fileName": "file name", "senderId": "sender ID ", "fileSize": "file size (unit: byte)", "fileStatus": "transfer status. 1: being received; 3: being sent", "resultCode": "result code", "resultDesc": "result code description" }</pre>

Triggering Condition

This event is triggered when a file is sent and waits to be received.

Parent topic: [I/O Events](#)

Multimedia Collaboration Events

[StartShareScreenResultEvent](#)

[SharingOwnerNotifyEvent](#)

[ShareScreenStateNotifyEvent](#)

[OperationPrivilegeRequestEvent](#)

[OperationPrivilegeStateEvent](#)

[ShareScreenWndSizeEvent](#)

Parent topic: [Event Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

StartShareScreenResultEvent

Event Description

Result of enabling screen sharing.

Parameter Description

Data Type	Description
String	{ "resultCode": "result code", "resultDesc": "result code description" }

Triggering Condition

- Screen sharing is successfully enabled.
- This event is triggered when the interface is successfully invoked, but screen sharing fails because of a network exception.

Parent topic: [Multimedia Collaboration Events](#)

SharingOwnerNotifyEvent

Event Description

Notification of the user with sharing rights. This event notifies participants of the user who owns the sharing rights.

Parameter Description

Data Type	Description
String	{ "action": "add: Add a user with sharing rights; delete: Delete the user with sharing rights", "userId" : 100878 }

NOTICE

A conference can have only one user who has sharing rights.

Triggering Condition

When a screen sharer has obtained or lost the sharing rights, Other participants receive this event.

Parent topic: [Multimedia Collaboration Events](#)

ShareScreenStateNotifyEvent

Event Description

Notification of the screen sharing status.

Parameter Description

Data Type	Description
String	{ "state": "sharing status. Start : sharing started; Stop : sharing ended", "shareType": "sharing type. Desktop : desktop sharing; Application : application sharing" }

Triggering Condition

- When the screen sharer successfully shares the screen, all participants receive this event, indicating that the screen sharing starts.
- When screen sharing is ended either by the sharer or caused by an exception, all participants receive this event, indicating that the screen sharing ends.

Parent topic: [Multimedia Collaboration Events](#)

OperationPrivilegeRequestEvent

Event Description

Notification of an application for remote control rights.

Parameter Description

Data Type	Description
String	{ "userId": "applicant ID", "privilegeType": "type of the rights to be applied for. Currently, only the value RemoteCtl (remote assistance) is available." }

Triggering Condition

This event is triggered when a participant requests the remote control rights from the screen sharer.

Parent topic: [Multimedia Collaboration Events](#)

OperationPrivilegeStateEvent

Event Description

Notification of changing a user's operation rights.

Parameter Description

Data Type	Description
String	{ "userId": "ID of a user whose operation rights are to be changed", "action": "change operation. Add : Grant rights; Delete : Revoke rights; Reject : Reject the application." "privilegeType": "rights type. Currently, only the value RemoteCtl (remote assistance) is available." }

Triggering Condition

All participants receive this event when the screen sharer successfully invokes the [SetOperationPrivilege](#) interface.

NOTICE

When the application is rejected, only the applicant receives the event. The **userId** parameter indicates the ID of the user who rejects the application but not the applicant ID.

Parent topic: [Multimedia Collaboration Events](#)

ShareScreenWndSizeEvent

Event Description

Notification of the size of the shared screen.

Parameter Description

Data Type	Description
String	{ "x": "horizontal resolution of the shared screen", "y": "vertical resolution of the shared screen" }

Triggering Condition

All participants receive this event when the screen sharer successfully shares the screen. This event notifies them of the size of the shared screen.

Parent topic: [Multimedia Collaboration Events](#)

Document Sharing Events

- [ShareFileLoadingProgressEvent](#)
- [ShareFileOpenEvent](#)
- [ShareFileCurrentPageEvent](#)
- [ShareFileCloseEvent](#)

Parent topic: [Event Description](#)

Copyright © Chengdu TD-Tech Co., Ltd.

ShareFileLoadingProgressEvent

Event Description

Notification of the load progress of a shared document.

Parameter Description

Data Type	Description
String	<pre>{ "fileId": "ID of the document to be shared", "LoadedPageCount": "number of loaded pages", "resultCode": "result code", 0: succeed; Other values: failure "resultDesc": "result code description" }</pre>

Triggering Condition

This event is triggered when a user invokes the [ShareFileOpen](#) interface to open a document being shared.

Parent topic: [Document Sharing Events](#)

ShareFileOpenEvent

Event Description

Result of opening a shared document.

Parameter Description

Data Type	Description
String	<pre>{ "fileId": "ID of the document to be shared", "owner": "owner of the shared document", self: yourself, other: other users "fileName": "name of the document" "resultCode": "result code", 0: succeed; Other values: failure "resultDesc": "result code description" }</pre>

Triggering Condition

When the [ShareFileOpen](#) is invoked, both the sharer and sharee receive this event.

Parent topic: [Document Sharing Events](#)

ShareFileCurrentPageEvent

Event Description

Notification of the current activated page number of a shared document.

Parameter Description

Data Type	Description
String	<pre>{ "fileId": "ID of the document to be shared", "currentPageNo": "current activated page number", The value is counted from 0. "pageCount": "total number of pages" "resultCode": "result code", 0: succeed; Other values: failure "resultDesc": "result code description" }</pre>

Triggering Condition

This event is triggered when one of the following situations occurs:

- The document sharer switches the document, turns to the previous or next page, or jumps to a specified page in the document.
 - If the operation is asynchronous, only the operator receives this event.
 - If the operation is synchronous, all users receive this event.
- When the [ShareFileOpen](#) interface is invoked, the system automatically switches to the document opened this time. Both the sharer and sharee receive this event.
- When the [ShareFileClose](#) interface is invoked to close the shared document, the system automatically switches to another document that is still open. Both the sharer and sharee receive this event.

Parent topic: [Document Sharing Events](#)

ShareFileCloseEvent

Description

Result of closing a shared document.

Parameter Description

Type	Description
String	{ "fileId" : "ID of the document being shared" , "resultCode" : "result code",0: succeed, others: fail, "resultDesc" : "result code description" }

Triggering Condition

When the user who shares a document invokes the ShareFileClose interface to close the document, all users receive this event when the document is successfully closed. If the document fails to be closed, only the user who closes the file receives this event.

Parent topic: [Document Sharing Events](#)

Return Code

This chapter describes return codes of the Conference OCX in detail.

[Public Return Codes](#)

[Meeting Return Code](#)

Parent topic: [Conference Interfaces \(ActiveX\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Public Return Codes

Return Code	Description	Remarks
0	Indicates that the interface is successfully invoked.	N/A
5000	Indicates a minor error.	N/A
5001	Indicates that the memory fails to be allocated.	This return code is returned only when the memory is extremely insufficient.
5002	Indicates that no video device is detected.	N/A
5003	Indicates that the parameter is not supported.	N/A
5004	Indicates that you have not joined the conference.	N/A
5005	Indicates that you have joined the conference.	N/A
5006	Indicates that the parameter is incorrect.	N/A
5007	Indicates that the window is invalid.	N/A
5008	Indicates that the system fails to set the window hook.	N/A
5009	Indicates that the file transfer or reception is canceled.	N/A
5010	Indicates that no moderator is detected.	N/A
5011	Indicates a timeout.	N/A
5050	Indicates that the window handle has not been set.	N/A
5051	Indicates that the display area size has not been set.	N/A
5052	Indicates that the document does not exist.	N/A
5053	Indicates that the document has not been opened.	N/A
5054	Indicates that a document is being opened.	N/A
5055	Indicates that no document is being opened.	N/A
5056	Indicates that the specified page does not exist or the document has no page.	N/A
5057	Indicates that the current document or page has not been activated.	N/A
5058	Indicates that the drag distance exceeds the valid range.	N/A
5059	Indicates that the number of shared documents that are opened exceeds the limit.	N/A
5060	Indicates that no document is being shared.	—
5061	Indicates insufficient disk space.	N/A
5062	Indicates that the status is incorrect.	
5499	Indicates an unknown error.	N/A

Parent topic: [Return Code](#)

Meeting Return Code

Return Code	Description	Remarks
1	Indicates the warning.	N/A
2	Indicates the error.	N/A
3	Indicates the failure.	N/A
4	Indicates the empty pointer.	If the input parameter value is 0 or null, or you have not joined the conference, this value is returned.
5	Indicates that the invoking times out.	N/A
6	Indicates that the parameter is incorrect.	N/A
7	Indicates that the memory is insufficient.	N/A
8	Indicates that the XML parameter is incorrect.	N/A
9	Indicates that you do not have the rights.	N/A
10	Indicates that the interface to be invoked is not supported or has not been implemented.	N/A
11	Indicates that the module is not loaded.	—
101	Indicates that your request is rejected.	N/A
102	Indicates a network error.	N/A
103	Indicates that the version is not supported.	N/A
104	Indicates that the communication protocol is incorrect.	N/A
105	Indicates that the number of connections on the server reaches the maximum.	N/A
106	Indicates that the license expires.	N/A
107	Indicates that the conference has ended.	N/A
109	Indicates the disconnection.	N/A
111	Indicates that the user does not exist.	N/A
112	Indicates that the number of channels in the conference reaches the threshold.	N/A
126	Indicates an authentication failure.	N/A
127	Indicates an unknown error.	N/A
136	Indicates that the authentication of the license times out, and you cannot join the conference.	N/A
137	Indicates that access to the server area is not allowed, and you cannot join the conference.	N/A
138	Indicates that you have joined the conference and cannot join the conference again.	N/A
300	Indicates that you leave the conference properly.	N/A
301	Indicates that you are forced to leave the conference.	N/A
302	Indicates that the token is deleted.	N/A
303	Indicates a system exception.	N/A
304	Indicates a network error.	N/A
305	Indicates a timeout.	N/A
306	Indicates an unknown error.	N/A
307	Indicates the maximum number in the license is exceeded.	N/A
308	Indicates a system error.	N/A
309	Indicates that the user is offline.	N/A
400	Indicates that the meeting component has not been initialized.	N/A
401	Indicates duplicate initialization.	N/A
402	Indicates that you have joined the conference.	N/A
403	Indicates that you have not joined the conference.	N/A
404	Indicates that the component has not been loaded.	N/A
405	Indicates the data is oversized.	N/A
406	Indicates that the sending speed is too fast.	N/A
407	Indicates that the conference has ended.	N/A
408	Indicates that you have left the conference.	N/A

Return Code	Description	Remarks
409	Indicates that the component has been loaded.	N/A
410	Indicates that the component has been uninstalled.	N/A
411	Indicates that you are disconnected from the conference.	N/A
412	Indicates that the parameter is incorrect.	N/A
413	Indicates that the conference environment has not been initialized.	N/A
414	Indicates that you are the presenter.	N/A
415	Indicates that the phone has not been initialized.	N/A
416	Indicates that you fail to join the phone conference.	N/A
417	Indicates a memory application failure.	N/A
418	Indicates that the parameter is invalid.	N/A
419	Indicates that the conference name exists.	N/A
420	Indicates that the conference ID is incorrect in the PaaS mode. The first 12 digits in the conference ID must be empty.	N/A
1101	Indicates that the document does not exist.	
1102	Indicates that the page does not exist.	
1103	Indicates that the parameter does not exist.	
1104	Indicates that the element does not exist.	
1105	Indicates that the document exists.	
1106	Indicates that the page exists.	
1107	Indicates that the .cwp file is invalid.	
1109	Indicates that the document property does not exist.	
1110	Indicates that the document has been opened.	
1111	Indicates that the module is not initialized.	
1112	Indicates that the callback interface is not set.	
1113	Indicates that the channel is not added.	
1114	Indicates that the user is offline.	
1115	Indicates that the document is being printed.	
1116	Indicates that the document page data is being downloaded.	
1117	Indicates that a saved whiteboard file is opened during document sharing, or a shared and saved document is loaded during whiteboard sharing.	
1118	Indicates that the page data is not uploaded to the server, and the sharer is not in the conference.	
1121	Indicates that the component object model (COM) fails to be invoked.	
1122	Indicates that the document contains no page.	
1123	Indicates that printing is canceled.	
1124	Indicates that the document format is not supported.	
1125	Indicates that the Microsoft Office version is not supported.	
1126	Indicates that conversion fails.	
1127	Indicates an empty file.	
1128	Indicates that the file format is incorrect.	
1129	Indicates that printing times out.	
1130	Indicates that the printer has not been installed.	
1131	Indicates a thread error during .ppt file loading.	
1132	Indicates a .ppt file loading error.	
1133	Indicates that the document page number exceeds the upper limit (200 pages).	
1134	Indicates a printer error.	
1135	Indicates a printing service error.	
1136	Indicates that the PowerPoint 2003 is running independently so that the Conference OCX cannot create an instance to load the .ppt or .pptx file.	
1137	Indicates that you have no rights to open the document.	

Return Code	Description	Remarks
1138	Indicates that WPS Office has not been installed.	
1140	Indicates that the laser point exists.	
1141	Indicates that the customized annotation type does not exist.	
1201	Indicates an unknown error.	N/A
1202	Indicates that the parameter is incorrect.	N/A
1203	Indicates a user error.	N/A
1204	Indicates a network error.	N/A
1205	Indicates that a component is not initialized.	N/A
1206	Indicates a status sharing error.	N/A
1207	Indicates that the window handle is incorrect.	N/A
1208	Indicates that the sharing task fails to be created.	N/A
1209	Indicates that the user is offline.	N/A
1210	Indicates an error in reading/writing an XML file.	N/A
1211	Indicates that the module is locked.	N/A
1212	Indicates that the first data frame has not been sent.	N/A
1301	Indicates that the window is empty.	N/A
1302	Indicates that the window is in use.	N/A
1303	Indicates that the video device is being disconnected.	N/A
1305	Indicates that the engine fails to be created.	N/A
1306	Indicates that there is no session for the video.	N/A
1307	Indicates that there is no object in the video.	N/A
1308	Indicates that there is no idle table for the video.	N/A
1309	Indicates that the device is already in the list of devices being turned on when you turn on the device.	N/A
1310	Indicates that the video component has not been prepared.	N/A
1311	Indicates that the video library has been uninstalled.	N/A
1312	Indicates that the resolution is beyond the supported range.	N/A
1313	Indicates that the resolution exceeds the maximum resolution supported by the device.	N/A
1314	Indicates that the number of opened video channels exceeds the maximum.	N/A
1320	Indicates that the same capabilities are being used on the device.	N/A
1321	Indicates that video components are released.	N/A
1322	Indicates that the cell corresponding to the user terminal cannot be detected for the video.	N/A
1323	Indicates that the number of opened video channels exceeds the maximum.	N/A
1324	Indicates that the video is paused.	N/A
1325	Indicates that the video is not paused.	N/A
1326	Indicates that an error occurs during switch between the high-resolution streams and low-resolution streams. This value is returned when the interface is not invoked by the decoding party, or the video is paused.	N/A
1327	Indicates a video operation error. (The video data table has been abnormal.)	N/A
1330	Indicates that traffic control is being performed.	N/A
1331	Indicates that external traffic control is being performed.	N/A
1340	Indicates that the video device is in use.	N/A
1341	Indicates that the video device is being used by the wizard.	N/A
1350	Indicates that the video device does not belong to the current user.	N/A
1351	Indicates that the video file name is too long.	N/A
1352	Indicates that the video rendering parameter is incorrect.	N/A
1353	Indicates that the video rotation parameter is incorrect.	N/A

Return Code	Description	Remarks
1354	Indicates that the function is not supported by the Windows operating system.	N/A
1355	Indicates that the object is not a window.	N/A
1356	Indicates that the resolution set on the device exceeds the maximum resolution for collecting video.	N/A
1357	Indicates that the handles of the window when the window is detached and attached are different.	N/A
1358	Indicates that the video Huawei Media Engine (HME) is being used by a conference. Multiple conferences cannot simultaneously use the HME.	N/A
1801	Indicates that the file cannot be created.	N/A
1802	Indicates that the download is canceled.	N/A
1803	Indicates an invalid file handle.	N/A
1804	Indicates an invalid component status.	N/A
1805	Indicates an invalid file.	N/A
1806	Indicates an empty file.	N/A
1807	Indicates that the file upload times out.	N/A
1808	Indicates that the file is being downloaded.	N/A

Parent topic: [Return Code](#)

VRC Interface (ActiveX)

[About This Document](#)

[API Reference](#)

[Data Reference](#)

Copyright © Chengdu TD-Tech Co., Ltd.

About This Document

[Overview](#)

[Intended Audience](#)

[Symbol Conventions](#)

[Change History](#)

Parent topic: [VRC Interface \(ActiveX\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Overview

This document describes video record client (VRC) interfaces for implementing screen inspection, including VRC application programming interfaces (APIs) and data structures.

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Intended Audience

This document is intended for:

- Technical support engineers
- Secondary development engineers

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Symbol Conventions

The symbols that may be found in this document are defined as follows.

Symbol	Description
 DANGER	Indicates an imminently hazardous situation which, if not avoided, will result in death or serious injury.
 WARNING	Indicates a potentially hazardous situation which, if not avoided, could result in death or serious injury.
 CAUTION	Indicates a potentially hazardous situation which, if not avoided, may result in minor or moderate injury.
 NOTICE	Indicates a potentially hazardous situation which, if not avoided, could result in equipment damage, data loss, performance deterioration, or unanticipated results. NOTICE is used to address practices not related to personal injury.
 NOTE	Calls attention to important information, best practices and tips. NOTE is used to address information not related to personal injury, equipment damage, and environment deterioration.

Parent topic: [About This Document](#)

Change History

- [Issue 06 \(2017-06-20\)](#)
- [Issue 05 \(2017-05-17\)](#)
- [Issue 04 \(2016-05-30\)](#)
- [Issue 03 \(2014-08-30\)](#)
- [Issue 02 \(2014-05-30\)](#)
- [Issue 01 \(2012-06-25\)](#)

Parent topic: [About This Document](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Issue 06 (2017-06-20)

This issue is released for IPCCV200R001C80SPC700, which incorporates the following changes:

- Added description in section [InitializeAgentEx](#).
- Added section [OnNotifyInitAgentResult](#).

Parent topic: [Change History](#).

Copyright © Chengdu TD-Tech Co., Ltd.

Issue 05 (2017-05-17)

This issue is released for IPCC V200R001C80SPC600, which incorporates the following changes:

- Deleted the InitializeAgent interface, which is used to sign the agent in passive mode. Discarded the passive mode because it does not meet safety requirements.

Parent topic: [Change History](#).

Copyright © Chengdu TD-Tech Co., Ltd.

Issue 04 (2016-05-30)

This issue is released for IPCC V200R001C80, which incorporates the following changes:

- Added section [SetRecordParam](#).

Parent topic: [Change History](#).

Copyright © Chengdu TD-Tech Co., Ltd.

Issue 03 (2014-08-30)

This issue is released for ICD V300R006C80, which incorporates the following changes:

- Added the InitializeAgent interface.
- Added the **AgentSockPort** and **AgentIP** parameters to section [SetRunParam](#)
- Added the description of **libmp4v2.dll** to the **Screen Inspection Files** section.
- Deleted the description of return values from section [Uninitialize](#)

Parent topic: [Change History](#).

Copyright © Chengdu TD-Tech Co., Ltd.

Issue 02 (2014-05-30)

This issue is released for ICD V300R006C70, which incorporates the following changes:

- Added section [Uninitialize](#), the InitializeAgent interface, and section [OnPlayEnd](#).
- Deleted the descriptions of the following interfaces not supported in the current version from the document: BatchPlayback, InitializeAgent, BatchPlaybackFor3, GetAudioFile, DelFile, HTTPPlayBackMedia, GetHttpAudioFile, GetAudioFile2Local, and GetHTTPAudioFile2Local.
- Updated custom parameters in section [SetRunParam](#).
- Supplemented the value ranges of the agent ID and port number.
- Deleted the description of the WTS mode from section "Deployment Mode of Cloud Agents."
- Updated section "Screen Inspection Files".
- Deleted the description of the screen inspection test tool.
- Deleted the descriptions of the OnGetAudio2LocalEnd event and the OnGetHttpAudioEnd event from section [Events](#).
- Changed the value range 0–65534 to 1–65534.
- Updated the codes for calling the SetRunParam function in sections "Codes."

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Issue 01 (2012-06-25)

Based on ICD V300R005C40, this issue is the first official release for ICD V300R006C10, which incorporates the following changes:

- Optimized section "Code Description."
- Changed the description of the virtual desktop infrastructure (VDI) mode in section "Deployment Mode of Cloud Agents."

Parent topic: [Change History](#)

Copyright © Chengdu TD-Tech Co., Ltd.

API Reference

[QC Console Interfaces](#)

[Agent Console Interfaces](#)

[Public Interfaces](#)

[Events](#)

Parent topic: [VRC Interface \(ActiveX\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

QC Console Interfaces

[InitializeQC](#)

[StartMonitor](#)

[StartMonitorEx](#)

[StopMonitor](#)

[StopMonitorEx](#)

[GetLastErrorCode](#)

[Playback](#)

[PlaybackFor3](#)

[PlaybackMedia](#)

[PlaybackEncryptMedia](#)

Parent topic: [API Reference](#)

Copyright © Chengdu TD-Tech Co., Ltd.

InitializeQC

Function

This function is used to initialize the QC console.
This function is a synchronous interface.

Prototype

```
long InitializeQC ();
```

Parameter Description

None

Return Value

Table 1 Return values of the InitializeQC function

Type	How to Understand	Error Code Description
long	Cause code.	See section Error Codes The specific error code is subject to actual prompts.

Constraints

- To initiate real-time screen inspection of an agent from the QC console, this interface must be invoked first.
- This interface needs to be invoked only once. It does not need to be invoked each time before [StartMonitor](#) is initiated.

Parent topic: [QC Console Interfaces](#)

StartMonitor

Function

This function is used to initiate real-time screen inspection to the agent console.
This function is an asynchronous interface.

Prerequisites

- 1. The InitializeQC method has been invoked to initiate the QC console.
- 2. The return value **ERROR_OK** has been received.

Prototype

```
long StartMonitor(LPCTSTR lpszAgentIP, long lAgentID);
```

Parameter Description

Table 1 Parameters of the StartMonitor function

Parameter	How to Understand	How to Set
lpszAgentIP	Destination IP address of the service representative to be inspected.	Format: 10.10.10.1
lAgentID	ID of the service representative to be inspected.	Type: integer This parameter must be set to a valid employee ID of the service representative. Value range: 1–59999

Return Value

Table 2 Return values of the StartMonitor function

Type	How to Understand	Error Code Description
Long	Cause code.	See section Error Codes The specific error code is subject to actual prompts.

Constraints

This interface is invoked in synchronous mode.

Associated API

1

Parent topic: [QC Console Interfaces](#)

StartMonitorEx

Function

This function is used to initiate real-time screen inspection to the agent console.
This function is invoked in asynchronous mode.

Prerequisites

- 1. The [InitializeQC](#) method has been invoked to initiate the QC console.
- 2. The return value **ERROR_OK** has been received.

Prototype

```
long CVRCControlCtrl::StartMonitorEx(LPCTSTR lpszAgentIP, long lAgentID, long lAgentPort);
```

Parameter Description

Parameters of the StartMonitorEx function

Parameter	How to Understand	How to Set
lpszAgentIP	Destination IP address of the service representative to be inspected.	Format: 10.10.10.1
lAgentID	ID of the service representative to be inspected.	Type: integer This parameter must be set to a valid employee ID of the service representative. Value range: 1–59999
ISockPort	Port number used on the agent console	This port number is the socket port number specified when the SetRunParam function is invoked to initialize the agent. Value range: 1–65534 NOTE: If the specified port number is not 6600, the web QC console cannot initiate real-time screen inspection to the agent console.

Return Value

Return values of the StartMonitorEx function

Type	How to Understand	Error Code Description
Long	Cause code.	See section Error Codes The specific error code is subject to actual prompts.

Constraints

None

Associated API

[StopMonitorEx](#)

Parent topic: [QC Console Interfaces](#)

StopMonitor

Function

This interface is used to stop real-time screen inspection of the agent console.
This function is an asynchronous interface.

Prerequisites

- 1. The [InitializeQC](#) method has been invoked to initiate the QC console.
- 2. The [StartMonitor](#) method has been invoked to start real-time screen inspection of the destination service representative.
- 3. The return value **ERROR_OK** has been received.

Prototype

```
long StopMonitor(LPCTSTR lpszAgentIP);
```

Parameter Description

Table 1 Parameters of the StopMonitor function

Parameter	How to Understand	How to Set
lpszAgentIP	Destination IP address of the service representative to be inspected.	Format: 10.10.10.1

Return Value

Table 2 Return values of the StopMonitor function

Type	How to Understand	Error Code Description
long	Cause code.	See section Error Codes The specific error code is subject to actual prompts.

Constraints

If the stopping of screen inspection is triggered by closing the screen inspection window, the [OnMonitorStop](#) event will be triggered.

Associated API

[StartMonitor](#)

Parent topic: [QC Console Interfaces](#)

StopMonitorEx

Function

This interface is used to stop real-time screen inspection of the agent console.
This function is an asynchronous interface.

Prototype

```
long CVRCControlCtrl::StopMonitorEx(long lAgentID);
```

Parameter Description

Parameters of the StopMonitorEx function

Parameter	How to Understand	How to Set
lAgentIP	Destination IP address of the service representative to be inspected.	Format: 10.10.10.1

Return Value

Return values of the StopMonitorEx function

Type	How to Understand	Error Code Description
long	Cause code.	See section Error Codes The specific error code is subject to actual prompts.

Constraints

If the stopping of screen inspection is triggered by closing the screen inspection window, the [OnMonitorStop](#) event will be triggered. If screen inspection is initiated using the [StartMonitorEx](#) interface, this interface must be used to stop the screen inspection.

Associated API

[StartMonitorEx](#)

Parent topic: [QC Console Interfaces](#)

GetLastErrorCode

Function

If the playback interface fails to be invoked and no error code is returned, this method can be invoked to obtain the operation failure cause.

Prerequisites

No success message or no any error code is returned after the playback interface is called.

Prototype

```
long GetLastErrorCode();
```

Parameter Description

None

Return Value

Table 1 Return values of the GetLastErrorCode function

Type	How to Understand	Error Code Description
long	Cause code.	See section Error Codes The specific error code is subject to actual prompts.

Parent topic: [QC Console Interfaces](#)

Playback

Function

This function is used to play back a single video file.
This function is an asynchronous interface.

Prototype

```
long Playback(LPCTSTR lpszFileName, LPCTSTR lpszUserName, LPCTSTR lpszPassword, long lStartSeg, long lPlayTime);
```

Parameter Description

The following table describes the parameters of the Playback function.

Parameter	How to Understand	How to Set
lpszFileName	Full name of the video file. The file name does not contain any file name extension.	File name format: - ftp://ip/x/x/x/xxxx Example: If the file name is as follows: ftp://10.10.10.1/temp/1/1/113245.vz, the value is as follows: ftp://10.10.10.1/temp/1/1/113245 - xxxx Example: If the file name is as follows: 113245.vz the value is as follows: \\10.10.10.1\\1\\1\\113245
lpszUserName	Name of the user to access the directory where the video file is stored.	Set the user name to the actual one.
lpszPassword	Character string of the encrypted user password.	The password must be consistent with the actual character string of the encrypted user password.
lStartSeg	Time offset of the start position of the video file to be played back with reference to the video file.	Unit: second
lPlayTime	Play duration of the video file to be played back	Unit: second

Return Value

The following table describes the return values of the Playback function.

Type	How to Understand	Error Code Description
long	Cause code.	See section 4.2 The specific error code is subject to actual prompts.

Constraints

None

Parent topic: [QC Console Interfaces](#)

PlaybackFor3

Function

This function enables third-party platforms to play back a single video file.
This function is an asynchronous interface for use by third-party platforms only.

NOTE

This interface has the same function as the Playback interface, except that the password of the user to access the file is not encrypted.

Prototype

```
long PlaybackFor3(LPCTSTR lpszFileName, LPCTSTR lpszUserName, LPCTSTR lpszPassword, long lStartSeg, long lPlayTime);
```

Parameter Description

The following table describes the parameters of the PlaybackFor3 function.

Parameter	How to Understand	How to Set
lpszFileName	Full name of the video file to be played back The file name does not contain any file name extension.	File name format: - ftp://ip/x/x/x/xxxx Example: If the file name is as follows: ftp://10.10.10.1/temp/1/1/113245.vz, the value is as follows: ftp://10.10.10.1/temp/1/1/113245 - xxxx Example: If the file name is as follows: 113245.vz the value is as follows: \\10.10.10.1\\1\\1\\113245
lpszUserName	Name of the user to access the directory where the file to be played back is stored.	Set the user name to the actual one.
lpszPassword	Password of the user to access the file to be played back.	Set the user password to the actual one.
lStartSeg	Time offset of the start position of the video file to be played back with reference to the video file.	Unit: second
lPlayTime	Play duration of the video file to be played back.	Unit: second

Return Value

The following table describes the return values of the PlaybackFor3 function.

Type	How to Understand	Error Code Description
long	Cause code.	See section Error Codes The specific error code is subject to actual prompts.

Constraints

None

Parent topic: [QC Console Interfaces](#)

PlaybackMedia

Function

This function is used to play a media file synthesized from a video file and an audio file to achieve the effect of synchronously playing images and sound. This function is an asynchronous interface.

Prototype

```
long PlaybackMedia(LPCTSTR lpszVideoFileName, LPCTSTR lpszVideoUser, LPCTSTR lpszVideoPassword, BOOL bHasAudio, LPCTSTR lpszAudioFileName, LPCTSTR lpszAudioUser, LPCTSTR lpszAudioPassword, LPCTSTR lpszAudioExt, BOOL bIsAudioEarlier, long lOffsetBeginTime, long lVideoOffsetFileTime, long lPlayVideoTime, long lPlayAudioTime);
```

Parameter Description

The following table describes the parameters of the PlaybackMedia function.

Parameter	How to Understand	How to Set
lpszVideoFileName	Video file to be played.	File name format: - ftp://ip/x/x/x/xxxx Example: If the file name is as follows: ftp://10.10.10.1/temp/1/1/113245.vz the value is as follows: ftp://10.10.10.1/temp/1/1/113245 - xxxx Example: If the file name is as follows: 113245.vz the value is as follows: \\10.10.10.1\\1\\1\\113245
lpszVideoUser	Name of the user to access the video file.	Set the user name to the actual one.
lpszVideoPassword	Password of the user to access the video file.	Set the user password to the actual one.
bHasAudio	Indicates whether there is an audio file to be synchronously played with the video file.	The options are as follows: 0: no 1: yes
lpszAudioFileName	Name of the audio file to be synthesized with the video file for playing.	Format: - ftp://ip/x/xx/xxx.v3 Example: If the file name is as follows: ftp://10.10.10.1/trmp/vrctemp/20110604.v3 the value is as follows: ftp://10.10.10.1/trmp/vrctemp/20110604.v3 \\ip\\xx\\xxx.v3 Example: If the file name is as follows: 20110604.v3 the value is as follows: 20110604.v3
lpszAudioUser	Name of the user to access the audio file.	Set the user name to the actual one.
lpszAudioPassword	Password of the user to access the audio file.	Set the user password to the actual one.
lpszAudioExt	Local file name extension of the audio file.	This parameter should be set to wav .
bIsAudioEarlier	Indicates whether the audio is played earlier than the video.	The options are as follows: 0: no 1: yes
lOffsetBeginTime	Start time offset between the video and the audio.	If the video is played earlier than the audio, this parameter is a positive value; otherwise, this parameter is a negative value.
lVideoOffsetFileTime	Time offset of the start position of the video to be played this time with reference to the start position of the video file.	Unit: millisecond
lPlayVideoTime	Play duration of the video file.	Unit: millisecond
lPlayAudioTime	Play duration of the audio file.	Unit: millisecond

Return Value

The following table describes the return values of the PlaybackMedia function.

Type	How to Understand	Error Code Description
long	Cause code.	See section Error Codes The specific error code is subject to actual prompts.

Constraints

None

Parent topic: [QC Console Interfaces](#)

PlaybackEncryptMedia

Function

This function is used to synchronously play a media file synthesized from a video file and an audio file, but whether to encrypt the passwords of the users to access the video file and audio file is controlled by the invoking party's parameter settings.

This function is an asynchronous interface.

Prototype

```
long PlaybackEncryptMedia (LPCTSTR lpszVideoFileName, LPCTSTR lpszVideoUser, LPCTSTR lpszVideoPassword, BOOL bHasAudio, LPCTSTR lpszAudioFileName, LPCTSTR lpszAudioUser, LPCTSTR lpszAudioPassword, LPCTSTR lpszAudioExt, BOOL bIsAudioEarlier, long lOffsetBeginTime, long lVideoOffsetFileTime, long lPlayVideoTime, long lPlayAudioTime, BOOL bVideoPwdEncrypt, BOOL bAudioPwdEncrypt);
```

Parameter Description

Description of parameters of the PlaybackEncryptMedia function

Parameter	How to Understand	How to Set
lpszVideoFileName	Video file to be played.	File name format: ftp://ip/x/x/x/xxxx Example: If the file name is as follows: ftp://10.10.10.1/temp/1/1/113245.vz the value is as follows: ftp://10.10.10.1/temp/1/1/113245
lpszVideoUser	Name of the user to access the video file	Set the user name to the actual one.
lpszVideoPassword	Password of the user to access the video file	Set the user password to the actual one.
bHasAudio	Indicates whether there is an audio file to be synchronously played with the video file.	The options are as follows: 0: no 1: yes
lpszAudioFileName	Name of the audio file to be synthesized with the video file for playing.	Format: ftp://ip/x/xx/xxx.v3 Example: If the file name is as follows: ftp://10.10.10.1/trmp/vrctemp/20110604.v3 the value is as follows: ftp://10.10.10.1/trmp/vrctemp/20110604.v3
lpszAudioUser	Name of the user to access the audio file.	Set the user name to the actual one.
lpszAudioPassword	Password of the user to access the audio file.	Set the user password to the actual one.
lpszAudioExt	Local file name extension of the audio file.	Directly enter wav .
bIsAudioEarlier	Indicates whether the audio is played earlier than the video.	The options are as follows: 0: no 1: yes
lOffsetBeginTime	Start time offset between the video and the audio.	If the video is played earlier than the audio, this parameter is a positive value; otherwise, this parameter is a negative value.
lVideoOffsetFileTime	Time offset of the start position of the video to be played this time with reference to the start position of the video file.	Unit: millisecond
lPlayVideoTime	Play duration of the video file.	Unit: millisecond
lPlayAudioTime	Play duration of the audio file.	Unit: millisecond
bVideoPwdEncrypt	Indicates whether to encrypt the password of the user to access the video file.	The options are as follows: 0: no 1: yes
bAudioPwdEncrypt	Indicates whether to encrypt the password of the user to access the audio file.	The options are as follows: 0: no 1: yes

Return Value

The following table describes the return values of the PlaybackEncryptMedia function.

Type	How to Understand	Error Code Description
long	Cause code.	See section Error Codes The specific error code is subject to actual prompts.

Constraints

None

Parent topic: [QC Console Interfaces](#)

Agent Console Interfaces

[InitializeAgentEx](#)

[ExitAgent](#)

Parent topic: [API Reference](#)

Copyright © Chengdu TD-Tech Co., Ltd.

InitializeAgentEx

Function

This function is used to sign in to the agent console in active mode.
This function is an asynchronous interface. This function will trigger event [OnNotifyInitAgentResult](#). This event indicates the result of agent initialization.

 **NOTE**

This function is an asynchronous interface. If the return value is 0, basic input parameter verification is passed and the agent initialization result is specified by the OnNotifyInitAgentResult event. If the return value is not 0, the OnNotifyInitAgentResult event will not be triggered.

Prototype

```
long InitializeAgentEx(BSTR pszEntryVRPList, short usAgentIDClass, BSTR pszAgentID, BSTR pszSelfIP, long ulSelfPort, BSTR pszAddiParam, BSTR pszToken);
```

Parameter Description

Parameter	How to Understand	How to Set
pszEntryVRPList	Entry VRP list for use during VRC login.	Format: IP(Port), IP(Port), ... Example: 10.71.105.82(6001), 10.71.105.82(6002), 10.71.105.83(6001)
usAgentIDClass	Login type of the VRC.	Set this parameter to 2. Currently, this parameter can be only set to 2, indicating an agent.
pszAgentID	Login ID of the VRC.	Set this parameter to a specific agent ID. Value range: 1–59999
pszSelfIP	IP address of the VRC to monitor and receive a real-time screen inspection task.	Set this parameter to the local IP address used for screen inspection.
ulSelfPort	Port number of the VRC to monitor and receive a real-time screen inspection task.	Set this parameter to the local port number used for screen inspection. If this parameter is left empty, the default port number 6600 is used. Value range: 1–65534
pszAddiParam	Other additional parameters. It is reserved.	Leave this parameter empty.
pszToken	This parameter is used for VRC and VRP authentication.	If Agent Server interfaces are used for development, the interface for obtaining screen recording authentication information is invoked to obtain this value by referring to the <i>Agent Gateway Development Guide</i> . If connection controls are used for development, the QueryConnectToken interface is invoked to obtain this value by referring to the <i>CTI Interface Reference (ActiveX)</i> . If the AgentSDK is used for development, the mediaTellerQueryVrcToken interface is invoked to obtain this value by referring to the <i>AgentSDK Interface Reference (ActiveX)</i> .

Return Value

Table 1 Return values of the InitializeAgentEx function

Type	How to Understand	Error Code Description
long	Cause code.	See section Error Codes . The specific error code is subject to actual prompts.

Constraints

None
Parent topic: [Agent Console Interfaces](#)

ExitAgent

The ExitAgent function is used to sign out of an agent.

- The [ExitAgent](#) interface corresponds to [InitializeAgentEx](#). The [InitializeAgentEx](#) interface is used to sign in an agent.
The [ExitAgent](#) interface is used to sign out of an agent.

NOTE

After the agent is successfully initialized, you can invoke this interface to release the agent. No value is returned after the interface is invoked.

Parent topic: [Agent Console Interfaces](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Public Interfaces

[Uninitialize](#)

[SetRunParam](#)

[SetRecordParam](#)

Parent topic: [API Reference](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Uninitialize

Function

This function is used to exit the QC console or agent console.
This function is a synchronous interface.

Prototype

```
long Uninitialize;
```

Parameter Description

None

Return Value

None

Constraints

- This interface is invoked to exit the QC console or agent console.
- This interface needs to be invoked only once.

Parent topic: [Public Interfaces](#)

SetRunParam

Function

This function is used to customize certain usability parameters for the running of the VRC.
This function is a synchronous interface.

Prototype

```
long SetRunParam(BSTR lpszParam);
```

Parameter Description

Table 1 Parameters of the SetRunParam function

Parameter	How to Understand	How to Set
lpszParam	Parameters to be customized.	Format: key1=value1;key2=value2;...

Table 2 Customizable parameters

Parameter	How to Understand	How to Set
AgentSockPort	Socket port number of the agent.	The invoking party specifies an available socket port number. Default: 6600 Value range: 1–65534
AgentIP	IP address of the agent. This parameter needs to be set only when multiple network interface cards (NICs) are installed on the computer of the agent.	The calling party specifies one of multiple IP addresses as the IP address of the agent. If this parameter is left empty, the first IP address in the host file of the computer will be used as the IP address of the agent.
MonitorCount	- If the SetRunParam function is invoked before the agent console invokes the InitializeAgentEx function, this parameter indicates the maximum number of QC inspectors to simultaneously perform screen inspection for one agent. - If the SetRunParam function is invoked before the QC console invokes the InitializeQC function, this parameter indicates the maximum number of agents to which one inspector can initiate screen inspection.	Value range: 5–10 Default: 10 NOTE: If the value you set here does not fall within the value range, the system automatically uses the default value.

Return Value

Table 3 Return values of the SetRunParam function

Type	How to Understand	Error Code Description
long	Cause code.	See section Error Codes The specific error code is subject to actual prompts.

Constraints

None

Parent topic: [Public Interfaces](#)

SetRecordParam

Function

This function is used to set parameters related to VRC dual-screen recording.
This function is a synchronous interface.

Prototype

```
long SetRecordParam(BSTR lpszParam);
```

Parameter Description

Table 1 Parameters of the SetRecordParam function

Parameter	How to Understand	How to Set
lpszParam	Parameters to be customized.	Format: key1=value1;key2=value2;...

Table 2 Customizable parameters

Parameter	How to Understand	How to Set
recordType	Recording type: single-screen recording or dual-screen recording.	The calling party specifies the recording type. Default: 1 Valid value: 1 (Single-screen) or 2 (Dual-screen)
screenNo	Screen number indicating the main screen or auxiliary screen. This parameter is valid only when the recording type indicates single-screen recording.	The calling party specifies the number of the screen to be recorded. Default: 0 Valid value: 0 (Main screen) or 1 (Auxiliary screen)
mainScreenX	Width of the main screen.	Set this parameter to the fixed value 0 or leave this parameter empty, indicating that recording is performed based on the resolution of the screen itself.
mainScreenY	Height of the main screen	Set this parameter to the fixed value 0 or leave this parameter empty, indicating that recording is performed based on the resolution of the screen itself.
subScreenX	Width of the auxiliary screen	Set this parameter to the fixed value 0 or leave this parameter null to represent recording based on the resolution of the screen itself.
subScreenY	Height of the auxiliary screen	Set this parameter to the fixed value 0 or leave this parameter empty, indicating that recording is performed based on the resolution of the screen itself.

 **NOTE**

The resolution cannot be lower than 96x96, and both the width and height must be an integer multiple of 16 according to HME requirements. If the requirements are not satisfied, the system automatically corrects the input value to the maximum allowed value less than the input value. For example, if the resolution value you enter is 1920x1080, the actual resolution will be 1920x1072 during screen recording.

Return Value

Table 3 Return values of the SetRecordParam function

Type	How to Understand	Error Code Description
long	Cause code.	See section Error Codes The specific error code is subject to actual prompts.

Constraints

- The resolution of the main screen and that of the auxiliary screen must be consistent with each other. If the two are inconsistent, the screen recording parameters you set for the auxiliary screen may be invalid.
- The maximum resolution is 1920x1080 for a single screen.
- Two and only two screens must exist during dual-screen or auxiliary-screen recording; otherwise, the main screen can be recorded instead or the screen recording may fail.

Parent topic: [Public Interfaces](#)

Events

[OnPlayEnd](#)

[OnMonitorStop](#)

[OnNotifyInitAgentResult](#)

Parent topic: [API Reference](#)

Copyright © Chengdu TD-Tech Co., Ltd.

OnPlayEnd

Function

This event indicates that the playback is complete.

Prototype

```
void OnPlayEnd();
```

Parameter Description

None

Triggering Condition

When the playback window is closed after the playback interface Playback, PlaybackFor3, PlaybackMedia, or PlaybackEncryptMedia is invoked for playback, this event will be triggered.

Parent topic: [Events](#)

Copyright © Chengdu TD-Tech Co., Ltd.

OnMonitorStop

Function

This event indicates that real-time screen inspection has been stopped.

Prototype

```
void OnMonitorStop(long lAgentID, BSTR lpszIPAddress);
```

Parameter Description

Table 1 Parameters of the OnMonitorStop event

Parameter	How to Understand
lAgentID	ID of the service representative to be inspected. This parameter is the same as the employee ID of the service representative described in section StartMonitor . Value range: 1–59999
lpszIPAddress	Destination IP address of the service representative to be inspected. This parameter is the same as the destination IP address described in section StartMonitor .

Triggering Condition

After real-time screen inspection is successfully initiated by invoking [StartMonitor](#) or [StartMonitorEx](#), if the screen inspection window is closed or screen inspection is unexpectedly stopped (because the screen inspection window fails to be created, the decoder or encoder fails to be enabled, the connection fails, or screen inspection times out), this event will be triggered.

Parent topic: [Events](#)

OnNotifyInitAgentResult

Function

This event indicates the result of agent initialization. This event is triggered by the InitializeAgentEx interface.

Prototype

```
void OnNotifyInitAgentResult(ULONG ulResult);
```

Parameter Description

Table 1 Parameters of the OnNotifyInitAgentResult event

Parameter	How to Understand
ulResult	Initialization result. See section Error Codes The specific error code is subject to actual prompts.

Triggering Condition

If [InitializeAgentEx](#) is successfully invoked to sign in to an agent in active mode, this event is triggered. If the return value is not 0 indicating that [InitializeAgentEx](#) fails to be invoked, this event is not triggered.

Parent topic: [Events](#)

Data Reference

[Enumeration](#)

[Error Codes](#)

Parent topic: [VRC Interface \(ActiveX\)](#)

Copyright © Chengdu TD-Tech Co., Ltd.

Enumeration

The following constants are defined for VRC interfaces:

```
const USHORT MAX_USER_NAME_LEN = 64; // Maximum length of user names
const USHORT MAX_USER_PASSWORD_LEN = 64; // Maximum length of user passwords
const UCHAR MAX_FILE_EXT = 3; // Maximum length of file name extensions
```

Table 1 Description of the constants

Enumeration	Value	Description
MAX_FNAME_LEN	256	Maximum length of a file name.
MAX_USER_NAME_LEN	64	Maximum length of a user name.
MAX_USER_PASSWORD_LEN	64	Maximum length of a user password.
MAX_PATH	260	Maximum length of a path.
MAX_FILE_EXT	3	Maximum length of a file name extension.

[PLAY FILE NAME](#)

[PLAY FILE INFO](#)

Parent topic: [Data Reference](#)

PLAY_FILE_NAME

Data Structure

```
typedef struct _PLAY_FILE_NAME
{
char szVideoFileName[MAX_PATH + 1]; // Name of the video file to be played
char szVideoUser[MAX_USER_NAME_LEN + 1]; // User name
char szVideoPassword[MAX_USER_PASSWORD_LEN + 1]; // User password
BOOL bHasAudio; // Indicates whether to simultaneously play the audio
char szAudioFileName[MAX_PATH + 1]; // Name of the audio file to be played if audio will also be played
char szAudioUser[MAX_USER_NAME_LEN + 1]; // User name
char szAudioPassword[MAX_USER_PASSWORD_LEN + 1]; // User password
char szAudioExt[MAX_FILE_EXT + 1]; // File name extension of the audio file
BOOL bIsAudioEarlier; // Indicates whether to generate the audio earlier than the video
ULONG ulOffsetBeginTime; // Start time offset between the video and the audio in ms
ULONG ulVideoOffsetFileTime; // Offset of the video portion of the recording task in the video file (when multiple tasks share the same file and a certain time offset exists)
ULONG ulPlayVideoTime; // Play duration of the video
ULONG ulBeginPlayAudioTime; // Offset of the audio portion of the recording task in the audio file, which must be 0
ULONG ulPlayAudioTime; // Duration of the audio portion of the recording task
}PLAY_FILE_NAME, *PPLAY_FILE_NAME;
```

Parameter Description

Parameters of the PLAY_FILE_NAME data structure

Parameter	How to Understand	How to Set
szVideoFileName	Video file to be played.	File name format: - ftp://ip/x/x/x/xxxx Example: If the file name is as follows: ftp://10.10.10.1/temp/1/1/113245.vz the value is as follows: ftp://10.10.10.1/temp/1/1/113245 - xxxx Example: If the file name is as follows: 113245.vz the value is as follows: \\10.10.10.1\\1\\1\\113245
szVideoUser	Name of the user to access the video file.	Set the user name to the actual one.
szVideoPassword	Password of the user to access the video file.	Set the user password to the actual one.
bHasAudio	Indicates whether there is an audio file to be synchronously played with the video file.	The options are as follows: 0: no 1: yes
szAudioFileName	Name of the audio file to be synthesized with the video file for playing.	File name format: ftp://10.10.10.1/temp/VRCtemp/VRC_0605.V3 \\10.10.10.1\\temp\\VRCtemp\\VRC_0605.V3
szAudioUser	Name of the user to access the audio file.	Set the user name to the actual one.
szAudioPassword	Password of the user to access the audio file.	Set the user password to the actual one.
szAudioExt	File name extension of the audio file.	Directly enter wav .
bIsAudioEarlier	Indicates whether the audio is played earlier than the video.	The options are as follows: 0: no 1: yes
ulOffsetBeginTime	Start time offset between the video and the audio.	If the video is played earlier than the audio, this parameter is a positive value; otherwise, this parameter is a negative value.
ulVideoOffsetFileTime	Time offset of the start position of the video to be played this time with reference to the start position of the video file.	Unit: millisecond
ulPlayVideoTime	Play duration of the video file.	Unit: millisecond
ulBeginPlayAudioTime	Time offset of the start position of the audio to be played this time with reference to the start position of the audio file.	Set this parameter to 0.
ulPlayAudioTime	Play duration of the audio file.	Unit: millisecond

Parent topic: [Enumeration](#)

PLAY_FILE_INFO

Data Structure

```
typedef struct _PLAY_FILE_INFO
{
char szRemoteFileName[MAX_FNAME_LEN + 1]; // Name of the remote file
char szUser[MAX_USER_NAME_LEN + 1]; // User name
char szPassword[MAX_USER_PASSWORD_LEN + 1]; // User password
ULONG ulBeginTime; // Start time offset
ULONG ulPlayTime; // Play duration
}PLAY_FILE_INFO, *PPLAYINFO;
```

Parameter Description

The following table describes the parameters of the PLAY_FILE_INFO data structure.

Parameter	How to Understand	How to Set
szRemoteFileName	Name of the remote file.	Format: - ftp://10.10.10.1/temp/VRCtemp/VRC_0605.V3 \\10.10.10.1\temp\VRCtemp\VRC_0605.V3
szUser	Name of the user to access the remote server.	Set the user name to the actual one.
szPassword	Password of the user to access the remote server.	Set the user password to the actual one.
ulBeginTime	Start time offset.	Unit: millisecond
ulPlayTime	Play duration	Unit: millisecond

Parent topic: [Enumeration](#)

Error Codes

The following error codes are defined for VRC interfaces:

enum VRC_ERROR_CODE		
{		
DEF_ERR(EVRC_INVALID_PARAM,	14401,	"The parameter is invalid",
DEF_ERR(EVRC_SEND_MESSAGE_TO_MODULE_FAILED,	14402,	"The message failed to be sent to the module",
DEF_ERR(EVRC_INIT_AGENT_MODULE_FAILED,	14403,	"The agent module of the VRC failed to be initialized",
DEF_ERR(EVRC_INIT_STREAM_CHANNEL_FAILED,	14404,	"Stream channel initialization failed",
DEF_ERR(EVRC_PUT_MESSAGE_TO_STREAM_CHANNEL_FAILED,	14405,	"The message failed to be put into the stream channel",
DEF_ERR(EVRC_QC_MGR_HAS_INITED,	14406,	"The QC management object has already been initialized",
DEF_ERR(EVRC_QV_MGR_HAS_NOT_INITED,	14407,	"The QC object has not yet been initialized",
DEF_ERR(EVRC_CREATE_FAIL,	14408,	"VRC creation failed",
DEF_ERR(EVRC_AGENT_MGR_SHOULD_NOT_BE_REINIT,	14409,	"The agent management object cannot be repetitively initialized",
DEF_ERR(EVRC_QC_MGR_CREATE_FAILED,	14410,	"The QC management object failed to be initialized",
DEF_ERR(EVRC_PUT_MESSAGE_FAILED,	14411,	"The message failed to be put into the connection channel",
DEF_ERR(EVRC_UNSUPPORTED_INTERFACE,	14412,	"The interface is not supported",
DEF_ERR(EVRC_UNSUPPORTED_OUTPUT_TYPE,	14413,	"The output object type is not supported",
DEF_ERR(EVRC_DETACH_OUTPUT_FAILED,	14414,	"The Detach failed to output the object",
DEF_ERR(EVRC_INVALID_ENCODE_HANDLE,	14415,	"The Encoder handle is invalid",
DEF_ERR(EVRC_INVALID_ENTRY_VRP_IP,	14416,	"The IP address of the entry VRP is invalid",
DEF_ERR(EVRC_INVALID_ENTRY_VRP_PORT,	14417,	"The port number of the entry VRP is invalid",
DEF_ERR(EVRC_INVALID_AGENTID,	14418,	"The agent ID is invalid",
DEF_ERR(EVRC_AGENTID_IS_OUT_OF_REANGE,	14419,	"The agent ID is out of range",
DEF_ERR(EVRC_UNSUPPORTED_AGENTID_CLASS,	14420,	"The agent ID type is not supported",
DEF_ERR(EVRC_CONVERT_BYTEORDER_FAILED,	14421,	"Byte order conversion failed",
DEF_ERR(EVRC_INNER_ERROR_UNDUPORTED_INTERFACE,	14422,	"Internal error: The called internal interface is not supported",
DEF_ERR(EVRC_PUSH_MESSAGE_TO_AGENT_QUEUE_FAILED,	14423,	"The message failed to be put into the agent queue",
DEF_ERR(EVRC_UNKNOWN_MODULEID,	14424,	"The module ID is unknown",
DEF_ERR(EVRC_START_MODULE_THREAD_FAILED,	14425,	"The module thread failed to be started",
DEF_ERR(EVRC_VRC_START_TIMEOUT,	14426,	"VRC start timed out",
DEF_ERR(EVRC_LOAD_HME_DLL_FAILED,	14427,	"The HME dynamic library failed to be loaded",
DEF_ERR(EVRC_INIT_HME_ENGINE_FAILED,	14428,	"The HME engine failed to be initialized",
DEF_ERR(EVRC_CREATE_CAPTURE_FAILED,	14429,	"The capturing channel failed to be created",
DEF_ERR(EVRC_CREATE_ENCODE_FAILED,	14430,	"The encoding channel failed to be created",
DEF_ERR(EVRC_START_CAPTURE_FAILED,	14431,	"The capturing channel failed to be started",
DEF_ERR(EVRC_ENCODE_PARAMS_FAILED,	14432,	"The encoding parameters failed to be set",
DEF_ERR(EVRC_ENCODE_RTCP_PARAMS_FAILED,	14433,	"The RTCP parameters failed to be set",
DEF_ERR(EVRC_ENCODE_SEND_PARAMS_FAILED,	14434,	"The send parameters failed to be set",
DEF_ERR(EVRC_ENCODE_H264_PARAMS_FAILED,	14435,	"The H.264 parameters failed to be set",
DEF_ERR(EVRC_ENCODE_ARS_PARAMS_FAILED,	14436,	"The ARS parameters failed to be set",
DEF_ERR(EVRC_CONNECT_CAP_ENC_FAILED,	14437,	"The capturing channel and encoding channel failed to be connected",
DEF_ERR(EVRC_START_ENCODE_FAILED,	14438,	"The encoding channel failed to be started",
DEF_ERR(EVRC_STOP_CAPTURE_FAILED,	14439,	"The capturing channel failed to be stopped",
DEF_ERR(EVRC_STOP_ENCODE_FAILED,	14440,	"The encoding channel failed to be stopped",
DEF_ERR(EVRC_INVALID_HME_FRAME,	14441,	"The frame data is invalid",
DEF_ERR(EVRC_WRITE_CAPTURE_FRAME_FAILED,	14442,	"The captured frame data failed to be written",
DEF_ERR(EVRC_ENTRYVRP_CHANNEL_FAILED,	14443,	"The channel initialization of the entry VRP failed",
DEF_ERR(EVRC_MANAGEVRP_CHANNEL_FAILED,	14444,	"The channel initialization of the management VRP failed",
DEF_ERR(EVRC_VRC_AUTH_STREAM_VRP_TIMEOUT,	14445,	"Stream control VRP authentication timed out",
DEF_ERR(EVRC_VRC_AUTH_STREAM_DATA_VRP_TIMEOUT,	14446,	"Stream data VRP authentication timed out",
DEF_ERR(EVRC_VRC_CONTROL_HANDSHAKE_DATA_VRP_TIMEOUT,	14447,	"The handshake with the VRP control failed",
DEF_ERR(EVRC_VRC_TASK_HANDSHAKE_CONTROL_VRP_TIMEOUT,	14448,	"The handshake with the VRP task failed",
DEF_ERR(EVRC_VRC_WAIT_STREM_VRP_EXIT_TIMEOUT,	14449,	"The system timed out with no reply to the VRP's exit from the recording process",
DEF_ERR(EVRC_VRC_RECORD_TIMEOUT,	14450,	"The system timed out when the VR starts screen recording",
DEF_ERR(EVRC_INVALID_CONNID,	14451,	"The connection ID is invalid",
DEF_ERR(EVRC_GET_HME_DIR_FAILURE,	14452,	"The path of the HME library failed to be obtained",
DEF_ERR(EVRC_UNSUPPORTED_ENCODE_OUTPUT,	14453,	"The encoding output object is invalid",
DEF_ERR(EVRC_STREAMVRP_CTRL_CHANNEL_FAILED,	14454,	"The VRP control channel failed to be started during recording",
DEF_ERR(EVRC_VRC_RECORD_FAILED,	14455,	"The recording process failed to be started",
DEF_ERR(EVRC_INVALID_INNER_STATE,	14456,	"Recording is not allowed in the status",
DEF_ERR(EVRC_WORKNO_MISMATCH,	14457,	"The agent ID is mismatched",
DEF_ERR(EVRC_INVALID_RECORD_VRP_ADDR,	14458,	"The recording process failed to be started because the IP address of the VRP is invalid",
DEF_ERR(EVRC_SEND_HANDSHAKE_WITH_CCS_TIMEOUT,	14459,	"The handshake between the VRC and the CCS timed out",
DEF_ERR(EVRC_HANDSHAKE_STREMR_CONTROL_TIMEOUT,	14460,	"The handshake between the VRC and the VRP recording control timed out",
DEF_ERR(EVRC_HANDSHAKE_STREAM_TASK_TIMEOUT,	14461,	"The handshake between the VRC and the CCS recording task timed out",
DEF_ERR(EVRC_MANAGEVRP_INFO_ACK_IP_INVALID,	14462,	"The IP address of the management VRP failed to be obtained",
DEF_ERR(EVRC_SELF_IP_INVALID,	14463,	"The local IP address is invalid",
DEF_ERR(EVRC_SELF_PORT_INVALID,	14464,	"The local port is invalid",
DEF_ERR(EVRC_FPS_OUT_OF_RANGE,	14465,	"The FPS value is invalid",
DEF_ERR(EVRC_EXIST_INVALID_IP_IN_ENTRY_VRP_LIST,	14466,	"An invalid IP address exists in the entry VRP list",
DEF_ERR(EVRC_MISSING_LEFT_BRACKET,	14467,	"A left bracket is missing behind the IP address",
DEF_ERR(EVRC_EXPECT_LEFT_BRACKET,	14468,	"A left bracket must follow behind the IP address",
DEF_ERR(EVRC_MISSING_PORT,	14469,	"The port number is missing",
DEF_ERR(EVRC_INVALID_PORT,	14470,	"The port number field is invalid",
DEF_ERR(EVRC_PORT_OUT_OF_RANGE,	14471,	"The port number is out of range",
DEF_ERR(EVRC_INVALID_PORTIN_ENTRY_VRP_LIST,	14472,	"The port number field is invalid",
DEF_ERR(EVRC_MISSING_RIGHT_BRACKET,	14473,	"A right bracket is missing behind the port number",
DEF_ERR(EVRC_EXPECT_RIGHT_BRACKET,	14474,	"The port number must be followed by a right bracket",
DEF_ERR(EVRC_MISSING_COMMA_BETWEEN_ADDR,	14475,	"Delimiting commas are missing between the multiple addresses",
DEF_ERR(EVRC_NONE_VALID_VRP_ADDR_EXIST,	14476,	"There is no valid entry VRP address",
DEF_ERR(EVRC_ENTRY_VRP_LIST_TOO_LONG,	14477,	"The entry VRP list parameter is too long",
DEF_ERR(EVRC_INVALID_ENTRY_VRP_IP_LIST,	14478,	"The entry VRP address list is invalid",
DEF_ERR(EVRC_CONNECTID_INVALID,	14479,	"The CONNECTID is invalid",
DEF_ERR(EVRC_UNINITED_MUTEX_FUNCTION,	14480,	"The audio and video combination module (function) has not yet been initialized",
DEF_ERR(EVRC_LOAD_AUDIO_VIDEO_DLL_ERROR,	14481,	"The dynamic libraries of audios and videos failed to be loaded",
DEF_ERR(EVRC_LOAD_AUDIO_VIDEO_FUN_ERROR,	14482,	"The interface functions of the dynamic libraries of audios and videos failed to be loaded",
DEF_ERR(EVRC_TOO_MANY_ENTRY_VRP_ADDR,	14483,	"There are too many entry VRPs (at most five VRPs are allowed)",
DEF_ERR(EVRC_RUN_DISPATCH_FAILED,	14484,	"The Dispatch object failed to be run",
DEF_ERR(EVRC_INIT_DISPATCH_FAILED,	14485,	"The Dispatch object failed to be initialized",

DEF_ERR(EVRC_DEST_MODULE_NOT_EXIST,	14486,	"The destination module does not exist",
DEF_ERR(EVRC_MESSAGE_FULL,	14487,	"The message queue is full",
DEF_ERR(EVRC_TURN_SELECTOR_FAILED,	14488,	"The connection failed to be transferred to the new selector",
DEF_ERR(EVRC_INVALID_NOTIFY_MESSAGE,	14489,	"The monitoring manager failed to be created",
DEF_ERR(EVRC_HANDSHAKE_STREEM_CONTROL_SEND,	14490,	"The handshake with the recording control failed to be initiated",
DEF_ERR(EVRC_HANDSHAKE_STREEM_TASK_SEND,	14491,	"The handshake with the recording task failed to be initiated",
DEF_ERR(EVRC_GET_SELF_IP_ERROR,	14492,	"An error occurred when getting own IP address",
DEF_ERR(EVRC_WINDOWS_NONE,	14493,	"The window is invalid",
DEF_ERR(EVRC_AGENTMGR_IS_CREATED_OR_NOT_DESTROYED,	14494,	"The AgentMgr object exists or is not yet destroyed",
DEF_ERR(EVRC_INVALID_DISPLAY_WINDOW,	14495,	"The display window is invalid",
DEF_ERR(EVRC_ALLOC_DIALOG_FAILED,	14496,	"Dialog box resources failed to be allocated",
DEF_ERR(EVRC_PARAMETER_INVALID,	14497,	"The parameter is invalid",
DEF_ERR(EVRC_ENCODE_PREPROCESS_PARAMS_FAILED,	14498,	"The encoder preprocessing parameters failed to be set",
DEF_ERR(EVRC_OTHER_ENCODEOUTPUT_HAS_ATTACH,	14499,	"Other EncodeOutput has been attached",
DEF_ERR(EVRC_INVALID_IP,	14500,	"The IP address is invalid",
DEF_ERR(EVRC_PLAY_BACK_DLG_USED,	14501,	"Playing video ...",
DEF_ERR(EVRC_QC_NOT_EXIST,	14502,	"The QC object does not exist",
DEF_ERR(EVRC_AGENT_NOT_EXIST,	14503,	"The agent object does not exist",
DEF_ERR(EVRC_QC_EXIST,	14504,	"The QC object exists",
DEF_ERR(EVRC_AGENT_EXIST,	14505,	"The agent object exists",
DEF_ERR(EVRC_SELF_ADDRESS_NOT_USABLE,	14506,	"The specified address is unavailable, and probably the port number is already occupied or the IP address is unavailable",
DEF_ERR(EVRC_INVALID_AUDIO_VIDEO_PARAM,	14507,	"The audio and video synchronization parameter is invalid",
DEF_ERR(EVRC_BEYOND_MAX_MONITOR_NUM,	14508,	"The maximum number of screens supported by the agent for screen inspection has been exceeded",
DEF_ERR(EVRP_ILLEGAL_TOKEN,	14304,	"Invalid token."
DEF_ERR(EVRP_ILLEGAL_VRC,	14261,	"Unauthorized client"
};		

Parent topic: [Data Reference](#)

AgentOther_PhoneRelease (Phone in On-Hook State)

Event Description

This event indicates that the phone of an agent is in the on-hook state.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
phoneState	int	Indicates the release cause. 2 : hang-up by the agent. 3 : hang-up by the platform.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentOther_PhoneRelease", "workNo": "20012", "content": {"phoneState": 3}}}</pre>
----------------------------	---

AgentState_Ready (Idle)

Event Description

This event indicates that an agent becomes idle.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentState_Ready","workNo":"49997","content":null}}</pre>
----------------------------	--

Call Types

Table 1 Call types

Value	Description
0	Common incoming call
6	Internal call
7	Common outgoing call
40	Reserved outgoing call
41	Preemptive outgoing call
43	Predictive outgoing call
44	Previewed outgoing call
45	Reserved callback
51	Call for internal help during two-party conversation
52	Call for internal help during three-party conversation
53	Multi-party call

AgentMediaEvent_PausePlayDone (Recording Playback Paused)

Event Description

This event indicates that recording playback is paused.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentMediaEvent_PausePlayDone", "workNo": "49999", "content": null}}</pre>
----------------------------	--

AgentEvent_ReleaseRequest (Request Release Events)

Event Description

This event indicates that the call is released on the agent side. The call is hung up either by the customer or the agent or is released due to platform reasons.

NOTE

This event is applicable only to the ECC scenario.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_ReleaseRequest","workNo":"20011","content":{"callId":"1477467960-16777237"}}</pre>
----------------------------	--

AgentOther_PhoneOffhook (Phone in Off-Hook State)

Event Description

This event indicates that the phone of an agent is in the off-hook state.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentOther_PhoneOffhook","workNo":"49999","content":null}}</pre>
----------------------------	---

AgentState_Busy (Talking)

Event Description

This event indicates that an agent is making a call.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"AgentState_Busy","workNo":"1010","content":null}}</pre>

AgentOther_PhoneAlerting (Phone in Ringing State)

Event Description

This event indicates that the phone of an agent is ringing.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentOther_PhoneAlerting","workNo":"4999","content":null}}</pre>
----------------------------	---

AgentEvent_Call_Release (Agent Exiting a Call)

Event Description

This event indicates that an agent exits a call with the specified **callId**.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the unique call ID (CallId).

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_Call_Release", "workNo": "49999", "content": "1456402370-7"}}</pre>
----------------------------	--

AgentEvent_Customer_Release (User Exiting a Call)

Event Description

This event indicates that a user exits a call with the specified **callId**.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
number	string	Indicates the phone number of the party who releases the call.
callId	string	Indicates the unique call ID.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_Customer_Release", "workNo": "49999", "content": {"callId": "1456404171-43", "number": "70093"}}</pre>
----------------------------	--

AgentEvent_SuccTransResult (Notifying the Success Transfer Result)

Event Description

This event indicates that an agent successfully invokes the transfer interface for success transfer in the voice or text transfer scenario. The event is not supported for an external call transfer.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
callId	string	Indicates the unique call ID.
result	int	Indicates the success transfer result. 0 : Succeed. Other values: Fail.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_SuccTransResult","workNo":"20011","content":{"result":1,"callId":"1477467960-16777237"}}</pre>
----------------------------	--

AgentMediaEvent_Play (Recording Playback Started)

Event Description

This event indicates that recording playback is started.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentMediaEvent_Play","workNo":"49999","content":null}}</pre>
----------------------------	--

AgentEvent_Inside_Call_Fail (Making an Internal Call Unsuccessfully)

Event Description

This event indicates that the internal call initiated by the agent fails.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the unique call ID (CallId).

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_Inside_Call_Fail", "workNo": "49999", "content": "1456402370-7"}}</pre>
----------------------------	--

AgentEvent_Connect_Fail (Failure to Connect to an Agent)

Event Description

This event indicates that connecting to the agent fails.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the unique call ID (CallId).

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_Connect_Fail", "workNo": "49999", "content": "1456402370-7"}}</pre>
----------------------------	--

AgentMediaEvent_Play_Succ (Recording Playback Succeeded)

Event Description

This event indicates that recording playback is successful.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json; charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentMediaEvent_Play_Succ", "workNo": "49999", "content": null}}</pre>
----------------------------	--

AgentMediaEvent_StopPlayDone (Recording Playback Stopped)

Event Description

This event indicates that recording playback is stopped.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: 0: Succeed - Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
cause	int	Indicates the cause for stopping the recording playback 0: normally stopped after playback 1: proactively stopped by an agent 2: stopped due to recording playback failure

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentMediaEvent_StopPlayDone","workNo":"49999","content":{"cause":0}}</pre>
----------------------------	--

AgentMediaEvent_Play_Fail (Recording Playback Failed)

Event Description

This event indicates that recording playback has failed.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentMediaEvent_Play_Fail","workNo":"49999","content":null}}</pre>
----------------------------	---

AgentState_Work (Working)

Event Description

This event indicates that an agent enters the work state.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Reserved.

Event Example

Example Type	Reference Format
Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 {"message":"","retcode":"0","event":{"eventType":"AgentState_Work","workNo":"1010","content":null}}</pre>

AgentMediaEvent_JumpPlayDone (Recording Playback Fast-Forwarded)

Event Description

This event indicates that recording playback is fast-forwarded.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Null.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentMediaEvent_JumpPlayDone","workNo":"49999","content":null}}</pre>
----------------------------	--

AgentEvent_Customer_Alerting (Customer Ringing)

Event Description

This event indicates that the phone of the customer associated with the agent is ringing.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2 .

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
otherPhoneWorkno	string	Indicates the work ID of the agent whose phone is ringing.
otherPhone	string	Indicates the phone number of the party who phone is ringing or the work ID of the agent whose phone is ringing.
callid	string	Indicates the unique call ID.
type	string	Indicates the media type of a call, either an assistant call or a main call.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message": "", "retcode": "0", "event": {"eventType": "AgentEvent_Customer_Alerting", "workNo": "49999", "content": {"callid": "1456401416-3", "otherPhoneWorkno": "", "otherPhone": "70092", "type": "main"}}</pre>
----------------------------	--

AgentEvent_Talking (Turning to the Talking State)

Event Description

This event indicates that the voice call of an agent enters the talking state.

Event Message

Table 1 Event parameter description

Parameter	Data Type	Description
Response Header		
Content-Type	string	The fixed value is application/json; charset=UTF-8 .
Response Body		
message	string	Indicates the message description.
retcode	string	Indicates the error code. The options are as follows: • 0: Succeed • Other values: Fail
event	map	Indicates the event object. For the parameter description of event , see Table 2

Table 2 Parameter description of event

Parameter	Data Type	Description
eventType	string	Indicates the event type.
workNo	string	Indicates the work ID of an agent.
content	object	Indicates the event content. For the parameter description of content , see Table 3 .

Table 3 Parameter description of content

Parameter	Data Type	Description
called	string	Indicates the called number.
caller	string	Indicates the calling number.
callid	string	Indicates the unique call ID.
type	string	Indicates the media type of a call, either an assistant call or a main call.
feature	string	Indicates the type of a call. See Table 1 .
mediaAbility	string	Indicates the media capability, where 1 indicates audio, 2 indicates video, and 3 indicates audio and video.

Event Example

Example of an event packet	<pre>HTTP/1.1 200 OK Content-Type: application/json;charset=UTF-8 Accept-Ranges: bytes Date: Thu, 16 Feb 2017 11:04:14 GMT {"message":"","retcode":"0","event":{"eventType":"AgentEvent_Talking","workNo":"49999","content":{"caller":"10086","callid":"1456401416-3","called":"70092","feature":"7","type":"main","mediaAbility":"1"}}</pre>
----------------------------	---

Agent Status

Table 1 Agent status description

Value	Description
0	Not sign-in
1	Idle
2	Preoccupied
3	Occupied
4	Answering
5	Talk
6	Adjust after call
7	Busy
8	Resting
9	Study

Copyright © Chengdu TD-Tech Co., Ltd.