1

```
\heartheinting\token list\rangle parameter]
\footline [\langle token list\rangle parameter]
```

These parameters contain, respectively, the current headline (header) and the current footline (footer). The plain TEX output routine places the headline at the top of each page and the footline at the bottom of each page. The default headline is empty and the default footline is a centered page number.

The headline and footline should both be as wide as $\nesuremath{\verb|hfil|}$, p. ' $\nesuremath{\verb|hfil|}$ ', for this if necessary). You should always include a font-setting command in these lines, since the current font is unpredictable when T_EX is calling the output routine. If you don't set the font explicitly, you'll get whatever font T_EX was using when it broke the page.

You shouldn't try to use \headline or \footline to produce multiline headers or footers. Although TeX won't complain, it will give you something that's very ugly. See page 'bighead' for a method of creating multiline headers or footers.

Example:

Example:

 $\mbox{\ensuremath{\mbox{\%}}}$ Produce the page number in ten-point italic at

% the outside bottom corner of each page.