1

## \strut

This command produces a box whose width is zero and whose height (8.5pt) and depth (3.5pt) are those of a more or less typical line of type in cmr10, the default plain TEX font. Its main use is in forcing lines to have the same height when you've disabled TEX's interline glue with \offinterlineskip or a similar command, e.g., when you're constructing an alignment. If the natural height of a line is too short, you can bring it up to standard by including a \strut in the line. The strut will force the height and depth of the line to be larger, but it won't print anything or consume any horizontal space.

If you're setting type in a font that's bigger or smaller than cmr10, you should redefine \strut for that context.

## Example: