# 实验 RIP 路由协议基本配置

#### 【实验名称】

RIP 路由协议基本配置。

#### 【实验目的】

掌握在路由器上如何配置 RIP 路由协议。

## 【背景描述】

假设在校园网在地理上分为 2 个区域,每个区域内分别有一台路由器连接了 2 个子网,需要将两台路由器通过以太网链路连接在一起并进行适当的配置,以实现这 4 个子网之间的互联互通。为了在未来每个校园区域扩充子网数量的时候,管理员不需要同时更改路由器的配置,计划使用 RIP 路由协议实现子网之间的互通。

#### 【需求分析】

两台路由器通过快速以太网端口连接在一起,每个路由器上设置 2 个 Loopback 端口模拟子网,在所有端口运行 RIP 路由协议,实现所有子网间的互通。

#### 【实验拓扑】




图 7-1 实验拓扑图

### 【实验设备】

路由器 2台

#### 【预备知识】

路由器的工作原理和基本配置方法,距离矢量路由协议,RIP工作原理和配置方法

#### 【实验原理】

RIP(Routing Information Protocols,路由信息协议)是应用较早、使用较普遍的 IGP(Interior Gateway Protocol,内部网关协议),适用于小型同类网络,是典型的距离矢量(distance-vector)协议。

RIP 协议以跳数做为衡量路径开销的, RIP 协议里规定最大跳数为 15。

RIP 在构造路由表时会使用到 3 种计时器: 更新计时器、无效计时器、刷新计时器。它让每台路由器周期性地向每个相邻的邻居发送完整的路由表。路由表包括每个网络或子网的信息,以及与之相关的度量值。

### 【实验步骤】

### 第一步:配置两台路由器的主机名、接口 IP 地址

RSR20#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

RSR20(config)#hostname RouterA

RouterA(config)#

RouterA(config)#interface fastEthernet 0/0

RouterA(config-if)#ip address 192.168.1.1 255.255.255.0

RouterA(config-if)#no shutdown

RouterA(config-if)#exit

RouterA(config)#

RouterA(config)#interface loopback 0

RouterA(config-if)#Aug 15 23:46:32 RouterA %7:%LINE PROTOCOL CHANGE:

Interface Loopback 0, changed state to UP

RouterA(config-if)#ip address 172.16.1.1 255.255.255.0

RouterA(config-if)#exit

RouterA(config)#

RouterA(config)#interface loopback 1

RouterA(config-if)#Aug 15 23:47:00 RouterA %7:%LINE PROTOCOL CHANGE:

Interface Loopback 1, changed state to UP

RouterA(config-if)#ip address 172.16.2.1 255.255.255.0

RouterA(config-if)#exit

RSR20#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

RSR20(config)#hostname RouterB

RouterB(config)#

RouterB(config)#interface fastEthernet 0/0

RouterB(config-if)#ip address 192.168.1.2 255.255.255.0

RouterB(config-if)#no shutdown

RouterB(config-if)#exit

RouterB(config)#

RouterB(config)#interface loopback 0

RouterB(config-if)#Aug 8 21:00:00 RouterB %7:%LINE PROTOCOL CHANGE:

Interface Loopback 0, changed state to UP

RouterB(config-if)#ip address 10.1.1.1 255.255.255.0

RouterB(config-if)#exit

RouterB(config)#

RouterB(config)#interface loopback 1

RouterB(config-if)#Aug 8 21:00:28 RouterB %7:%LINE PROTOCOL CHANGE:

Interface Loopback 1, changed state to UP

RouterB(config-if)#ip address 10.2.2.1 255.255.255.0

### RouterB(config-if)#exit

## 第二步:在两台路由器上配置 RIP 路由协议

RouterA(config)#router rip

RouterA(config-router)#network 192.168.1.0

RouterA(config-router)#network 172.16.1.0

RouterA(config-router)#exit

RouterB(config)#router rip

RouterB(config-router)#network 192.168.1.0

RouterB(config-router)#network 10.0.0.0

RouterB(config-router)#exit

### 第三步: 查看 RIP 配置信息,路由表

### RouterA#show ip route

Codes: C - connected, S - static, R - RIP B - BGP

O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

\* - candidate default

### Gateway of last resort is no set

## R 10.0.0.0/8 [120/1] via 192.168.1.2, 00:00:17, FastEthernet 0/0

- C 172.16.1.0/24 is directly connected, Loopback 0
- C 172.16.1.1/32 is local host.
- C 172.16.2.0/24 is directly connected, Loopback 1
- C 172.16.2.1/32 is local host.
- C 192.168.1.0/24 is directly connected, FastEthernet 0/0
- C 192.168.1.1/32 is local host.

### RouterA#

#### Routing Protocol is "rip"

#### Sending updates every 30 seconds, next due in 21 seconds

## Invalid after 180 seconds, flushed after 120 seconds

Outgoing update filter list for all interface is: not set

Incoming update filter list for all interface is: not set

Default redistribution metric is 1

Redistributing:

Default version control: send version 1, receive any version

Interface	Send	Recv	Key-chain
FastEthernet 0/0	1	1 2	
Loopback 0	1	1 2	
Loopback 1	1	1 2	

Routing for Networks:

172.16.0.0

192.168.1.0

Distance: (default is 120)

RouterA#

## RouterB#show ip route

Codes: C - connected, S - static, R - RIP B - BGP

O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

\* - candidate default

### Gateway of last resort is no set

C 10.1.1.0/24 is directly connected, Loopback 0

C 10.1.1.1/32 is local host.

C 10.2.2.0/24 is directly connected, Loopback 1

C 10.2.2.1/32 is local host.

R 172.16.0.0/16 [120/1] via 192.168.1.1, 00:00:12, FastEthernet 0/0

C 192.168.1.0/24 is directly connected, FastEthernet 0/0

C 192.168.1.2/32 is local host.

#### RouterA#show ip rip database

10.0.0.0/8 auto-summary

10.0.0.0/8

[1] via 192.168.1.2 FastEthernet 0/0 00:09

172.16.0.0/16 auto-summary

172.16.1.0/24

[1] directly connected, Loopback 0

172.16.2.0/24

[1] directly connected, Loopback 1

192.168.1.0/24 auto-summary

192.168.1.0/24

[1] directly connected, FastEthernet 0/0

### RouterA#show ip rip interface

FastEthernet 0/0 is up, line protocol is up

**Routing Protocol: RIP** 

Receive RIPv1 and RIPv2 packets

Send RIPv1 packets only

Passive interface: Disabled

Split horizon: Enabled

V2 Broadcast: Disabled Multicast registe: Registed Interface Summary Rip:

Not Configured IP interface address:

192.168.1.1/24

FastEthernet 0/1 is down, line protocol is down

RIP is not enabled on this interface

Null 0 is up, line protocol is up

RIP is not enabled on this interface

## Loopback 0 is up, line protocol is up

**Routing Protocol: RIP** 

Receive RIPv1 and RIPv2 packets

Send RIPv1 packets only

Passive interface: Disabled **Split horizon: Enabled**V2 Broadcast: Disabled

Multicast registe: Registed

Interface Summary Rip:

Not Configured IP interface address:

172.16.1.1/24

### Loopback 1 is up, line protocol is up

**Routing Protocol: RIP** 

Receive RIPv1 and RIPv2 packets

**Send RIPv1 packets only** Passive interface: Disabled

**Split horizon: Enabled** V2 Broadcast: Disabled

Multicast registe: Registed Interface Summary Rip:

Not Configured IP interface address:

172.16.2.1/24

#### RouterB#show ip rip

Routing Protocol is "rip"

Sending updates every 30 seconds, next due in 21 seconds

## Invalid after 180 seconds, flushed after 120 seconds

Outgoing update filter list for all interface is: not set Incoming update filter list for all interface is: not set

Default redistribution metric is 1

Redistributing:

Default version control: send version 1, receive any version

Interface Send Recv Key-chain

FastEthernet 0/0 1 1 2
Loopback 0 1 1 2
Loopback 1 1 1 2

Routing for Networks:

10.0.0.0 192.168.1.0

Distance: (default is 120)

#### RouterB#show ip rip database

10.0.0.0/8 auto-summary

10.1.1.0/24

[1] directly connected, Loopback 0

10.2.2.0/24

[1] directly connected, Loopback 1

172.16.0.0/16 auto-summary

172.16.0.0/16

[1] via 192.168.1.1 FastEthernet 0/0 00:08

192.168.1.0/24 auto-summary

192.168.1.0/24

[1] directly connected, FastEthernet 0/0

### RouterB#show ip rip interface

FastEthernet 0/0 is up, line protocol is up

**Routing Protocol: RIP** 

Receive RIPv1 and RIPv2 packets

Send RIPv1 packets only

Passive interface: Disabled

**Split horizon: Enabled** V2 Broadcast: Disabled

Multicast registe: Registed

Interface Summary Rip:

Not Configured

IP interface address:

192.168.1.2/24

FastEthernet 0/1 is down, line protocol is down

RIP is not enabled on this interface

Null 0 is up, line protocol is up

RIP is not enabled on this interface

Loopback 0 is up, line protocol is up

**Routing Protocol: RIP** 

Receive RIPv1 and RIPv2 packets

Send RIPv1 packets only

Passive interface: Disabled

Split horizon: Enabled

V2 Broadcast: Disabled Multicast registe: Registed Interface Summary Rip:

Not Configured IP interface address:

10.1.1.1/24

## Loopback 1 is up, line protocol is up

**Routing Protocol: RIP** 

Receive RIPv1 and RIPv2 packets

**Send RIPv1 packets only**Passive interface: Disabled

**Split horizon: Enabled** V2 Broadcast: Disabled Multicast registe: Registed

Interface Summary Rip:

Not Configured IP interface address:

10.2.2.1/24

#### 第四步:测试网络连通性

### RouterA#ping 10.1.1.1

Sending 5, 100-byte ICMP Echoes to 10.1.1.1, timeout is 2 seconds:

< press Ctrl+C to break >

!!!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms

## RouterA#ping 10.2.2.1

Sending 5, 100-byte ICMP Echoes to 10.2.2.1, timeout is 2 seconds:

< press Ctrl+C to break >

!!!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 1/2/10 ms

## RouterB#ping 172.16.1.1

Sending 5, 100-byte ICMP Echoes to 172.16.1.1, timeout is 2 seconds:

< press Ctrl+C to break >

!!!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms

## RouterB#ping 172.16.2.1

Sending 5, 100-byte ICMP Echoes to 172.16.2.1, timeout is 2 seconds:

< press Ctrl+C to break >

!!!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms

#### 第五步:用 debug 命令观察路由器接收和发生路由更新的情况

下面是一个完整的 RIP 路由器接收更新和发送更新的过程,从中可以看到 RouterB 接收到了 RouterA 发送的更新,其中包含一条路由信息 172.16.0.0(可以看到水平分割原则的作用),然后刷新了路由表。

RouterB 本身发送的更新报文则在 Fa0/0、Lo0 和 Lo1 三个端口发出,采用广播的方式,广播地址分别为 192.168.1.255, 10.1.1.255, 10.2.2.255, 使用 UDP 的 520 端口。在水平分割的原则下,每个端口发送的路由信息均不相同。

#### RouterB#debug ip rip

Aug 8 21:06:08 RouterB %7: [RIP] RIP recveived packet, sock=2125 src=192.168.1.1 len=24

Aug 8 21:06:08 RouterB %7: [RIP] Cancel peer remove timer

Aug 8 21:06:08 RouterB %7:[RIP] Peer remove timer shedule...

Aug 8 21:06:08 RouterB %7: route-entry: family 2 ip 172.16.0.0 metric 1

Aug 8 21:06:08 RouterB %7: [RIP] Received version 1 response packet

Aug 8 21:06:08 RouterB %7: [RIP] Translate mask to 16

Aug 8 21:06:08 RouterB %7: [RIP] Old path is: nhop=192.168.1.1 routesrc=192.168.1.1 intf=1

Aug 8 21:06:08 RouterB %7: [RIP] New path is: nhop=192.168.1.1 routesrc=192.168.1.1

### Aug 8 21:06:08 RouterB %7: [RIP] [172.16.0.0/16] RIP route refresh!

Aug 8 21:06:08 RouterB %7: [RIP] [172.16.0.0/16] RIP distance apply from 192.168.1.1!

Aug 8 21:06:08 RouterB %7: [RIP] [172.16.0.0/16] ready to refresh kernel...

Aug 8 21:06:08 RouterB %7: [RIP] NSM refresh: IPv4 RIP Route 172.16.0.0/16 distance=120 metric=1 nexthop\_num=1 distance=120 nexhop=192.168.1.1 ifindex=1

Aug 8 21:06:08 RouterB %7: [RIP] [172.16.0.0/16] cancel route timer

Aug 8 21:06:08 RouterB %7: [RIP] [172.16.0.0/16] route timer schedule...

Aug 8 21:06:23 RouterB %7: [RIP] Output timer expired to send reponse

Aug 8 21:06:23 RouterB %7: [RIP] Prepare to send BROADCAST response...

Aug 8 21:06:23 RouterB %7: [RIP] Building update entries on FastEthernet 0/0

Aug 8 21:06:23 RouterB %7: network 10.0.0.0 metric 1

Aug 8 21:06:23 RouterB %7: [RIP] Send packet to 192.168.1.255 Port 520 on FastEthernet 0/0

Aug 8 21:06:23 RouterB %7: [RIP] Prepare to send BROADCAST response...

Aug 8 21:06:23 RouterB %7: [RIP] Building update entries on Loopback 0

Aug 8 21:06:23 RouterB %7: network 10.2.2.0 metric 1

Aug 8 21:06:23 RouterB %7: network 172.16.0.0 metric 2

Aug 8 21:06:23 RouterB %7: network 192.168.1.0 metric 1

Aug 8 21:06:23 RouterB %7: [RIP] **Send packet to 10.1.1.255 Port 520 on Loopback 0** 

Aug 8 21:06:23 RouterB %7: [RIP] Prepare to send BROADCAST response...

```
Aug 8 21:06:23 RouterB %7: [RIP] Building update entries on Loopback 1
```

 Aug
 8 21:06:23 RouterB %7:
 network 10.1.1.0 metric 1

 Aug
 8 21:06:23 RouterB %7:
 network 172.16.0.0 metric 2

 Aug
 8 21:06:23 RouterB %7:
 network 192.168.1.0 metric 1

Aug 8 21:06:23 RouterB %7: [RIP] Send packet to 10.2.2.255 Port 520 on

Loopback 1

Aug 8 21:06:23 RouterB %7: [RIP] Schedule response send timer

#### 【注意事项】

- 1、配置 RIP 的 Network 命令时只支持 A、B、C 的主网络号,如果写入子网则自动转为主网络号。
- 2、No auto-summary 功能只有在 RIPv2 支持。

### 【参考配置】

### RouterA#show running-config

```
Building configuration...
Current configuration: 612 bytes
!
version RGNOS 10.1.00(4), Release(18443)(Tue Jul 17 20:50:30 CST 2007 -ubu1server)
hostname RouterA
interface FastEthernet 0/0
 ip address 192.168.1.1 255.255.255.0
 duplex auto
 speed auto
interface FastEthernet 0/1
 duplex auto
 speed auto
interface Loopback 0
 ip address 172.16.1.1 255.255.255.0
interface Loopback 1
 ip address 172.16.2.1 255.255.255.0
!
router rip
 network 172.16.0.0
 network 192.168.1.0
line con 0
```

```
line aux 0
line vty 0 4
login
!
```

## RouterB#show running-config

```
Building configuration...
Current configuration: 606 bytes
!
version RGNOS 10.1.00(4), Release(18443)(Tue Jul 17 20:50:30 CST 2007 -ubu1server)
hostname RouterB
interface FastEthernet 0/0
 ip address 192.168.1.2 255.255.255.0
 duplex auto
 speed auto
!
interface FastEthernet 0/1
 duplex auto
 speed auto
!
interface Loopback 0
 ip address 10.1.1.1 255.255.255.0
interface Loopback 1
 ip address 10.2.2.1 255.255.255.0
!
router rip
 network 10.0.0.0
 network 192.168.1.0
!
line con 0
line aux 0
line vty 04
 login
!
end
```