
. How do you reset your login password to Ubuntu Linux if you forget it?

To reset a Ubuntu login password, follow these steps:

BOOT INTO RECOVERY MODE: Turn on your Ubuntu machine and press and hold the Shift key to enter the GRUB boot menu. Select "Advanced options for Ubuntu" and then select the recovery mode option.



ENTER INTO ROOT MODE: When the recovery menu appears, select the option that says "root - Drop to root shell prompt". This will give you root access to the system.

GNU GRUB version 2.06


```
Ubuntu, with Linux 5.15.0-60-generic (recovery mode)

*Ubuntu, with Linux 5.15.0-25-generic
Ubuntu, with Linux 5.15.0-25-generic (recovery mode)

Ubuntu, with Linux 5.15.0-25-generic (recovery mode)
```

Use the ↑ and ↓ keys to select which entry is highlighted.
Press enter to boot the selected OS, `e' to edit the commands
before booting or `c' for a command-line. ESC to return previous
menu.

```
2.086358] rcu: Hierarchical SRCU implementation.
2.0913181 NMI watchdog: Perf NMI watchdog permanently disabled
2.094819] smp: Bringing up secondary CPUs ...
2.096900] x86: Booting SMP configuration:
2.0982741 ... node #0, CPUs: #1
0.954252] Disabled fast string operations
0.954252] smpboot: CPU 1 Converting physical 2 to logical package 1
0.954252] smpboot: CPU 1 Converting physical 0 to logical die 1
2.102807] smp Brought up 1 node, 2 CPUs
2.110271] smpboot: Max logical packages: 128
2.1142701 smpboot: Total of 2 processors activated (7967.99 BogoMIPS)
2.118269] devtmpfs: initialized
2.1199001 x86/mm: Memory block size: 128MB
2.122539] ACPI: PM: Registering ACPI NVS region [Mem 0xbb6ff000-0xbb6fffff]
(4096 bytes)
2.1257861 clocksource: jiffies: mask: 0xffffffff max_cycles: 0xffffffff, max_idle_ns: 7645041785100000 ns
2.1264821 futex hash table entries: 32768 (order: 9, 2097152 bytes, linear)
2.1294661 pinctrl core: initialized pinctrl subsystem
2.1310341 PM: RTC time: 11:30:16, date: 2023-02-21
2.1345181 NET: Registered PF_NETLINK/PF_ROUTE protocol family
2.1380901 DMA: preallocated 512 KiB GFP_KERNEL!GFP_DMA pool for atomic allocations
2.1383671 DMA: preallocated 512 KiB GFP_KERNEL!GFP_DMA pool for atomic allocations
2.1414991 DMA: preallocated 512 KiB GFP_KERNEL!GFP_DMA pool for atomic allocations
```



REMOUNT FILE SYSTEM: In the root shell prompt, type the following command to remount the file system in read/write mode:

mount -rw -o remount /

ls /home [verify user name]


Reset the password: Next, type the following command to reset the password for a specific user (replace "username" with the username of the user whose password you want to reset)

passwd username

Enter new password: You will be prompted to enter a new password for the user. Type a new password and then confirm it when prompted.

```
root@mpnlab:~# mount –rw –o remount /
root@mpnlab:~# ls /home
mpn
root@mpnlab:~# passwd mpn
New password:
Retype new password:
passwd: password updated successfully
root@mpnlab:~#
```

Reboot/resume normal boot: After the password has been reset, type the following command to reboot the system/resume normal boot



Reboot/Resume with normal boot

```
mpnlab login: mpn
Password:
Welcome to Ubuntu 22.04 LTS (GNU/Linux 5.15.0-60-generic x86_64)

* Documentation: https://help.ubuntu.com
* Management: https://landscape.canonical.com
* Support: https://ubuntu.com/advantage

System information as of Tue Feb 21 11:38:21 AM UTC 2023

System load: 0.65283203125 Processes: 203
Usage of /: 37.9% of 9.75GB Users logged in: 0
Memory usage: 11% IPv4 address for ens33: 192.168.83.129
Swap usage: 0%

86 updates can be applied immediately.
To see these additional updates run: apt list --upgradable
Failed to connect to https://changelogs.ubuntu.com/meta-release-lts. Check your Internet connection or proxy settings

Last login: Tue Feb 21 11:19:03 UTC 2023 on tty1
mpn@mpnlab:~$ __
```

Once your system reboots, you should be able to log in with the new password for the user account you just updated.